

Qwt User's Guide Reference Manual

5.2.0

Generated by Doxygen 1.5.0

Sun Mar 22 16:44:05 2009

Contents

1	Qwt - Qt Widgets for Technical Applications	1
2	Qwt User's Guide Hierarchical Index	3
3	Qwt User's Guide Class Index	6
4	Qwt User's Guide File Index	9
5	Qwt User's Guide Page Index	12
6	Qwt User's Guide Class Documentation	12
7	Qwt User's Guide File Documentation	398
8	Qwt User's Guide Page Documentation	400

1 Qwt - Qt Widgets for Technical Applications

The Qwt library contains GUI Components and utility classes which are primarily useful for programs with a technical background. Beside a 2D plot widget it provides scales, sliders, dials, compasses, thermometers, wheels and knobs to control or display values, arrays, or ranges of type double.

1.1 License

Qwt is distributed under the terms of the [Qwt License, Version 1.0](#).

1.2 Platforms

Qwt 5.x might be usable in all environments where you find [Qt](#). It is compatible with Qt 3.3.x and Qt 4.x, but the documentation is generated for Qt 4.x.

1.3 Screenshots

- [Curve Plots](#)
- [Scatter Plot](#)
- [Spectrogram, Contour Plot](#)
- [Histogram](#)
- [Dials, Compasses, Knobs, Wheels, Sliders, Thermos](#)

Screenshots are only available in the HTML docs.

1.4 Downloads

Stable releases, prereleases and snapshots are available at the [Qwt project page](#).

For getting a snapshot with all bugfixes for the latest 5.2 release:

```
svn co https://qwt.svn.sourceforge.net/svnroot/qwt/branches/qwt-5.2
```

For getting a development snapshot from the SVN repository:

```
svn co https://qwt.svn.sourceforge.net/svnroot/qwt/trunk/qwt
```

Qwt doesn't distribute binary packages, but today all major Linux distributors offer one. Note, that these packages often don't include the examples.

1.5 Installation

Have a look at the qwt.pro project file. It is prepared for building dynamic libraries in Win32 and Unix/X11 environments. If you don't know what to do with it, read the file [INSTALL](#) and/or Trolltechs [qmake](#) documentation. Once you have build the library you have to install all files from the lib, include and doc directories.

1.6 Support

- Mailing list

For all kind of Qwt related questions use the [Qwt mailing list](#).

If you prefer newsgroups use the mail to news gateway of [Gmane](#).

- Forum

[Qt Centre](#) is a great resource for Qt related questions. It has a sub forum, that is dedicated to Qwt related questions.

- Individual support

If you are looking for individual support, or need someone who implements your Qwt component/application contact qwt-support@tigertal.de.

1.7 Related Projects

[QwtPolar](#), a polar plot widget.

[QwtPlot3D](#), an OpenGL 3D plot widget.

[QtiPlot](#), data analysis and scientific plotting tool, using [QwtPlot](#).

1.8 Language Bindings

[PyQwt](#), a set of Qwt Python bindings.

[Korundum/QtRuby](#), including a set of Qwt Ruby bindings.

1.9 Donations

Sourceforge offers a [Donation System](#) via PayPal. You can use it, if you like to [support](#) the development of Qwt.

1.10 Credits:

Authors:

Uwe Rathmann, Josef Wilgen (<= Qwt 0.2)

Project admin:

Uwe Rathmann <rathmann@users.sourceforge.net>

2 Qwt User's Guide Hierarchical Index

2.1 Qwt User's Guide Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

QwtAbstractScale	12
QwtKnob	116
QwtSlider	350
QwtThermo	383
QwtAbstractScaleDraw	17
QwtRoundScaleDraw	312
QwtDialScaleDraw	84
QwtScaleDraw	321
QwtArrowButton	40
QwtClipper	43
QwtColorMap	44
QwtAlphaColorMap	32
QwtLinearColorMap	134
QwtCompassRose	54
QwtSimpleCompassRose	348
QwtCurveFitter	66
QwtSplineCurveFitter	361

QwtData	67
QwtArrayData	38
QwtCPointerData	64
QwtPolygonFData	305
QwtDialNeedle	83
QwtCompassMagnetNeedle	51
QwtCompassWindArrow	55
QwtDialSimpleNeedle	86
QwtDoubleInterval	89
QwtDoubleRange	95
QwtAbstractSlider	24
QwtDial	69
QwtAnalogClock	34
QwtCompass	47
QwtKnob	116
QwtSlider	350
QwtWheel	392
QwtCounter	58
QwtDynGridLayout	101
QwtEventPattern	106
QwtPicker	161
QwtPlotPicker	260
QwtPlotZoomer	297
QwtEventPattern::KeyPattern	113
QwtEventPattern::MousePattern	113
QwtIntervalData	114
QwtLegend	120
QwtLegendItemManager	132
QwtPlotItem	232

QwtPlotCurve	209
QwtPlotGrid	226
QwtPlotMarker	252
QwtPlotRasterItem	270
QwtPlotSpectrogram	286
QwtPlotScaleItem	281
QwtPlotSvgItem	294
QwtMagnifier	141
QwtPlotMagnifier	250
QwtMetricsMap	150
QwtPainter	152
QwtPanner	156
QwtPlotPanner	258
QwtPickerMachine	180
QwtPickerClickPointMachine	177
QwtPickerClickRectMachine	178
QwtPickerDragPointMachine	179
QwtPickerDragRectMachine	179
QwtPickerPolygonMachine	182
QwtPlotCanvas	205
QwtPlotDict	224
QwtPlot	185
QwtPlotLayout	242
QwtPlotPrintFilter	267
QwtPlotRescaler	274
QwtRasterData	306
QwtScaleArithmetic	315
QwtScaleDiv	317
QwtScaleEngine	329

QwtLinearScaleEngine	138
QwtLog10ScaleEngine	139
QwtScaleMap	335
QwtScaleTransformation	338
QwtScaleWidget	340
QwtSpline	358
QwtSymbol	363
QwtText	368
QwtTextEngine	377
QwtMathMLTextEngine	148
QwtPlainTextEngine	182
QwtRichTextEngine	310
QwtTextLabel	380
QwtLegendItem	126

3 Qwt User's Guide Class Index

3.1 Qwt User's Guide Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

QwtAbstractScale (An abstract base class for classes containing a scale)	12
QwtAbstractScaleDraw (A abstract base class for drawing scales)	17
QwtAbstractSlider (An abstract base class for slider widgets)	24
QwtAlphaColorMap (QwtAlphaColorMap variies the alpha value of a color)	32
QwtAnalogClock (An analog clock)	34
QwtArrayData (Data class containing two QwtArray<double> objects)	38
QwtArrowButton (Arrow Button)	40
QwtClipper (Some clipping algos)	43
QwtColorMap (QwtColorMap is used to map values into colors)	44
QwtCompass (A Compass Widget)	47
QwtCompassMagnetNeedle (A magnet needle for compass widgets)	51

QwtCompassRose (Abstract base class for a compass rose)	54
QwtCompassWindArrow (An indicator for the wind direction)	55
QwtCounter (The Counter Widget)	58
QwtCPointerData (Data class containing two pointers to memory blocks of doubles)	64
QwtCurveFitter (Abstract base class for a curve fitter)	66
QwtData (QwtData defines an interface to any type of curve data)	67
QwtDial (QwtDial class provides a rounded range control)	69
QwtDialNeedle (Base class for needles that can be used in a QwtDial)	83
QwtDialScaleDraw (A special scale draw made for QwtDial)	84
QwtDialSimpleNeedle (A needle for dial widgets)	86
QwtDoubleInterval (A class representing an interval)	89
QwtDoubleRange (A class which controls a value within an interval)	95
QwtDynGridLayout (Lays out widgets in a grid, adjusting the number of columns and rows to the current size)	101
QwtEventPattern (A collection of event patterns)	106
QwtEventPattern::KeyPattern (A pattern for key events)	113
QwtEventPattern::MousePattern (A pattern for mouse events)	113
QwtIntervalData (Series of samples of a value and an interval)	114
QwtKnob (The Knob Widget)	116
QwtLegend (The legend widget)	120
QwtLegendItem (A legend label)	126
QwtLegendItemManager (Abstract API to bind plot items to the legend)	132
QwtLinearColorMap (QwtLinearColorMap builds a color map from color stops)	134
QwtLinearScaleEngine (A scale engine for linear scales)	138
QwtLog10ScaleEngine (A scale engine for logarithmic (base 10) scales)	139
QwtMagnifier (QwtMagnifier provides zooming, by magnifying in steps)	141
QwtMathMLTextEngine (Text Engine for the MathML renderer of the Qt solutions package)	148
QwtMetricsMap (A Map to translate between layout, screen and paint device metrics)	150
QwtPainter (A collection of QPainter workarounds)	152

QwtPanner (QwtPanner provides panning of a widget)	156
QwtPicker (QwtPicker provides selections on a widget)	161
QwtPickerClickPointMachine (A state machine for point selections)	177
QwtPickerClickRectMachine (A state machine for rectangle selections)	178
QwtPickerDragPointMachine (A state machine for point selections)	179
QwtPickerDragRectMachine (A state machine for rectangle selections)	179
QwtPickerMachine (A state machine for QwtPicker selections)	180
QwtPickerPolygonMachine (A state machine for polygon selections)	182
QwtPlainTextEngine (A text engine for plain texts)	182
QwtPlot (A 2-D plotting widget)	185
QwtPlotCanvas (Canvas of a QwtPlot)	205
QwtPlotCurve (A plot item, that represents a series of points)	209
QwtPlotDict (A dictionary for plot items)	224
QwtPlotGrid (A class which draws a coordinate grid)	226
QwtPlotItem (Base class for items on the plot canvas)	232
QwtPlotLayout (Layout engine for QwtPlot)	242
QwtPlotMagnifier (QwtPlotMagnifier provides zooming, by magnifying in steps)	250
QwtPlotMarker (A class for drawing markers)	252
QwtPlotPanner (QwtPlotPanner provides panning of a plot canvas)	258
QwtPlotPicker (QwtPlotPicker provides selections on a plot canvas)	260
QwtPlotPrintFilter (A base class for plot print filters)	267
QwtPlotRasterItem (A class, which displays raster data)	270
QwtPlotRescaler (QwtPlotRescaler takes care of fixed aspect ratios for plot scales)	274
QwtPlotScaleItem (A class which draws a scale inside the plot canvas)	281
QwtPlotSpectrogram (A plot item, which displays a spectrogram)	286
QwtPlotSvgItem (A plot item, which displays data in Scalable Vector Graphics (SVG) format)	294
QwtPlotZoomer (QwtPlotZoomer provides stacked zooming for a plot widget)	297
QwtPolygonFDData (Data class containing a single <code>QwtArray<QwtDoublePoint></code> object)	305
QwtRasterData (QwtRasterData defines an interface to any type of raster data)	306

QwtRichTextEngine (A text engine for Qt rich texts)	310
QwtRoundScaleDraw (A class for drawing round scales)	312
QwtScaleArithmetic (Arithmetic including a tolerance)	315
QwtScaleDiv (A class representing a scale division)	317
QwtScaleDraw (A class for drawing scales)	321
QwtScaleEngine (Base class for scale engines)	329
QwtScaleMap (A scale map)	335
QwtScaleTransformation (Operations for linear or logarithmic (base 10) transformations)	338
QwtScaleWidget (A Widget which contains a scale)	340
QwtSimpleCompassRose (A simple rose for QwtCompass)	348
QwtSlider (The Slider Widget)	350
QwtSpline (A class for spline interpolation)	358
QwtSplineCurveFitter (A curve fitter using cubic splines)	361
QwtSymbol (A class for drawing symbols)	363
QwtText (A class representing a text)	368
QwtTextEngine (Abstract base class for rendering text strings)	377
QwtTextLabel (A Widget which displays a QwtText)	380
QwtThermo (The Thermometer Widget)	383
QwtWheel (The Wheel Widget)	392

4 Qwt User's Guide File Index

4.1 Qwt User's Guide File List

Here is a list of all documented files with brief descriptions:

qwt_abstract_scale.h	??
qwt_abstract_scale_draw.h	??
qwt_abstract_slider.h	??
qwt_analog_clock.h	??
qwt_array.h	??
qwt_arrow_button.h	??

qwt_clipper.h	??
qwt_color_map.h	??
qwt_compass.h	??
qwt_compass_rose.h	??
qwt_counter.h	??
qwt_curve_fitter.h	??
qwt_data.h	??
qwt_dial.h	??
qwt_dial_needle.h	??
qwt_double_interval.h	??
qwt_double_range.h	??
qwt_double_rect.h	398
qwt_dyngrid_layout.h	??
qwt_event_pattern.h	??
qwt_global.h	??
qwt_interval_data.h	??
qwt_knob.h	??
qwt_layout_metrics.h	??
qwt_legend.h	??
qwt_legend_item.h	??
qwt_legend_itemmanager.h	??
qwt_magnifier.h	??
qwt_math.h	??
qwt_mathml_text_engine.h	??
qwt_paint_buffer.h	??
qwtPainter.h	??
qwt_panner.h	??
qwt_picker.h	??
qwt_picker_machine.h	??

qwt_plot.h	??
qwt_plot_canvas.h	??
qwt_plot_curve.h	??
qwt_plot_dict.h	399
qwt_plot_grid.h	??
qwt_plot_item.h	??
qwt_plot_layout.h	??
qwt_plot_magnifier.h	??
qwt_plot_marker.h	??
qwt_plot_panner.h	??
qwt_plot_picker.h	??
qwt_plot_printfilter.h	??
qwt_plot_rasteritem.h	??
qwt_plot_rescaler.h	??
qwt_plot_scaleitem.h	??
qwt_plot_spectrogram.h	??
qwt_plot_svgitem.h	??
qwt_plot_zoomer.h	??
qwt_polygon.h	??
qwt_raster_data.h	??
qwt_round_scale_draw.h	??
qwt_scale_div.h	??
qwt_scale_draw.h	??
qwt_scale_engine.h	??
qwt_scale_map.h	??
qwt_scale_widget.h	??
qwt_slider.h	??
qwt_spline.h	??
qwt_symbol.h	??

qwt_text.h	??
qwt_text_engine.h	??
qwt_text_label.h	??
qwt_thermo.h	??
qwt_valuelist.h	??
qwt_wheel.h	??

5 Qwt User's Guide Page Index

5.1 Qwt User's Guide Related Pages

Here is a list of all related documentation pages:

Qwt License, Version 1.0	400
INSTALL	409
Curve Plots	411
Scatter Plot	411
Spectrogram, Contour Plot	411
Histogram	411
Dials, Compasses, Knobs, Wheels, Sliders, Thermos	411
Deprecated List	411


6 Qwt User's Guide Class Documentation

6.1 QwtAbstractScale Class Reference

An abstract base class for classes containing a scale.

```
#include <qwt_abstract_scale.h>
```

Inheritance diagram for QwtAbstractScale:



Public Member Functions

- [QwtAbstractScale \(\)](#)

- virtual `~QwtAbstractScale ()`
- void `setScale (double vmin, double vmax, double step=0.0)`
- void `setScale (const QwtDoubleInterval &, double step=0.0)`
- void `setScale (const QwtScaleDiv &s)`
- void `setAutoScale ()`
- bool `autoScale () const`
- void `setScaleMaxMajor (int ticks)`
- int `scaleMaxMinor () const`
- void `setScaleMaxMinor (int ticks)`
- int `scaleMaxMajor () const`
- void `setScaleEngine (QwtScaleEngine *)`
- const `QwtScaleEngine * scaleEngine () const`
- `QwtScaleEngine * scaleEngine ()`
- const `QwtScaleMap & scaleMap () const`

Protected Member Functions

- void `rescale (double vmin, double vmax, double step=0.0)`
- void `setAbstractScaleDraw (QwtAbstractScaleDraw *)`
- const `QwtAbstractScaleDraw * abstractScaleDraw () const`
- `QwtAbstractScaleDraw * abstractScaleDraw ()`
- virtual void `scaleChange ()`

6.1.1 Detailed Description

An abstract base class for classes containing a scale.

`QwtAbstractScale` is used to provide classes with a `QwtScaleDraw`, and a `QwtScaleDiv`. The `QwtScaleDiv` might be set explicitly or calculated by a `QwtScaleEngine`.

6.1.2 Constructor & Destructor Documentation

6.1.2.1 QwtAbstractScale::QwtAbstractScale ()

Constructor

Creates a default `QwtScaleDraw` and a `QwtLinearScaleEngine`. Autoscaling is enabled, and the `stepSize` is initialized by 0.0.

6.1.2.2 QwtAbstractScale::~QwtAbstractScale () [virtual]

Destructor.

6.1.3 Member Function Documentation

6.1.3.1 void QwtAbstractScale::setScale (double *vmin*, double *vmax*, double *stepSize* = 0.0)

Specify a scale.

Disable autoscaling and define a scale by an interval and a step size

Parameters:

vmin lower limit of the scale interval
vmax upper limit of the scale interval
stepSize major step size

See also:

[setAutoScale\(\)](#)

6.1.3.2 void QwtAbstractScale::setScale (const QwtDoubleInterval & interval, double stepSize = 0.0)

Specify a scale.

Disable autoscaling and define a scale by an interval and a step size

Parameters:

interval Interval
stepSize major step size

See also:

[setAutoScale\(\)](#)

6.1.3.3 void QwtAbstractScale::setScale (const QwtScaleDiv & scaleDiv)

Specify a scale.

Disable autoscaling and define a scale by a scale division

Parameters:

scaleDiv Scale division

See also:

[setAutoScale\(\)](#)

6.1.3.4 void QwtAbstractScale::setAutoScale ()

Advise the widget to control the scale range internally.

Autoscaling is on by default.

See also:

[setScale\(\)](#), [autoScale\(\)](#)

6.1.3.5 bool QwtAbstractScale::autoScale () const**Returns:**

`true` if autoscaling is enabled

6.1.3.6 void QwtAbstractScale::setScaleMaxMajor (int ticks)

Set the maximum number of major tick intervals.

The scale's major ticks are calculated automatically such that the number of major intervals does not exceed ticks. The default value is 5.

Parameters:

ticks maximal number of major ticks.

See also:

[QwtAbstractScaleDraw](#)

6.1.3.7 int QwtAbstractScale::scaleMaxMinor () const**Returns:**

Max. number of minor tick intervals The default value is 3.

6.1.3.8 void QwtAbstractScale::setScaleMaxMinor (int ticks)

Set the maximum number of minor tick intervals.

The scale's minor ticks are calculated automatically such that the number of minor intervals does not exceed ticks. The default value is 3.

Parameters:

ticks

See also:

[QwtAbstractScaleDraw](#)

6.1.3.9 int QwtAbstractScale::scaleMaxMajor () const**Returns:**

Max. number of major tick intervals The default value is 5.

6.1.3.10 void QwtAbstractScale::setScaleEngine (QwtScaleEngine * scaleEngine)

Set a scale engine.

The scale engine is responsible for calculating the scale division, and in case of auto scaling how to align the scale.

scaleEngine has to be created with new and will be deleted in ~QwtAbstractScale or the next call of setScaleEngine.

6.1.3.11 `const QwtScaleEngine * QwtAbstractScale::scaleEngine () const`**Returns:**

Scale engine

See also:

[setScaleEngine\(\)](#)

6.1.3.12 `QwtScaleEngine * QwtAbstractScale::scaleEngine ()`**Returns:**

Scale engine

See also:

[setScaleEngine\(\)](#)

6.1.3.13 `const QwtScaleMap & QwtAbstractScale::scaleMap () const`**Returns:**

[abstractScaleDraw\(\)->scaleMap\(\)](#)

6.1.3.14 `void QwtAbstractScale::rescale (double vmin, double vmax, double stepSize = 0.0)`
[protected]

Recalculate the scale division and update the scale draw.

Parameters:

vmin Lower limit of the scale interval

vmax Upper limit of the scale interval

stepSize Major step size

See also:

[scaleChange\(\)](#)

6.1.3.15 `void QwtAbstractScale::setAbstractScaleDraw (QwtAbstractScaleDraw * scaleDraw)`
[protected]

Set a scale draw.

scaleDraw has to be created with `new` and will be deleted in `~QwtAbstractScale` or the next call of `setAbstractScaleDraw`.

6.1.3.16 `const QwtAbstractScaleDraw * QwtAbstractScale::abstractScaleDraw () const` [protected]

Returns:

Scale draw

See also:

[setAbstractScaleDraw\(\)](#)

6.1.3.17 `QwtAbstractScaleDraw * QwtAbstractScale::abstractScaleDraw ()` [protected]

Returns:

Scale draw

See also:

[setAbstractScaleDraw\(\)](#)

6.1.3.18 `void QwtAbstractScale::scaleChange ()` [protected, virtual]

Notify changed scale.

Dummy empty implementation, intended to be overloaded by derived classes


Reimplemented in [QwtSlider](#), and [QwtThermo](#).

6.2 QwtAbstractScaleDraw Class Reference

A abstract base class for drawing scales.

```
#include <qwt_abstract_scale_draw.h>
```

Inheritance diagram for QwtAbstractScaleDraw:

**Public Types**

- enum [ScaleComponent](#) {
 - Backbone** = 1,
 - Ticks** = 2,
 - Labels** = 4 }

Public Member Functions

- [QwtAbstractScaleDraw](#) ()
- [QwtAbstractScaleDraw](#) (const [QwtAbstractScaleDraw](#) &)
- virtual [~QwtAbstractScaleDraw](#) ()
- [QwtAbstractScaleDraw](#) & [operator=](#) (const [QwtAbstractScaleDraw](#) &)
- void [setScaleDiv](#) (const [QwtScaleDiv](#) &s)
- const [QwtScaleDiv](#) & [scaleDiv](#) () const
- void [setTransformation](#) ([QwtScaleTransformation](#) *)
- const [QwtScaleMap](#) & [map](#) () const
- void [enableComponent](#) ([ScaleComponent](#), bool enable=true)
- bool [hasComponent](#) ([ScaleComponent](#)) const
- void [setTickLength](#) ([QwtScaleDiv::TickType](#), int length)
- int [tickLength](#) ([QwtScaleDiv::TickType](#)) const
- int [majTickLength](#) () const
- void [setSpacing](#) (int margin)
- int [spacing](#) () const
- virtual void [draw](#) (QPainter *, const QPalette &) const
- virtual [QwtText](#) [label](#) (double) const
- virtual int [extent](#) (const QPen &, const QFont &) const=0
- void [setMinimumExtent](#) (int)
- int [minimumExtent](#) () const
- [QwtScaleMap](#) & [scaleMap](#) ()

Protected Member Functions

- virtual void [drawTick](#) (QPainter *painter, double value, int len) const=0
- virtual void [drawBackbone](#) (QPainter *painter) const=0
- virtual void [drawLabel](#) (QPainter *painter, double value) const=0
- void [invalidateCache](#) ()
- const [QwtText](#) & [tickLabel](#) (const QFont &, double value) const

6.2.1 Detailed Description

A abstract base class for drawing scales.

[QwtAbstractScaleDraw](#) can be used to draw linear or logarithmic scales.

After a scale division has been specified as a [QwtScaleDiv](#) object using [QwtAbstractScaleDraw::setScaleDiv\(const QwtScaleDiv &s\)](#), the scale can be drawn with the [QwtAbstractScaleDraw::draw\(\)](#) member.

6.2.2 Member Enumeration Documentation**6.2.2.1 enum [QwtAbstractScaleDraw::ScaleComponent](#)**

Components of a scale

- Backbone
- Ticks
- Labels

See also:

[enableComponent\(\)](#), [hasComponent](#)

6.2.3 Constructor & Destructor Documentation

6.2.3.1 QwtAbstractScaleDraw::QwtAbstractScaleDraw ()

Constructor.

The range of the scale is initialized to [0, 100], The spacing (distance between ticks and labels) is set to 4, the tick lengths are set to 4,6 and 8 pixels

6.2.3.2 QwtAbstractScaleDraw::QwtAbstractScaleDraw (const [QwtAbstractScaleDraw](#) &)

Copy constructor.

6.2.3.3 QwtAbstractScaleDraw::~~QwtAbstractScaleDraw () [virtual]

Destructor.

6.2.4 Member Function Documentation

6.2.4.1 [QwtAbstractScaleDraw](#) & QwtAbstractScaleDraw::operator= (const [QwtAbstractScaleDraw](#) &)

Assignment operator.

6.2.4.2 void QwtAbstractScaleDraw::setScaleDiv (const [QwtScaleDiv](#) & *sd*)

Change the scale division

Parameters:

sd New scale division

6.2.4.3 const [QwtScaleDiv](#) & QwtAbstractScaleDraw::scaleDiv () const

Returns:

scale division

6.2.4.4 void QwtAbstractScaleDraw::setTransformation ([QwtScaleTransformation](#) * *transformation*)

Change the transformation of the scale

Parameters:

transformation New scale transformation

6.2.4.5 `const QwtScaleMap & QwtAbstractScaleDraw::map () const`

Returns:

Map how to translate between scale and pixel values

6.2.4.6 `void QwtAbstractScaleDraw::enableComponent (ScaleComponent component, bool enable = true)`

En/Disable a component of the scale

Parameters:

component Scale component

enable On/Off

See also:

[hasComponent\(\)](#)

6.2.4.7 `bool QwtAbstractScaleDraw::hasComponent (ScaleComponent component) const`

Check if a component is enabled

See also:

[enableComponent\(\)](#)

6.2.4.8 `void QwtAbstractScaleDraw::setTickLength (QwtScaleDiv::TickType tickType, int length)`

Set the length of the ticks

Parameters:

tickType Tick type

length New length

Warning:

the length is limited to [0..1000]

6.2.4.9 `int QwtAbstractScaleDraw::tickLength (QwtScaleDiv::TickType tickType) const`

Return the length of the ticks

See also:

[setTickLength\(\)](#), [majTickLength\(\)](#)

6.2.4.10 `int QwtAbstractScaleDraw::majTickLength () const`

The same as `QwtAbstractScaleDraw::tickLength(QwtScaleDiv::MajorTick)`.

6.2.4.11 void QwtAbstractScaleDraw::setSpacing (int *spacing*)

Set the spacing between tick and labels.

The spacing is the distance between ticks and labels. The default spacing is 4 pixels.

Parameters:

spacing Spacing

See also:

[spacing\(\)](#)

6.2.4.12 int QwtAbstractScaleDraw::spacing () const

Get the spacing.

The spacing is the distance between ticks and labels. The default spacing is 4 pixels.

See also:

[setSpacing\(\)](#)

6.2.4.13 void QwtAbstractScaleDraw::draw (QPainter * *painter*, const QPalette & *palette*) const
[virtual]

Draw the scale.

Parameters:

painter The painter

palette Palette, text color is used for the labels, foreground color for ticks and backbone

6.2.4.14 [QwtText](#) QwtAbstractScaleDraw::label (double *value*) const [virtual]

Convert a value into its representing label.

The value is converted to a plain text using `QLocale::system().toString(value)`. This method is often overloaded by applications to have individual labels.

Parameters:

value Value

Returns:

Label string.

Reimplemented in [QwtDialScaleDraw](#).

6.2.4.15 `virtual int QwtAbstractScaleDraw::extent (const QPen &, const QFont &) const` [pure virtual]

Calculate the extent

The extent is the distance from the baseline to the outermost pixel of the scale draw in opposite to its orientation. It is at least `minimumExtent()` pixels.

See also:

[setMinimumExtent\(\)](#), [minimumExtent\(\)](#)

Implemented in [QwtRoundScaleDraw](#), and [QwtScaleDraw](#).

6.2.4.16 `void QwtAbstractScaleDraw::setMinimumExtent (int minExtent)`

Set a minimum for the extent.

The extent is calculated from the components of the scale draw. In situations, where the labels are changing and the layout depends on the extent (f.e scrolling a scale), setting an upper limit as minimum extent will avoid jumps of the layout.

Parameters:

minExtent Minimum extent

See also:

[extent\(\)](#), [minimumExtent\(\)](#)

6.2.4.17 `int QwtAbstractScaleDraw::minimumExtent () const`

Get the minimum extent

See also:

[extent\(\)](#), [setMinimumExtent\(\)](#)

6.2.4.18 `QwtScaleMap & QwtAbstractScaleDraw::scaleMap ()`

Returns:

Map how to translate between scale and pixel values

6.2.4.19 `virtual void QwtAbstractScaleDraw::drawTick (QPainter * painter, double value, int len) const` [protected, pure virtual]

Draw a tick

Parameters:

painter Painter

value Value of the tick

len Length of the tick

See also:

[drawBackbone\(\)](#), [drawLabel\(\)](#)

Implemented in [QwtRoundScaleDraw](#), and [QwtScaleDraw](#).

6.2.4.20 virtual void QwtAbstractScaleDraw::drawBackbone (QPainter * *painter*) const
[protected, pure virtual]

Draws the baseline of the scale

Parameters:

painter Painter

See also:

[drawTick\(\)](#), [drawLabel\(\)](#)

Implemented in [QwtRoundScaleDraw](#), and [QwtScaleDraw](#).

6.2.4.21 virtual void QwtAbstractScaleDraw::drawLabel (QPainter * *painter*, double *value*) const
[protected, pure virtual]

Draws the label for a major scale tick

Parameters:

painter Painter

value Value

See also:

[drawTick](#), [drawBackbone](#)

Implemented in [QwtRoundScaleDraw](#), and [QwtScaleDraw](#).

6.2.4.22 void QwtAbstractScaleDraw::invalidateCache () [protected]

Invalidate the cache used by [QwtAbstractScaleDraw::tickLabel](#)

The cache is invalidated, when a new [QwtScaleDiv](#) is set. If the labels need to be changed, while the same [QwtScaleDiv](#) is set, [QwtAbstractScaleDraw::invalidateCache](#) needs to be called manually.

6.2.4.23 const QwtText & QwtAbstractScaleDraw::tickLabel (const QFont & *font*, double *value*) const [protected]

Convert a value into its representing label and cache it.

The conversion between value and label is called very often in the layout and painting code. Unfortunately the calculation of the label sizes might be slow (really slow for rich text in Qt4), so it's necessary to cache the labels.

Parameters:

font Font

value Value

Returns:


Tick label

6.3 QwtAbstractSlider Class Reference

An abstract base class for slider widgets.

```
#include <qwt_abstract_slider.h>
```

Inheritance diagram for QwtAbstractSlider:

**Public Types**

- enum [ScrollMode](#) {
 ScrNone,
 ScrMouse,
 ScrTimer,
 ScrDirect,
 ScrPage }

Public Slots

- virtual void [setValue](#) (double val)
- virtual void [fitValue](#) (double val)
- virtual void [incValue](#) (int steps)
- virtual void [setReadOnly](#) (bool)

Signals

- void [valueChanged](#) (double value)
- void [sliderPressed](#) ()
- void [sliderReleased](#) ()
- void [sliderMoved](#) (double value)

Public Member Functions

- [QwtAbstractSlider](#) (Qt::Orientation, QWidget *parent=NULL)
- virtual [~QwtAbstractSlider](#) ()
- void [setUpdateTime](#) (int t)
- void [stopMoving](#) ()
- void [setTracking](#) (bool enable)
- virtual void [setMass](#) (double val)
- virtual double [mass](#) () const
- virtual void [setOrientation](#) (Qt::Orientation o)
- Qt::Orientation [orientation](#) () const
- bool [isReadOnly](#) () const
- bool [isValid](#) () const
- void [setValid](#) (bool valid)

Protected Member Functions

- virtual void [setPosition](#) (const QPoint &)
- virtual void [valueChange](#) ()
- virtual void [timerEvent](#) (QTimerEvent *e)
- virtual void [mousePressEvent](#) (QMouseEvent *e)
- virtual void [mouseReleaseEvent](#) (QMouseEvent *e)
- virtual void [mouseMoveEvent](#) (QMouseEvent *e)
- virtual void [keyPressEvent](#) (QKeyEvent *e)
- virtual void [wheelEvent](#) (QWheelEvent *e)
- virtual double [getValue](#) (const QPoint &p)=0
- virtual void [getScrollMode](#) (const QPoint &p, int &scrollMode, int &direction)=0
- void [setMouseOffset](#) (double)
- double [mouseOffset](#) () const
- int [scrollMode](#) () const

6.3.1 Detailed Description

An abstract base class for slider widgets.

[QwtAbstractSlider](#) is a base class for slider widgets. It handles mouse events and updates the slider's value accordingly. Derived classes only have to implement the [getValue\(\)](#) and [getScrollMode\(\)](#) members, and should react to a [valueChange\(\)](#), which normally requires repainting.

6.3.2 Member Enumeration Documentation

6.3.2.1 enum [QwtAbstractSlider::ScrollMode](#)

Scroll mode

See also:

[getScrollMode\(\)](#)

6.3.3 Constructor & Destructor Documentation

6.3.3.1 QwtAbstractSlider::QwtAbstractSlider (Qt::Orientation *orientation*, QWidget * *parent* = NULL) [explicit]

Constructor.

Parameters:

orientation Orientation

parent Parent widget

6.3.3.2 QwtAbstractSlider::~~QwtAbstractSlider () [virtual]

Destructor.

6.3.4 Member Function Documentation

6.3.4.1 void QwtAbstractSlider::setUpdateTime (int *t*)

Specify the update interval for automatic scrolling.

Parameters:

t update interval in milliseconds

See also:

[getScrollMode\(\)](#)

6.3.4.2 void QwtAbstractSlider::stopMoving ()

Stop updating if automatic scrolling is active.

6.3.4.3 void QwtAbstractSlider::setTracking (bool *enable*)

Enables or disables tracking.

If tracking is enabled, the slider emits a [valueChanged\(\)](#) signal whenever its value changes (the default behaviour). If tracking is disabled, the value changed() signal will only be emitted if:

- the user releases the mouse button and the value has changed or
- at the end of automatic scrolling.

Tracking is enabled by default.

Parameters:

enable `true` (enable) or `false` (disable) tracking.

6.3.4.4 void QwtAbstractSlider::setMass (double *val*) [virtual]

Set the slider's mass for flywheel effect.

If the slider's mass is greater than 0, it will continue to move after the mouse button has been released. Its speed decreases with time at a rate depending on the slider's mass. A large mass means that it will continue to move for a long time.

Derived widgets may overload this function to make it public.

Parameters:

val New mass in kg

See also:

[mass\(\)](#)

Reimplemented in [QwtWheel](#).

6.3.4.5 double QwtAbstractSlider::mass () const [virtual]**Returns:**

mass

See also:

[setMass\(\)](#)

Reimplemented in [QwtWheel](#).

6.3.4.6 void QwtAbstractSlider::setOrientation (Qt::Orientation *o*) [virtual]

Set the orientation.

Parameters:

o Orientation. Allowed values are Qt::Horizontal and Qt::Vertical.

Reimplemented in [QwtSlider](#), and [QwtWheel](#).

6.3.4.7 Qt::Orientation QwtAbstractSlider::orientation () const**Returns:**

Orientation

See also:

[setOrientation\(\)](#)

6.3.4.8 bool QwtAbstractSlider::isReadOnly () const

In read only mode the slider can't be controlled by mouse or keyboard.

Returns:

true if read only

See also:

[setReadOnly\(\)](#)

6.3.4.9 bool QwtAbstractSlider::isValid () const [inline]**See also:**

[QwtDbIRange::isValid\(\)](#)

Reimplemented from [QwtDoubleRange](#).

6.3.4.10 void QwtAbstractSlider::setValid (bool *valid*) [inline]**Parameters:**

valid true/false

See also:

[QwtDbIRange::isValid\(\)](#)

Reimplemented from [QwtDoubleRange](#).

6.3.4.11 void QwtAbstractSlider::setValue (double *val*) [virtual, slot]

Move the slider to a specified value.

This function can be used to move the slider to a value which is not an integer multiple of the step size.

Parameters:

val new value

See also:

[fitValue\(\)](#)

Reimplemented from [QwtDoubleRange](#).

6.3.4.12 void QwtAbstractSlider::fitValue (double *value*) [virtual, slot]

Set the slider's value to the nearest integer multiple of the step size.

Parameters:

value Value

See also:

[setValue\(\)](#), [incValue\(\)](#)

Reimplemented from [QwtDoubleRange](#).

6.3.4.13 void QwtAbstractSlider::incValue (int *steps*) [virtual, slot]

Increment the value by a specified number of steps.

Parameters:

steps number of steps

See also:

[setValue\(\)](#)

Reimplemented from [QwtDoubleRange](#).

6.3.4.14 void QwtAbstractSlider::setReadOnly (bool *readOnly*) [virtual, slot]

En/Disable read only mode

In read only mode the slider can't be controlled by mouse or keyboard.

Parameters:

readOnly Enables in case of true

See also:

[isReadOnly\(\)](#)

6.3.4.15 void QwtAbstractSlider::valueChanged (double *value*) [signal]

Notify a change of value.

In the default setting (tracking enabled), this signal will be emitted every time the value changes (see [setTracking\(\)](#)).

Parameters:

value new value

6.3.4.16 void QwtAbstractSlider::sliderPressed () [signal]

This signal is emitted when the user presses the movable part of the slider (start ScrMouse Mode).

6.3.4.17 void QwtAbstractSlider::sliderReleased () [signal]

This signal is emitted when the user releases the movable part of the slider.

6.3.4.18 void QwtAbstractSlider::sliderMoved (double *value*) [signal]

This signal is emitted when the user moves the slider with the mouse.

Parameters:

value new value

6.3.4.19 void QwtAbstractSlider::setPosition (const QPoint & *p*) [protected, virtual]

Move the slider to a specified point, adjust the value and emit signals if necessary.

6.3.4.20 void QwtAbstractSlider::valueChange () [protected, virtual]

Notify change of value

This function can be reimplemented by derived classes in order to keep track of changes, i.e. repaint the widget. The default implementation emits a [valueChanged\(\)](#) signal if tracking is enabled.

Reimplemented from [QwtDoubleRange](#).

Reimplemented in [QwtDial](#), [QwtSlider](#), and [QwtWheel](#).

6.3.4.21 void QwtAbstractSlider::timerEvent (QTimerEvent * *e*) [protected, virtual]

Qt timer event

Parameters:

e Timer event

6.3.4.22 void QwtAbstractSlider::mousePressEvent (QMouseEvent * *e*) [protected, virtual]

Mouse press event handler

Parameters:

e Mouse event

6.3.4.23 void QwtAbstractSlider::mouseReleaseEvent (QMouseEvent * *e*) [protected, virtual]

Mouse Release Event handler

Parameters:

e Mouse event

6.3.4.24 void QwtAbstractSlider::mouseMoveEvent (QMouseEvent * *e*) [protected, virtual]

Mouse Move Event handler

Parameters:

e Mouse event

6.3.4.25 void QwtAbstractSlider::keyPressEvent (QKeyEvent * *e*) [protected, virtual]

Handles key events

- `Key_Down`, `KeyLeft`
Decrement by 1
- `Key_Up`, `Key_Right`
Increment by 1

Parameters:

e Key event

See also:

[isReadOnly\(\)](#)

Reimplemented in [QwtCompass](#), and [QwtDial](#).

6.3.4.26 void QwtAbstractSlider::wheelEvent (QWheelEvent * e) [protected, virtual]

Wheel Event handler

Parameters:

e Wheel event

6.3.4.27 virtual double QwtAbstractSlider::getValue (const QPoint & p) [protected, pure virtual]

Determine the value corresponding to a specified point.

This is an abstract virtual function which is called when the user presses or releases a mouse button or moves the mouse. It has to be implemented by the derived class.

Parameters:

p point

Implemented in [QwtDial](#), [QwtSlider](#), and [QwtWheel](#).

6.3.4.28 virtual void QwtAbstractSlider::getScrollMode (const QPoint & p, int & scrollMode, int & direction) [protected, pure virtual]

Determine what to do when the user presses a mouse button.

This function is abstract and has to be implemented by derived classes. It is called on a mousePress event. The derived class can determine what should happen next in dependence of the position where the mouse was pressed by returning scrolling mode and direction. [QwtAbstractSlider](#) knows the following modes:

QwtAbstractSlider::ScrNone Scrolling switched off. Don't change the value.

QwtAbstractSlider::ScrMouse Change the value while the user keeps the button pressed and moves the mouse.

QwtAbstractSlider::ScrTimer Automatic scrolling. Increment the value in the specified direction as long as the user keeps the button pressed.

QwtAbstractSlider::ScrPage Automatic scrolling. Same as ScrTimer, but increment by page size.

Parameters:

p point where the mouse was pressed

Return values:

scrollMode The scrolling mode

direction direction: 1, 0, or -1.

Implemented in [QwtDial](#), [QwtSlider](#), and [QwtWheel](#).

6.4 QwtAlphaColorMap Class Reference

[QwtAlphaColorMap](#) varies the alpha value of a color.

```
#include <qwt_color_map.h>
```

Inheritance diagram for QwtAlphaColorMap:

**Public Member Functions**

- [QwtAlphaColorMap](#) (const QColor &=QColor(Qt::gray))
- [QwtAlphaColorMap](#) (const [QwtAlphaColorMap](#) &)
- virtual [~QwtAlphaColorMap](#) ()
- [QwtAlphaColorMap](#) & operator= (const [QwtAlphaColorMap](#) &)
- virtual [QwtColorMap](#) * [copy](#) () const
- void [setColor](#) (const QColor &)
- QColor [color](#) () const
- virtual QRgb [rgb](#) (const [QwtDoubleInterval](#) &, double value) const

6.4.1 Detailed Description

[QwtAlphaColorMap](#) varies the alpha value of a color.

6.4.2 Constructor & Destructor Documentation

6.4.2.1 [QwtAlphaColorMap::QwtAlphaColorMap](#) (const QColor & *color* = QColor(Qt::gray))

Constructor

Parameters:

color Color of the map

6.4.2.2 QwtAlphaColorMap::QwtAlphaColorMap (const [QwtAlphaColorMap](#) & *other*)

Copy constructor

Parameters:

other Other color map

6.4.2.3 QwtAlphaColorMap::~~QwtAlphaColorMap () [virtual]

Destructor.

6.4.3 Member Function Documentation

6.4.3.1 [QwtAlphaColorMap](#) & QwtAlphaColorMap::operator= (const [QwtAlphaColorMap](#) & *other*)

Assignment operator

Parameters:

other Other color map

Returns:

*this

6.4.3.2 [QwtColorMap](#) * QwtAlphaColorMap::copy () const [virtual]

Clone the color map.

Implements [QwtColorMap](#).

6.4.3.3 void QwtAlphaColorMap::setColor (const [QColor](#) & *color*)

Set the color

Parameters:

color Color

See also:

[color\(\)](#)

6.4.3.4 [QColor](#) QwtAlphaColorMap::color () const

Returns:

the color

See also:

[setColor\(\)](#)

6.4.3.5 `QRgb QwtAlphaColorMap::rgb (const QwtDoubleInterval & interval, double value) const`
 [virtual]

Map a value of a given interval into a alpha value.

$\text{alpha} := (\text{value} - \text{interval.minValue}()) / \text{interval.width}();$

Parameters:

interval Range for all values

value Value to map into a rgb value

Returns:

rgb value, with an alpha value


Implements [QwtColorMap](#).

6.5 QwtAnalogClock Class Reference

An analog clock.

```
#include <qwt_analog_clock.h>
```

Inheritance diagram for QwtAnalogClock:



Public Types

- enum [Hand](#) {
SecondHand,
MinuteHand,
HourHand,
NHands }

Public Slots

- void [setCurrentTime](#) ()
- void [setTime](#) (const [QTime](#) &=[QTime::currentTime](#)())

Public Member Functions

- [QwtAnalogClock](#) (QWidget *parent=NULL)
- virtual [~QwtAnalogClock](#) ()
- virtual void [setHand](#) (Hand, [QwtDialNeedle](#) *)
- const [QwtDialNeedle](#) * [hand](#) (Hand) const
- [QwtDialNeedle](#) * [hand](#) (Hand)

Protected Member Functions

- virtual [QwtText](#) [scaleLabel](#) (double) const
- virtual void [drawNeedle](#) (QPainter *, const QPoint &, int radius, double direction, [QPalette::ColorGroup](#)) const
- virtual void [drawHand](#) (QPainter *, [Hand](#), const QPoint &, int radius, double direction, [QPalette::ColorGroup](#)) const

6.5.1 Detailed Description

An analog clock.

Example

```
#include <qwt_analog_clock.h>

QwtAnalogClock *clock = new QwtAnalogClock(...);
clock->scaleDraw()->setPenWidth(3);
clock->setLineWidth(6);
clock->setFrameShadow(QwtDial::Sunken);
clock->setTime();

// update the clock every second
QTimer *timer = new QTimer(clock);
timer->connect(timer, SIGNAL(timeout()), clock, SLOT(setCurrentTime()));
timer->start(1000);
```

Qwt is missing a set of good looking hands. Contributions are very welcome.

Note:

The examples/dials example shows how to use [QwtAnalogClock](#).

6.5.2 Member Enumeration Documentation

6.5.2.1 enum [QwtAnalogClock::Hand](#)

Hand type

See also:

[setHand\(\)](#), [hand\(\)](#)

6.5.3 Constructor & Destructor Documentation

6.5.3.1 QwtAnalogClock::QwtAnalogClock (QWidget * *parent* = NULL) [explicit]

Constructor

Parameters:

parent Parent widget

6.5.3.2 QwtAnalogClock::~QwtAnalogClock () [virtual]

Destructor.

6.5.4 Member Function Documentation

6.5.4.1 void QwtAnalogClock::setHand (Hand *hand*, QwtDialNeedle * *needle*) [virtual]

Set a clockhand

Parameters:

hand Specifies the type of hand

needle Hand

See also:

[hand\(\)](#)

6.5.4.2 const QwtDialNeedle * QwtAnalogClock::hand (Hand *hd*) const

Returns:

Clock hand

Parameters:

hd Specifies the type of hand

See also:

[setHand\(\)](#)

6.5.4.3 QwtDialNeedle * QwtAnalogClock::hand (Hand *hd*)

Returns:

Clock hand

Parameters:

hd Specifies the type of hand

See also:

[setHand\(\)](#)

6.5.4.4 void QwtAnalogClock::setCurrentTime () [slot]

Set the current time.

This is the same as [QwtAnalogClock::setTime\(\)](#), but Qt < 3.0 can't handle default parameters for slots.

6.5.4.5 void QwtAnalogClock::setTime (const QTime & *time* = QTime::currentTime ()) [slot]

Set a time

Parameters:

time Time to display

6.5.4.6 [QwtText](#) QwtAnalogClock::scaleLabel (double *value*) const [protected, virtual]

Find the scale label for a given value

Parameters:

value Value

Returns:

Label

Reimplemented from [QwtDial](#).

6.5.4.7 void QwtAnalogClock::drawNeedle (QPainter * *painter*, const QPoint & *center*, int *radius*, double *direction*, QPalette::ColorGroup *cg*) const [protected, virtual]

Draw the needle.

A clock has no single needle but three hands instead. `drawNeedle` translates `value()` into directions for the hands and calls `drawHand()`.

Parameters:

painter Painter

center Center of the clock

radius Maximum length for the hands

direction Dummy, not used.

cg ColorGroup

See also:

[drawHand\(\)](#)

Reimplemented from [QwtDial](#).

6.5.4.8 `void QwtAnalogClock::drawHand (QPainter * painter, Hand hd, const QPoint & center, int radius, double direction, QPalette::ColorGroup cg) const` [protected, virtual]

Draw a clock hand

Parameters:

painter Painter

hd Specify the type of hand

center Center of the clock

radius Maximum length for the hands

direction Direction of the hand in degrees, counter clockwise


cg ColorGroup

6.6 QwtArrayData Class Reference

Data class containing two QwtArray<double> objects.

```
#include <qwt_data.h>
```

Inheritance diagram for QwtArrayData:



Public Member Functions

- [QwtArrayData](#) (const QwtArray< double > &*x*, const QwtArray< double > &*y*)
- [QwtArrayData](#) (const double **x*, const double **y*, size_t *size*)
- [QwtArrayData & operator=](#) (const [QwtArrayData](#) &)
- virtual [QwtData * copy](#) () const
- virtual size_t [size](#) () const
- virtual double [x](#) (size_t *i*) const
- virtual double [y](#) (size_t *i*) const
- const QwtArray< double > & [xData](#) () const
- const QwtArray< double > & [yData](#) () const
- virtual [QwtDoubleRect boundingRect](#) () const

6.6.1 Detailed Description

Data class containing two QwtArray<double> objects.

6.6.2 Constructor & Destructor Documentation

6.6.2.1 QwtArrayData::QwtArrayData (const QwtArray< double > & *x*, const QwtArray< double > & *y*)

Constructor

Parameters:

x Array of x values

y Array of y values

See also:

[QwtPlotCurve::setData\(\)](#)

6.6.2.2 QwtArrayData::QwtArrayData (const double * x, const double * y, size_t size)

Constructor

Parameters:

x Array of x values

y Array of y values

size Size of the x and y arrays

See also:

[QwtPlotCurve::setData\(\)](#)

6.6.3 Member Function Documentation**6.6.3.1 QwtArrayData & QwtArrayData::operator= (const QwtArrayData &)**

Assignment.

6.6.3.2 QwtData * QwtArrayData::copy () const [virtual]**Returns:**

Pointer to a copy (virtual copy constructor)

Implements [QwtData](#).

6.6.3.3 size_t QwtArrayData::size () const [virtual]**Returns:**

Size of the data set

Implements [QwtData](#).

6.6.3.4 double QwtArrayData::x (size_t i) const [virtual]

Return the x value of data point *i*

Parameters:

i Index

Returns:

x X value of data point *i*

Implements [QwtData](#).

6.6.3.5 `double QwtArrayData::y (size_t i) const` [virtual]

Return the y value of data point i

Parameters:

i Index

Returns:

y Y value of data point i

Implements [QwtData](#).

6.6.3.6 `const QwtArray< double > & QwtArrayData::xData () const`**Returns:**

Array of the x-values

6.6.3.7 `const QwtArray< double > & QwtArrayData::yData () const`**Returns:**

Array of the y-values

6.6.3.8 `QwtDoubleRect QwtArrayData::boundingRect () const` [virtual]

Returns the bounding rectangle of the data. If there is no bounding rect, like for empty data the rectangle is invalid: `QwtDoubleRect::isValid() == false`

Reimplemented from [QwtData](#).

6.7 QwtArrowButton Class Reference

Arrow Button.

```
#include <qwt_arrow_button.h>
```

Public Member Functions

- [QwtArrowButton](#) (int num, Qt::ArrowType, QWidget *parent=NULL)
- virtual [~QwtArrowButton](#) ()
- Qt::ArrowType [arrowType](#) () const
- int [num](#) () const
- virtual QSize [sizeHint](#) () const
- virtual QSize [minimumSizeHint](#) () const

Protected Member Functions

- virtual void [paintEvent](#) (QPaintEvent *event)
- virtual void [drawButtonLabel](#) (QPainter *p)
- virtual void [drawArrow](#) (QPainter *, const QRect &, Qt::ArrowType) const
- virtual QRect [labelRect](#) () const
- virtual QSize [arrowSize](#) (Qt::ArrowType, const QSize &boundingSize) const
- virtual void [keyPressEvent](#) (QKeyEvent *)

6.7.1 Detailed Description

Arrow Button.

A push button with one or more filled triangles on its front. An Arrow button can have 1 to 3 arrows in a row, pointing up, down, left or right.

6.7.2 Constructor & Destructor Documentation

6.7.2.1 `QwtArrowButton::QwtArrowButton (int num, Qt::ArrowType arrowType, QWidget *parent = NULL)` [explicit]

Parameters:

- num* Number of arrows
- arrowType* see Qt::ArrowType in the Qt docs.
- parent* Parent widget

6.7.2.2 `QwtArrowButton::~QwtArrowButton ()` [virtual]

Destructor.

6.7.3 Member Function Documentation

6.7.3.1 `Qt::ArrowType QwtArrowButton::arrowType () const`

The direction of the arrows.

6.7.3.2 `int QwtArrowButton::num () const`

The number of arrows.

6.7.3.3 `QSize QwtArrowButton::sizeHint () const` [virtual]

Returns:

- a size hint

6.7.3.4 `QSize QwtArrowButton::minimumSizeHint () const` [virtual]

Return a minimum size hint.

6.7.3.5 void QwtArrowButton::paintEvent (QPaintEvent * *event*) [protected, virtual]

Paint event handler

Parameters:

event Paint event

6.7.3.6 void QwtArrowButton::drawButtonLabel (QPainter * *painter*) [protected, virtual]

Draw the button label.

Parameters:

painter Painter

See also:

The Qt Manual on QPushButton

6.7.3.7 void QwtArrowButton::drawArrow (QPainter * *painter*, const QRect & *r*, Qt::ArrowType *arrowType*) const [protected, virtual]

Draw an arrow int a bounding rect

Parameters:

painter Painter

r Rectangle where to paint the arrow

arrowType Arrow type

6.7.3.8 QRect QwtArrowButton::labelRect () const [protected, virtual]**Returns:**

the bounding rect for the label

6.7.3.9 QSize QwtArrowButton::arrowSize (Qt::ArrowType *arrowType*, const QSize & *boundingSize*) const [protected, virtual]

Calculate the size for a arrow that fits into a rect of a given size

Parameters:

arrowType Arrow type

boundingSize Bounding size

Returns:

Size of the arrow

6.7.3.10 void QwtArrowButton::keyPressEvent (QKeyEvent *) [protected, virtual]

autoRepeat for the space keys

6.8 QwtClipper Class Reference

Some clipping algos.

```
#include <qwt_clipper.h>
```

Static Public Member Functions

- static QwtPolygon [clipPolygon](#) (const QRect &, const QwtPolygon &)
- static QwtPolygonF [clipPolygonF](#) (const QwtDoubleRect &, const QwtPolygonF &)
- static QwtArray< QwtDoubleInterval > [clipCircle](#) (const QwtDoubleRect &, const QwtDoublePoint &, double radius)

6.8.1 Detailed Description

Some clipping algos.

6.8.2 Member Function Documentation

6.8.2.1 QwtPolygon QwtClipper::clipPolygon (const QRect & *clipRect*, const QwtPolygon & *polygon*) [static]

Sutherland-Hodgman polygon clipping

Parameters:

clipRect Clip rectangle

polygon Polygon

Returns:

Clipped polygon

6.8.2.2 QwtPolygonF QwtClipper::clipPolygonF (const QwtDoubleRect & *clipRect*, const QwtPolygonF & *polygon*) [static]

Sutherland-Hodgman polygon clipping

Parameters:

clipRect Clip rectangle

polygon Polygon

Returns:

Clipped polygon

6.8.2.3 `QwtArray< QwtDoubleInterval > QwtClipper::clipCircle (const QwtDoubleRect & clipRect, const QwtDoublePoint & center, double radius)` [static]

Circle clipping

`clipCircle()` divides a circle into intervals of angles representing arcs of the circle. When the circle is completely inside the clip rectangle an interval $[0.0, 2 * M_PI]$ is returned.

Parameters:

- clipRect* Clip rectangle
- center* Center of the circle
- radius* Radius of the circle

Returns:


Arcs of the circle

6.9 QwtColorMap Class Reference

`QwtColorMap` is used to map values into colors.

```
#include <qwt_color_map.h>
```

Inheritance diagram for `QwtColorMap`:



Public Types

- enum `Format` {
 RGB,
 Indexed }

Public Member Functions

- `QwtColorMap (Format=QwtColorMap::RGB)`
- virtual `~QwtColorMap ()`
- `Format format () const`
- virtual `QwtColorMap * copy () const=0`
- virtual `QRgb rgb (const QwtDoubleInterval &interval, double value) const=0`
- virtual `unsigned char colorIndex (const QwtDoubleInterval &interval, double value) const=0`
- `QColor color (const QwtDoubleInterval &, double value) const`
- virtual `QVector< QRgb > colorTable (const QwtDoubleInterval &) const`

6.9.1 Detailed Description

[QwtColorMap](#) is used to map values into colors.

For displaying 3D data on a 2D plane the 3rd dimension is often displayed using colors, like f.e in a spectrogram.

Each color map is optimized to return colors for only one of the following image formats:

- `QImage::Format_Indexed8`
- `QImage::Format_ARGB32`

See also:

[QwtPlotSpectrogram](#), [QwtScaleWidget](#)

6.9.2 Member Enumeration Documentation

6.9.2.1 enum `QwtColorMap::Format`

- `RGB`
The map is intended to map into `QRgb` values.
- `Indexed`
The map is intended to map into 8 bit values, that are indices into the color table.

See also:

[rgb\(\)](#), [colorIndex\(\)](#), [colorTable\(\)](#)

6.9.3 Constructor & Destructor Documentation

6.9.3.1 `QwtColorMap::QwtColorMap (Format = QwtColorMap::RGB)`

Constructor.

6.9.3.2 `QwtColorMap::~QwtColorMap ()` [virtual]

Destructor.

6.9.4 Member Function Documentation

6.9.4.1 `QwtColorMap::Format QwtColorMap::format () const` [inline]

Returns:

Intended format of the color map

See also:

[Format](#)

6.9.4.2 virtual `QwtColorMap* QwtColorMap::copy () const` [pure virtual]

Clone the color map.

Implemented in [QwtLinearColorMap](#), and [QwtAlphaColorMap](#).

6.9.4.3 virtual `QRgb QwtColorMap::rgb (const QwtDoubleInterval & interval, double value) const` [pure virtual]

Map a value of a given interval into a rgb value.

Parameters:

interval Range for the values

value Value

Returns:

rgb value, corresponding to value

Implemented in [QwtLinearColorMap](#), and [QwtAlphaColorMap](#).

6.9.4.4 virtual `unsigned char QwtColorMap::colorIndex (const QwtDoubleInterval & interval, double value) const` [pure virtual]

Map a value of a given interval into a color index

Parameters:

interval Range for the values

value Value

Returns:

color index, corresponding to value

Implemented in [QwtLinearColorMap](#).

6.9.4.5 `QColor QwtColorMap::color (const QwtDoubleInterval & interval, double value) const` [inline]

Map a value into a color

Parameters:

interval Valid interval for values

value Value

Returns:

Color corresponding to value

Warning:

This method is slow for Indexed color maps. If it is necessary to map many values, its better to get the color table once and find the color using [colorIndex\(\)](#).

6.9.4.6 QwtColorTable `QwtColorMap::colorTable (const QwtDoubleInterval & interval) const` [virtual]

Build and return a color map of 256 colors

The color table is needed for rendering indexed images in combination with using [colorIndex\(\)](#).

Parameters:

interval Range for the values

Returns:


A color table, that can be used for a QImage

6.10 QwtCompass Class Reference

A Compass Widget.

```
#include <qwt_compass.h>
```

Inheritance diagram for QwtCompass:



Public Member Functions

- [QwtCompass](#) (QWidget *parent=NULL)
- virtual [~QwtCompass](#) ()
- void [setRose](#) ([QwtCompassRose](#) *rose)
- const [QwtCompassRose](#) * [rose](#) () const
- [QwtCompassRose](#) * [rose](#) ()
- const QMap< double, QString > & [labelMap](#) () const
- QMap< double, QString > & [labelMap](#) ()
- void [setLabelMap](#) (const QMap< double, QString > &map)

Protected Member Functions

- virtual [QwtText](#) [scaleLabel](#) (double value) const
- virtual void [drawRose](#) (QPainter *, const QPoint ¢er, int radius, double north, QPalette::Color-Group) const
- virtual void [drawScaleContents](#) (QPainter *, const QPoint ¢er, int radius) const
- virtual void [keyPressEvent](#) (QKeyEvent *)

6.10.1 Detailed Description

A Compass Widget.

[QwtCompass](#) is a widget to display and enter directions. It consists of a scale, an optional needle and rose.

Note:

The examples/dials example shows how to use [QwtCompass](#).

6.10.2 Constructor & Destructor Documentation

6.10.2.1 [QwtCompass::QwtCompass \(QWidget * *parent* = NULL\)](#) [explicit]

Constructor.

Parameters:

parent Parent widget

Create a compass widget with a scale, no needle and no rose. The default origin is 270.0 with no valid value. It accepts mouse and keyboard inputs and has no step size. The default mode is `QwtDial::RotateNeedle`.

6.10.2.2 [QwtCompass::~QwtCompass \(\)](#) [virtual]

Destructor.

6.10.3 Member Function Documentation

6.10.3.1 [void QwtCompass::setRose \(QwtCompassRose * *rose*\)](#)

Set a rose for the compass

Parameters:

rose Compass rose

Warning:

The rose will be deleted, when a different rose is set or in `~QwtCompass`

See also:

[rose\(\)](#)

6.10.3.2 [const QwtCompassRose * QwtCompass::rose \(\) const](#)

Returns:

rose

See also:

[setRose\(\)](#)

6.10.3.3 [QwtCompassRose](#) * [QwtCompass::rose](#) ()

Returns:

rose

See also:

[setRose\(\)](#)

6.10.3.4 `const QMap< double, QString > & QwtCompass::labelMap () const`

Returns:

map, mapping values to labels

See also:

[setLabelMap\(\)](#)

6.10.3.5 `QMap< double, QString > & QwtCompass::labelMap ()`

Returns:

map, mapping values to labels

See also:

[setLabelMap\(\)](#)

6.10.3.6 `void QwtCompass::setLabelMap (const QMap< double, QString > & map)`

Set a map, mapping values to labels.

Parameters:

map value to label map

The values of the major ticks are found by looking into this map. The default map consists of the labels N, NE, E, SE, S, SW, W, NW.

Warning:

The map will have no effect for values that are no major tick values. Major ticks can be changed by [QwtScaleDraw::setScale](#)

See also:

[labelMap\(\)](#), [scaleDraw\(\)](#), [setScale\(\)](#)

6.10.3.7 [QwtText](#) `QwtCompass::scaleLabel (double value) const` [protected, virtual]

Map a value to a corresponding label

Parameters:

value Value that will be mapped

Returns:

Label, or `QString::null`

`label()` looks in a map for a corresponding label for value or return an null text.

See also:

[labelMap\(\)](#), [setLabelMap\(\)](#)

Reimplemented from [QwtDial](#).

6.10.3.8 `void QwtCompass::drawRose (QPainter * painter, const QPoint & center, int radius, double north, QPalette::ColorGroup cg) const` [protected, virtual]

Draw the compass rose

Parameters:

painter Painter

center Center of the compass

radius of the circle, where to paint the rose

north Direction pointing north, in degrees counter clockwise

cg Color group

6.10.3.9 `void QwtCompass::drawScaleContents (QPainter * painter, const QPoint & center, int radius) const` [protected, virtual]

Draw the contents of the scale

Parameters:

painter Painter

center Center of the content circle

radius Radius of the content circle

Reimplemented from [QwtDial](#).

6.10.3.10 `void QwtCompass::keyPressEvent (QKeyEvent * kev)` [protected, virtual]

Handles key events

Beside the keys described in [QwtDial::keyPressEvent](#) numbers from 1-9 (without 5) set the direction according to their position on the num pad.

See also:

[isReadOnly\(\)](#)


Reimplemented from [QwtDial](#).

6.11 QwtCompassMagnetNeedle Class Reference

A magnet needle for compass widgets.

```
#include <qwt_dial_needle.h>
```

Inheritance diagram for QwtCompassMagnetNeedle:



Public Types

- enum [Style](#) {
 Arrow,
 Ray,
 TriangleStyle,
 ThinStyle,
 Style1,
 Style2,
 NoSymbol = -1,
 Ellipse,
 Rect,
 Diamond,
 Triangle,
 DTriangle,
 UTriangle,
 LTriangle,
 RTriangle,
 Cross,
 XCross,
 HLine,
 VLine,
 Star1,
 Star2,
 Hexagon,
 StyleCnt }

Public Member Functions

- [QwtCompassMagnetNeedle](#) ([Style](#)=TriangleStyle, const QColor &light=Qt::white, const QColor &dark=Qt::red)
- virtual void [draw](#) (QPainter *, const QPoint &, int length, double direction, QPalette::ColorGroup=QPalette::Active) const

Static Public Member Functions

- static void [drawTriangleNeedle](#) (QPainter *, const QPalette &, QPalette::ColorGroup, const QPoint &, int length, double direction)
- static void [drawThinNeedle](#) (QPainter *, const QPalette &, QPalette::ColorGroup, const QPoint &, int length, double direction)

Static Protected Member Functions

- static void [drawPointer](#) (QPainter *painter, const QBrush &brush, int colorOffset, const QPoint ¢er, int length, int width, double direction)

6.11.1 Detailed Description

A magnet needle for compass widgets.

A magnet needle points to two opposite directions indicating north and south.

The following colors are used:

- QColorGroup::Light
Used for pointing south
- QColorGroup::Dark
Used for pointing north
- QColorGroup::Base
Knob (ThinStyle only)

See also:

[QwtDial](#), [QwtCompass](#)

6.11.2 Member Enumeration Documentation

6.11.2.1 enum [QwtCompassMagnetNeedle::Style](#)

Style of the needle.

6.11.3 Constructor & Destructor Documentation

6.11.3.1 [QwtCompassMagnetNeedle::QwtCompassMagnetNeedle](#) (**Style** = TriangleStyle, const QColor & *light* = Qt::white, const QColor & *dark* = Qt::red)

Constructor.

6.11.4 Member Function Documentation

6.11.4.1 void [QwtCompassMagnetNeedle::draw](#) (QPainter * *painter*, const QPoint & *center*, int *length*, double *direction*, QPalette::ColorGroup *colorGroup* = QPalette::Active) const [virtual]

Draw the needle

Parameters:

painter Painter
center Center of the dial, start position for the needle
length Length of the needle
direction Direction of the needle, in degrees counter clockwise
colorGroup Color group, used for painting

Implements [QwtDialNeedle](#).

6.11.4.2 void QwtCompassMagnetNeedle::drawTriangleNeedle (QPainter * *painter*, const QPalette & *palette*, QPalette::ColorGroup *colorGroup*, const QPoint & *center*, int *length*, double *direction*) [static]

Draw a compass needle

Parameters:

painter Painter
palette Palette
colorGroup Color group
center Center, where the needle starts
length Length of the needle
direction Direction

6.11.4.3 void QwtCompassMagnetNeedle::drawThinNeedle (QPainter * *painter*, const QPalette & *palette*, QPalette::ColorGroup *colorGroup*, const QPoint & *center*, int *length*, double *direction*) [static]

Draw a compass needle

Parameters:

painter Painter
palette Palette
colorGroup Color group
center Center, where the needle starts
length Length of the needle
direction Direction

6.11.4.4 void QwtCompassMagnetNeedle::drawPointer (QPainter * *painter*, const QBrush & *brush*, int *colorOffset*, const QPoint & *center*, int *length*, int *width*, double *direction*) [static, protected]

Draw a compass needle

Parameters:

painter Painter


brush Brush
colorOffset Color offset
center Center, where the needle starts
length Length of the needle
width Width of the needle
direction Direction

6.12 QwtCompassRose Class Reference

Abstract base class for a compass rose.

```
#include <qwt_compass_rose.h>
```

Inheritance diagram for QwtCompassRose:



Public Member Functions

- virtual void [setPalette](#) (const QPalette &p)
- const QPalette & [palette](#) () const
- virtual void [draw](#) (QPainter *painter, const QPoint ¢er, int radius, double north, QPalette::ColorGroup colorGroup=QPalette::Active) const=0

6.12.1 Detailed Description

Abstract base class for a compass rose.

6.12.2 Member Function Documentation

6.12.2.1 virtual void QwtCompassRose::setPalette (const QPalette &p) [inline, virtual]

Assign a palette.

6.12.2.2 const QPalette& QwtCompassRose::palette () const [inline]

Returns:

Current palette

6.12.2.3 virtual void QwtCompassRose::draw (QPainter * painter, const QPoint & center, int radius, double north, QPalette::ColorGroup colorGroup = QPalette::Active) const [pure virtual]

Draw the rose

Parameters:

painter Painter
center Center point
radius Radius of the rose
north Position
colorGroup Color group


Implemented in [QwtSimpleCompassRose](#).

6.13 QwtCompassWindArrow Class Reference

An indicator for the wind direction.

```
#include <qwt_dial_needle.h>
```

Inheritance diagram for QwtCompassWindArrow:

**Public Types**

- enum [Style](#) {
 - Arrow,**
 - Ray,**
 - TriangleStyle,**
 - ThinStyle,**
 - Style1,**
 - Style2,**
 - NoSymbol = -1,**
 - Ellipse,**
 - Rect,**
 - Diamond,**
 - Triangle,**
 - DTriangle,**
 - UTriangle,**
 - LTriangle,**
 - RTriangle,**
 - Cross,**
 - XCross,**
 - HLine,**
 - VLine,**

Star1,
Star2,
Hexagon,
StyleCnt }

Public Member Functions

- [QwtCompassWindArrow](#) ([Style](#), const QColor &light=Qt::white, const QColor &dark=Qt::gray)
- virtual void [draw](#) (QPainter *, const QPoint &, int length, double direction, QPalette::ColorGroup=QPalette::Active) const

Static Public Member Functions

- static void [drawStyle1Needle](#) (QPainter *, const QPalette &, QPalette::ColorGroup, const QPoint &, int length, double direction)
- static void [drawStyle2Needle](#) (QPainter *, const QPalette &, QPalette::ColorGroup, const QPoint &, int length, double direction)

6.13.1 Detailed Description

An indicator for the wind direction.

[QwtCompassWindArrow](#) shows the direction where the wind comes from.

- QColorGroup::Light
Used for Style1, or the light half of Style2
- QColorGroup::Dark
Used for the dark half of Style2

See also:

[QwtDial](#), [QwtCompass](#)

6.13.2 Member Enumeration Documentation

6.13.2.1 enum [QwtCompassWindArrow::Style](#)

Style of the arrow.

6.13.3 Constructor & Destructor Documentation

6.13.3.1 [QwtCompassWindArrow::QwtCompassWindArrow](#) ([Style](#) *style*, const QColor & *light* = Qt::white, const QColor & *dark* = Qt::gray)

Constructor

Parameters:

style Arrow style
light Light color
dark Dark color

6.13.4 Member Function Documentation

6.13.4.1 void QwtCompassWindArrow::draw (QPainter * *painter*, const QPoint & *center*, int *length*, double *direction*, QPalette::ColorGroup *colorGroup* = QPalette::Active) const [virtual]

Draw the needle

Parameters:

painter Painter

center Center of the dial, start position for the needle

length Length of the needle

direction Direction of the needle, in degrees counter clockwise

colorGroup Color group, used for painting

Implements [QwtDialNeedle](#).

6.13.4.2 void QwtCompassWindArrow::drawStyle1Needle (QPainter * *painter*, const QPalette & *palette*, QPalette::ColorGroup *colorGroup*, const QPoint & *center*, int *length*, double *direction*) [static]

Draw a compass needle

Parameters:

painter Painter

palette Palette

colorGroup colorGroup

center Center of the dial, start position for the needle

length Length of the needle

direction Direction of the needle, in degrees counter clockwise

6.13.4.3 void QwtCompassWindArrow::drawStyle2Needle (QPainter * *painter*, const QPalette & *palette*, QPalette::ColorGroup *colorGroup*, const QPoint & *center*, int *length*, double *direction*) [static]

Draw a compass needle

Parameters:

painter Painter

palette Palette

colorGroup colorGroup

center Center of the dial, start position for the needle

length Length of the needle


direction Direction of the needle, in degrees counter clockwise

6.14 QwtCounter Class Reference

The Counter Widget.

```
#include <qwt_counter.h>
```

Inheritance diagram for QwtCounter:



Public Types

- enum [Button](#) {
 Button1,
 Button2,
 Button3,
 ButtonCnt }

Signals

- void [buttonReleased](#) (double value)
- void [valueChanged](#) (double value)

Public Member Functions

- [QwtCounter](#) (QWidget *parent=NULL)
- virtual [~QwtCounter](#) ()
- bool [editable](#) () const
- void [setEditable](#) (bool)
- void [setNumButtons](#) (int n)
- int [numButtons](#) () const
- void [setIncSteps](#) ([QwtCounter::Button](#) btn, int nSteps)
- int [incSteps](#) ([QwtCounter::Button](#) btn) const
- virtual void [setValue](#) (double)
- virtual QSize [sizeHint](#) () const
- virtual void [polish](#) ()
- double [step](#) () const
- void [setStep](#) (double s)
- double [minVal](#) () const
- void [setMinValue](#) (double m)
- double [maxVal](#) () const
- void [setMaxValue](#) (double m)
- void [setStepButton1](#) (int nSteps)
- int [stepButton1](#) () const
- void [setStepButton2](#) (int nSteps)
- int [stepButton2](#) () const
- void [setStepButton3](#) (int nSteps)
- int [stepButton3](#) () const
- virtual double [value](#) () const

Protected Member Functions

- virtual bool [event](#) (QEvent *)
- virtual void [wheelEvent](#) (QWheelEvent *)
- virtual void [keyPressEvent](#) (QKeyEvent *)
- virtual void [rangeChange](#) ()

6.14.1 Detailed Description

The Counter Widget.

A Counter consists of a label displaying a number and one or more (up to three) push buttons on each side of the label which can be used to increment or decrement the counter's value.

A Counter has a range from a minimum value to a maximum value and a step size. The range can be specified using [QwtDblRange::setRange\(\)](#). The counter's value is an integer multiple of the step size. The number of steps by which a button increments or decrements the value can be specified using [QwtCounter::setIncSteps\(\)](#). The number of buttons can be changed with [QwtCounter::setNumButtons\(\)](#).

Holding the space bar down with focus on a button is the fastest method to step through the counter values. When the counter underflows/overflows, the focus is set to the smallest up/down button and counting is disabled. Counting is re-enabled on a button release event (mouse or space bar).

Example:

```
#include "../include/qwt_counter.h>

QwtCounter *cnt;

cnt = new QwtCounter(parent, name);

cnt->setRange(0.0, 100.0, 1.0);           // From 0.0 to 100, step 1.0
cnt->setNumButtons(2);                   // Two buttons each side
cnt->setIncSteps(QwtCounter::Button1, 1); // Button 1 increments 1 step
cnt->setIncSteps(QwtCounter::Button2, 20); // Button 2 increments 20 steps

connect(cnt, SIGNAL(valueChanged(double)), my_class, SLOT(newValue(double)));
```

6.14.2 Member Enumeration Documentation

6.14.2.1 enum [QwtCounter::Button](#)

Button index

6.14.3 Constructor & Destructor Documentation

6.14.3.1 [QwtCounter::QwtCounter](#) (QWidget * *parent* = NULL) [explicit]

The default number of buttons is set to 2. The default increments are:

- Button 1: 1 step
- Button 2: 10 steps
- Button 3: 100 steps

Parameters:

parent

6.14.3.2 QwtCounter::~~QwtCounter () [virtual]

Destructor.

6.14.4 Member Function Documentation

6.14.4.1 bool QwtCounter::editable () const

returns whether the line edit is edatable. (default is yes)

6.14.4.2 void QwtCounter::setEditable (bool *editable*)

Allow/disallow the user to manually edit the value.

Parameters:

editable true enables editing

See also:

[editable\(\)](#)

6.14.4.3 void QwtCounter::setNumButtons (int *n*)

Specify the number of buttons on each side of the label.

Parameters:

n Number of buttons

6.14.4.4 int QwtCounter::numButtons () const

Returns:

The number of buttons on each side of the widget.

6.14.4.5 void QwtCounter::setIncSteps (QwtCounter::Button *btn*, int *nSteps*)

Specify the number of steps by which the value is incremented or decremented when a specified button is pushed.

Parameters:

btn One of QwtCounter::Button1, QwtCounter::Button2, QwtCounter::Button3

nSteps Number of steps

6.14.4.6 int QwtCounter::incSteps (QwtCounter::Button *btn*) const

Returns:

the number of steps by which a specified button increments the value or 0 if the button is invalid.

Parameters:

btn One of QwtCounter::Button1, QwtCounter::Button2, QwtCounter::Button3

6.14.4.7 void QwtCounter::setValue (double *v*) [virtual]

Set a new value.

Parameters:

v new value Calls [QwtDoubleRange::setValue](#) and does all visual updates.

See also:

[QwtDoubleRange::setValue\(\)](#)

Reimplemented from [QwtDoubleRange](#).

6.14.4.8 QSize QwtCounter::sizeHint () const [virtual]

A size hint.

6.14.4.9 void QwtCounter::polish () [virtual]

Sets the minimum width for the buttons

6.14.4.10 double QwtCounter::step () const

returns the step size

Reimplemented from [QwtDoubleRange](#).

6.14.4.11 void QwtCounter::setStep (double *stepSize*)

Set the step size

Parameters:

stepSize Step size

See also:

[QwtDoubleRange::setStep\(\)](#)

Reimplemented from [QwtDoubleRange](#).

6.14.4.12 double QwtCounter::minVal () const

returns the minimum value of the range

6.14.4.13 void QwtCounter::setMinValue (double *value*)

Set the minimum value of the range

Parameters:

value Minimum value

See also:

[setMaxValue\(\)](#), [minVal\(\)](#)

6.14.4.14 double QwtCounter::maxVal () const

returns the maximum value of the range

6.14.4.15 void QwtCounter::setMaxValue (double *value*)

Set the maximum value of the range

Parameters:

value Maximum value

See also:

[setMinValue\(\)](#), [maxVal\(\)](#)

6.14.4.16 void QwtCounter::setStepButton1 (int *nSteps*)

Set the number of increment steps for button 1

Parameters:

nSteps Number of steps

6.14.4.17 int QwtCounter::stepButton1 () const

returns the number of increment steps for button 1

6.14.4.18 void QwtCounter::setStepButton2 (int *nSteps*)

Set the number of increment steps for button 2

Parameters:

nSteps Number of steps

6.14.4.19 int QwtCounter::stepButton2 () const

returns the number of increment steps for button 2

6.14.4.20 void QwtCounter::setStepButton3 (int *nSteps*)

Set the number of increment steps for button 3

Parameters:

nSteps Number of steps

6.14.4.21 int QwtCounter::stepButton3 () const

returns the number of increment steps for button 3

6.14.4.22 `double QwtCounter::value () const` [virtual]**Returns:**

Current value

Reimplemented from [QwtDoubleRange](#).

6.14.4.23 `void QwtCounter::buttonReleased (double value)` [signal]

This signal is emitted when a button has been released

Parameters:

value The new value

6.14.4.24 `void QwtCounter::valueChanged (double value)` [signal]

This signal is emitted when the counter's value has changed

Parameters:

value The new value

6.14.4.25 `bool QwtCounter::event (QEvent * e)` [protected, virtual]

Handle PolishRequest events

6.14.4.26 `void QwtCounter::wheelEvent (QWheelEvent * e)` [protected, virtual]

Handle wheel events

Parameters:

e Wheel event

6.14.4.27 `void QwtCounter::keyPressEvent (QKeyEvent * e)` [protected, virtual]

Handle key events

- Ctrl + Qt::Key_Home Step to [minValue\(\)](#)
- Ctrl + Qt::Key_End Step to [maxValue\(\)](#)
- Qt::Key_Up Increment by [incSteps\(QwtCounter::Button1\)](#)
- Qt::Key_Down Decrement by [incSteps\(QwtCounter::Button1\)](#)
- Qt::Key_PageUp Increment by [incSteps\(QwtCounter::Button2\)](#)
- Qt::Key_PageDown Decrement by [incSteps\(QwtCounter::Button2\)](#)
- Shift + Qt::Key_PageUp Increment by [incSteps\(QwtCounter::Button3\)](#)
- Shift + Qt::Key_PageDown Decrement by [incSteps\(QwtCounter::Button3\)](#)

6.14.4.28 void QwtCounter::rangeChange () [protected, virtual]

Notify change of range.

This function updates the enabled property of all buttons contained in [QwtCounter](#).


Reimplemented from [QwtDoubleRange](#).

6.15 QwtCPointerData Class Reference

Data class containing two pointers to memory blocks of doubles.

```
#include <qwt_data.h>
```

Inheritance diagram for QwtCPointerData:

**Public Member Functions**

- [QwtCPointerData](#) (const double *x, const double *y, size_t size)
- [QwtCPointerData](#) & `operator=` (const [QwtCPointerData](#) &)
- virtual [QwtData](#) * `copy` () const
- virtual size_t `size` () const
- virtual double `x` (size_t i) const
- virtual double `y` (size_t i) const
- const double * `xData` () const
- const double * `yData` () const
- virtual [QwtDoubleRect](#) `boundingRect` () const

6.15.1 Detailed Description

Data class containing two pointers to memory blocks of doubles.

6.15.2 Constructor & Destructor Documentation**6.15.2.1 QwtCPointerData::QwtCPointerData (const double * x, const double * y, size_t size)**

Constructor

Parameters:

- x* Array of x values
- y* Array of y values
- size* Size of the x and y arrays

Warning:

The programmer must assure that the memory blocks referenced by the pointers remain valid during the lifetime of the [QwtPlotCPointer](#) object.

See also:

[QwtPlotCurve::setData\(\)](#), [QwtPlotCurve::setRawData\(\)](#)

6.15.3 Member Function Documentation

6.15.3.1 [QwtCPointerData](#) & [QwtCPointerData::operator= \(const \[QwtCPointerData\]\(#\) &\)](#)

Assignment.

6.15.3.2 [QwtData](#) * [QwtCPointerData::copy \(\) const](#) [virtual]

Returns:

Pointer to a copy (virtual copy constructor)

Implements [QwtData](#).

6.15.3.3 [size_t](#) [QwtCPointerData::size \(\) const](#) [virtual]

Returns:

Size of the data set

Implements [QwtData](#).

6.15.3.4 [double](#) [QwtCPointerData::x \(size_t *i*\) const](#) [virtual]

Return the x value of data point *i*

Parameters:

i Index

Returns:

x X value of data point *i*

Implements [QwtData](#).

6.15.3.5 [double](#) [QwtCPointerData::y \(size_t *i*\) const](#) [virtual]

Return the y value of data point *i*

Parameters:

i Index

Returns:

y Y value of data point *i*

Implements [QwtData](#).

6.15.3.6 `const double * QwtCPointerData::xData () const`**Returns:**

Array of the x-values

6.15.3.7 `const double * QwtCPointerData::yData () const`**Returns:**

Array of the y-values

6.15.3.8 `QwtDoubleRect QwtCPointerData::boundingRect () const` [virtual]

Returns the bounding rectangle of the data. If there is no bounding rect, like for empty data the rectangle is invalid: `QwtDoubleRect::isValid() == false`


Reimplemented from [QwtData](#).

6.16 QwtCurveFitter Class Reference

Abstract base class for a curve fitter.

```
#include <qwt_curve_fitter.h>
```

Inheritance diagram for QwtCurveFitter:

**Public Member Functions**

- virtual `~QwtCurveFitter ()`
- virtual `QPolygonF fitCurve (const QPolygonF &polygon) const=0`

Protected Member Functions

- `QwtCurveFitter ()`

6.16.1 Detailed Description

Abstract base class for a curve fitter.

6.16.2 Constructor & Destructor Documentation**6.16.2.1** `QwtCurveFitter::~~QwtCurveFitter ()` [virtual]

Destructor.

6.16.2.2 QwtCurveFitter::QwtCurveFitter () [protected]

Constructor.

6.16.3 Member Function Documentation**6.16.3.1 virtual QPolygonF QwtCurveFitter::fitCurve (const QPolygonF & polygon) const** [pure virtual]

Find a curve which has the best fit to a series of data points

Parameters:

polygon Series of data points

Returns:

Curve points


Implemented in [QwtSplineCurveFitter](#).

6.17 QwtData Class Reference

[QwtData](#) defines an interface to any type of curve data.

```
#include <qwt_data.h>
```

Inheritance diagram for QwtData:

**Public Member Functions**

- [QwtData \(\)](#)
- virtual [~QwtData \(\)](#)
- virtual [QwtData * copy \(\)](#) const=0
- virtual [size_t size \(\)](#) const=0
- virtual [double x \(size_t i\)](#) const=0
- virtual [double y \(size_t i\)](#) const=0
- virtual [QwtDoubleRect boundingRect \(\)](#) const

Protected Member Functions

- [QwtData & operator= \(const QwtData &\)](#)

6.17.1 Detailed Description

[QwtData](#) defines an interface to any type of curve data.

Classes, derived from [QwtData](#) may:

- store the data in almost any type of container
- calculate the data on the fly instead of storing it

6.17.2 Constructor & Destructor Documentation

6.17.2.1 [QwtData::QwtData \(\)](#)

Constructor.

6.17.2.2 [QwtData::~~QwtData \(\)](#) [virtual]

Destructor.

6.17.3 Member Function Documentation

6.17.3.1 [virtual \[QwtData*\]\(#\) \[QwtData::copy \\(\\)\]\(#\) const](#) [pure virtual]

Returns:

Pointer to a copy (virtual copy constructor)

Implemented in [QwtPolygonFData](#), [QwtArrayData](#), and [QwtCPointerData](#).

6.17.3.2 [virtual \[size_t\]\(#\) \[QwtData::size \\(\\)\]\(#\) const](#) [pure virtual]

Returns:

Size of the data set

Implemented in [QwtPolygonFData](#), [QwtArrayData](#), and [QwtCPointerData](#).

6.17.3.3 [virtual \[double\]\(#\) \[QwtData::x \\(size_t i\\)\]\(#\) const](#) [pure virtual]

Return the x value of data point *i*

Parameters:

i Index

Returns:

x X value of data point *i*

Implemented in [QwtPolygonFData](#), [QwtArrayData](#), and [QwtCPointerData](#).

6.17.3.4 virtual double QwtData::y (size_t *i*) const [pure virtual]

Return the y value of data point *i*

Parameters:

i Index

Returns:

y Y value of data point *i*

Implemented in [QwtPolygonFData](#), [QwtArrayData](#), and [QwtCPointerData](#).

6.17.3.5 QwtDoubleRect QwtData::boundingRect () const [virtual]

Returns the bounding rectangle of the data. If there is no bounding rect, like for empty data the rectangle is invalid: `QwtDoubleRect::isValid() == false`

Warning:

This is an slow implementation iterating over all points. It is intended to be overloaded by derived classes. In case of auto scaling `boundingRect()` is called for every replot, so it might be worth to implement a cache, or use `x(0)`, `x(size() - 1)` for ordered data ...

Reimplemented in [QwtArrayData](#), and [QwtCPointerData](#).

6.17.3.6 QwtData& QwtData::operator= (const QwtData &) [protected]


Assignment operator (virtualized)

6.18 QwtDial Class Reference

[QwtDial](#) class provides a rounded range control.

```
#include <qwt_dial.h>
```

Inheritance diagram for [QwtDial](#):

**Public Types**

- enum [Shadow](#) {
 - Plain** = `QFrame::Plain`,
 - Raised** = `QFrame::Raised`,
 - Sunken** = `QFrame::Sunken` }

- enum [ScaleOptions](#) {
ScaleBackbone = 1,
ScaleTicks = 2,
ScaleLabel = 4 }
- enum [Mode](#) {
FixedColors,
ScaledColors,
RotateNeedle,
RotateScale }
- enum [Direction](#) {
Clockwise,
CounterClockwise }

Public Member Functions

- [QwtDial](#) (QWidget *parent=NULL)
- virtual [~QwtDial](#) ()
- void [setFrameShadow](#) ([Shadow](#))
- [Shadow](#) [frameShadow](#) () const
- bool [hasVisibleBackground](#) () const
- void [showBackground](#) (bool)
- void [setLineWidth](#) (int)
- int [lineWidth](#) () const
- void [setMode](#) ([Mode](#))
- [Mode](#) [mode](#) () const
- virtual void [setWrapping](#) (bool)
- bool [wrapping](#) () const
- virtual void [setScale](#) (int maxMajIntv, int maxMinIntv, double step=0.0)
- void [setScaleArc](#) (double min, double max)
- void [setScaleOptions](#) (int)
- void [setScaleTicks](#) (int minLen, int medLen, int majLen, int penWidth=1)
- double [minScaleArc](#) () const
- double [maxScaleArc](#) () const
- virtual void [setOrigin](#) (double)
- double [origin](#) () const
- void [setDirection](#) ([Direction](#))
- [Direction](#) [direction](#) () const
- virtual void [setNeedle](#) ([QwtDialNeedle](#) *)
- const [QwtDialNeedle](#) * [needle](#) () const
- [QwtDialNeedle](#) * [needle](#) ()
- QRect [boundingRect](#) () const
- QRect [contentsRect](#) () const
- virtual QRect [scaleContentsRect](#) () const
- virtual QSize [sizeHint](#) () const
- virtual QSize [minimumSizeHint](#) () const
- virtual void [setScaleDraw](#) ([QwtDialScaleDraw](#) *)
- [QwtDialScaleDraw](#) * [scaleDraw](#) ()
- const [QwtDialScaleDraw](#) * [scaleDraw](#) () const

Protected Member Functions

- virtual void [paintEvent](#) (QPaintEvent *)
- virtual void [resizeEvent](#) (QResizeEvent *)
- virtual void [keyPressEvent](#) (QKeyEvent *)
- virtual void [updateMask](#) ()
- virtual void [drawFrame](#) (QPainter *p)
- virtual void [drawContents](#) (QPainter *) const
- virtual void [drawFocusIndicator](#) (QPainter *) const
- virtual void [drawScale](#) (QPainter *, const QPoint ¢er, int radius, double origin, double arcMin, double arcMax) const
- virtual void [drawScaleContents](#) (QPainter *painter, const QPoint ¢er, int radius) const
- virtual void [drawNeedle](#) (QPainter *, const QPoint &, int radius, double direction, QPalette::ColorGroup) const
- virtual [QwtText scaleLabel](#) (double) const
- void [updateScale](#) ()
- virtual void [rangeChange](#) ()
- virtual void [valueChange](#) ()
- virtual double [getValue](#) (const QPoint &)
- virtual void [getScrollMode](#) (const QPoint &, int &scrollMode, int &direction)

Friends

- class [QwtDialScaleDraw](#)

6.18.1 Detailed Description

[QwtDial](#) class provides a rounded range control.

[QwtDial](#) is intended as base class for dial widgets like speedometers, compass widgets, clocks ...

A dial contains a scale and a needle indicating the current value of the dial. Depending on Mode one of them is fixed and the other is rotating. If not [isReadOnly\(\)](#) the dial can be rotated by dragging the mouse or using keyboard inputs (see [keyPressEvent\(\)](#)). A dial might be wrapping, what means a rotation below/above one limit continues on the other limit (f.e compass). The scale might cover any arc of the dial, its values are related to the [origin\(\)](#) of the dial.

Qwt is missing a set of good looking needles ([QwtDialNeedle](#)). Contributions are very welcome.

See also:

[QwtCompass](#), [QwtAnalogClock](#), [QwtDialNeedle](#)

Note:

The examples/dials example shows different types of dials.

6.18.2 Member Enumeration Documentation

6.18.2.1 enum [QwtDial::Shadow](#)

Frame shadow.

Unfortunately it is not possible to use [QFrame::Shadow](#) as a property of a widget that is not derived from [QFrame](#). The following enum is made for the designer only. It is safe to use [QFrame::Shadow](#) instead.

6.18.2.2 enum [QwtDial::ScaleOptions](#)

see [QwtDial::setScaleOptions](#)

6.18.2.3 enum [QwtDial::Mode](#)

In case of RotateNeedle the needle is rotating, in case of RotateScale, the needle points to [origin\(\)](#) and the scale is rotating.

6.18.2.4 enum [QwtDial::Direction](#)

Direction of the dial

6.18.3 Constructor & Destructor Documentation

6.18.3.1 [QwtDial::QwtDial \(QWidget *parent = NULL\)](#) [explicit]

Constructor.

Parameters:

parent Parent widget

Create a dial widget with no scale and no needle. The default origin is 90.0 with no valid value. It accepts mouse and keyboard inputs and has no step size. The default mode is [QwtDial::RotateNeedle](#).

6.18.3.2 [QwtDial::~~QwtDial \(\)](#) [virtual]

Destructor.

6.18.4 Member Function Documentation

6.18.4.1 void [QwtDial::setFrameShadow \(Shadow shadow\)](#)

Sets the frame shadow value from the frame style.

Parameters:

shadow Frame shadow

See also:

[setLineWidth\(\)](#), [QFrame::setFrameShadow\(\)](#)

6.18.4.2 [QwtDial::Shadow QwtDial::frameShadow \(\)](#) const

Returns:

Frame shadow /sa [setFrameShadow\(\)](#), [lineWidth\(\)](#), [QFrame::frameShadow](#)

6.18.4.3 bool QwtDial::hasVisibleBackground () const

true when the area outside of the frame is visible

See also:

[showBackground\(\)](#), [setMask\(\)](#)

6.18.4.4 void QwtDial::showBackground (bool *show*)

Show/Hide the area outside of the frame

Parameters:

show Show if true, hide if false

See also:

[hasVisibleBackground\(\)](#), [setMask\(\)](#)

Warning:

When [QwtDial](#) is a toplevel widget the window border might disappear too.

6.18.4.5 void QwtDial::setLineWidth (int *lineWidth*)

Sets the line width

Parameters:

lineWidth Line width

See also:

[setFrameShadow\(\)](#)

6.18.4.6 int QwtDial::lineWidth () const

Returns:

Line width of the frame

See also:

[setLineWidth\(\)](#), [frameShadow\(\)](#), [lineWidth\(\)](#)

6.18.4.7 void QwtDial::setMode (Mode *mode*)

Change the mode of the meter.

Parameters:

mode New mode

The value of the meter is indicated by the difference between north of the scale and the direction of the needle. In case of `QwtDial::RotateNeedle` north is pointing to the `origin()` and the needle is rotating, in case of `QwtDial::RotateScale`, the needle points to `origin()` and the scale is rotating.

The default mode is `QwtDial::RotateNeedle`.

See also:

[mode\(\)](#), [setValue\(\)](#), [setOrigin\(\)](#)

6.18.4.8 `QwtDial::Mode` `QwtDial::mode () const`

Returns:

mode of the dial.

The value of the dial is indicated by the difference between the origin and the direction of the needle. In case of `QwtDial::RotateNeedle` the scale arc is fixed to the `origin()` and the needle is rotating, in case of `QwtDial::RotateScale`, the needle points to `origin()` and the scale is rotating.

The default mode is `QwtDial::RotateNeedle`.

See also:

[setMode\(\)](#), [origin\(\)](#), [setScaleArc\(\)](#), [value\(\)](#)

6.18.4.9 `void QwtDial::setWrapping (bool wrapping) [virtual]`

Sets whether it is possible to step the value from the highest value to the lowest value and vice versa to on.

Parameters:

wrapping en/disables wrapping

See also:

[wrapping\(\)](#), [QwtDoubleRange::periodic\(\)](#)

Note:

The meaning of wrapping is like the wrapping property of `QSpinBox`, but not like it is used in `QDial`.

6.18.4.10 `bool QwtDial::wrapping () const`

`wrapping()` holds whether it is possible to step the value from the highest value to the lowest value and vice versa.

See also:

[setWrapping\(\)](#), [QwtDoubleRange::setPeriodic\(\)](#)

Note:

The meaning of wrapping is like the wrapping property of `QSpinBox`, but not like it is used in `QDial`.

6.18.4.11 void QwtDial::setScale (int *maxMajIntv*, int *maxMinIntv*, double *step* = 0.0)
[virtual]

Change the intervals of the scale

See also:

[QwtAbstractScaleDraw::setScale\(\)](#)

6.18.4.12 void QwtDial::setScaleArc (double *minArc*, double *maxArc*)

Change the arc of the scale

Parameters:

minArc Lower limit

maxArc Upper limit

6.18.4.13 void QwtDial::setScaleOptions (int *options*)

A wrapper method for accessing the scale draw.

- options == 0
No visible scale: [setScaleDraw\(NULL\)](#)
- options & ScaleBackbone
En/disable the backbone of the scale.
- options & ScaleTicks
En/disable the ticks of the scale.
- options & ScaleLabel
En/disable scale labels

See also:

[QwtAbstractScaleDraw::enableComponent\(\)](#)

6.18.4.14 void QwtDial::setScaleTicks (int *minLen*, int *medLen*, int *majLen*, int *penWidth* = 1)

Assign length and width of the ticks

Parameters:

minLen Length of the minor ticks

medLen Length of the medium ticks

majLen Length of the major ticks

penWidth Width of the pen for all ticks

See also:

[QwtAbstractScaleDraw::setTickLength\(\)](#), [QwtDialScaleDraw::setPenWidth\(\)](#)

6.18.4.15 `double QwtDial::minScaleArc () const`**Returns:**

Lower limit of the scale arc

6.18.4.16 `double QwtDial::maxScaleArc () const`**Returns:**

Upper limit of the scale arc

6.18.4.17 `void QwtDial::setOrigin (double origin) [virtual]`

Change the origin.

The origin is the angle where scale and needle is relative to.

Parameters:

origin New origin

See also:

[origin\(\)](#)

6.18.4.18 `double QwtDial::origin () const`

The origin is the angle where scale and needle is relative to.

Returns:

Origin of the dial

See also:

[setOrigin\(\)](#)

6.18.4.19 `void QwtDial::setDirection (Direction direction)`

Set the direction of the dial (clockwise/counterclockwise)

Direction *direction*

See also:

[direction\(\)](#)

6.18.4.20 QwtDial::Direction QwtDial::direction () const**Returns:**

Direction of the dial

The default direction of a dial is QwtDial::Clockwise

See also:

[setDirection\(\)](#)

6.18.4.21 void QwtDial::setNeedle (QwtDialNeedle * *needle*) [virtual]

Set a needle for the dial

Qwt is missing a set of good looking needles. Contributions are very welcome.

Parameters:

needle Needle

Warning:

The needle will be deleted, when a different needle is set or in [~QwtDial\(\)](#)

6.18.4.22 const QwtDialNeedle * QwtDial::needle () const**Returns:**

needle

See also:

[setNeedle\(\)](#)

6.18.4.23 QwtDialNeedle * QwtDial::needle ()**Returns:**

needle

See also:

[setNeedle\(\)](#)

6.18.4.24 QRect QwtDial::boundingRect () const**Returns:**

bounding rect of the dial including the frame

See also:

[setLineWidth\(\)](#), [scaleContentsRect\(\)](#), [contentsRect\(\)](#)

6.18.4.25 `QRect QwtDial::contentsRect () const`**Returns:**

bounding rect of the circle inside the frame

See also:

[setLineWidth\(\)](#), [scaleContentsRect\(\)](#), [boundingRect\(\)](#)

6.18.4.26 `QRect QwtDial::scaleContentsRect () const` [virtual]**Returns:**

rect inside the scale

See also:

[setLineWidth\(\)](#), [boundingRect\(\)](#), [contentsRect\(\)](#)

6.18.4.27 `QSize QwtDial::sizeHint () const` [virtual]**Returns:**

Size hint

6.18.4.28 `QSize QwtDial::minimumSizeHint () const` [virtual]

Return a minimum size hint.

Warning:

The return value of [QwtDial::minimumSizeHint\(\)](#) depends on the font and the scale.

6.18.4.29 `void QwtDial::setScaleDraw (QwtDialScaleDraw * scaleDraw)` [virtual]

Set an individual scale draw

Parameters:

scaleDraw Scale draw

Warning:

The previous scale draw is deleted

6.18.4.30 `QwtDialScaleDraw * QwtDial::scaleDraw ()`

Return the scale draw.

6.18.4.31 `const QwtDialScaleDraw * QwtDial::scaleDraw () const`

Return the scale draw.

6.18.4.32 void QwtDial::paintEvent (QPaintEvent * *e*) [protected, virtual]

Paint the dial

Parameters:

e Paint event

6.18.4.33 void QwtDial::resizeEvent (QResizeEvent * *e*) [protected, virtual]

Resize the dial widget

Parameters:

e Resize event

6.18.4.34 void QwtDial::keyPressEvent (QKeyEvent * *event*) [protected, virtual]

Handles key events

- Key_Down, KeyLeft
Decrement by 1
- Key_Prior
Decrement by [pageSize\(\)](#)
- Key_Home
Set the value to [minValue\(\)](#)
- Key_Up, KeyRight
Increment by 1
- Key_Next
Increment by [pageSize\(\)](#)
- Key_End
Set the value to [maxValue\(\)](#)

Parameters:

event Key event

See also:

[isReadOnly\(\)](#)

Reimplemented from [QwtAbstractSlider](#).

Reimplemented in [QwtCompass](#).

6.18.4.35 void QwtDial::updateMask () [protected, virtual]

Update the mask of the dial.

In case of "hasVisibleBackground() == false", the background is transparent by a mask.

See also:

[showBackground\(\)](#), [hasVisibleBackground\(\)](#)

6.18.4.36 void QwtDial::drawFrame (QPainter *painter) [protected, virtual]

Draw the frame around the dial

Parameters:

painter Painter

See also:

[lineWidth\(\)](#), [frameShadow\(\)](#)

6.18.4.37 void QwtDial::drawContents (QPainter *painter) const [protected, virtual]

Draw the contents inside the frame.

QColorGroup::Background is the background color outside of the frame. QColorGroup::Base is the background color inside the frame. QColorGroup::Foreground is the background color inside the scale.

Parameters:

painter Painter

See also:

[boundingRect\(\)](#), [contentsRect\(\)](#), [scaleContentsRect\(\)](#), [QWidget::setPalette\(\)](#)

6.18.4.38 void QwtDial::drawFocusIndicator (QPainter *painter) const [protected, virtual]

Draw a dotted round circle, if !isReadOnly()

Parameters:

painter Painter

6.18.4.39 void QwtDial::drawScale (QPainter *painter, const QPoint ¢er, int radius, double origin, double minArc, double maxArc) const [protected, virtual]

Draw the scale

Parameters:

painter Painter

center Center of the dial
radius Radius of the scale
origin Origin of the scale
minArc Minimum of the arc
maxArc Maximum of the arc

See also:

QwtAbstractScaleDraw::setAngleRange()

6.18.4.40 void QwtDial::drawScaleContents (QPainter * *painter*, const QPoint & *center*, int *radius*)
const [protected, virtual]

Draw the contents inside the scale

Paints nothing.

Parameters:

painter Painter
center Center of the contents circle
radius Radius of the contents circle

Reimplemented in [QwtCompass](#).

6.18.4.41 void QwtDial::drawNeedle (QPainter * *painter*, const QPoint & *center*, int *radius*, double *direction*, QPalette::ColorGroup *cg*) const [protected, virtual]

Draw the needle

Parameters:

painter Painter
center Center of the dial
radius Length for the needle
direction Direction of the needle in degrees, counter clockwise
cg ColorGroup

Reimplemented in [QwtAnalogClock](#).

6.18.4.42 [QwtText](#) QwtDial::scaleLabel (double *value*) const [protected, virtual]

Find the label for a value

Parameters:

value Value

Returns:

label

Reimplemented in [QwtAnalogClock](#), and [QwtCompass](#).

6.18.4.43 void QwtDial::updateScale () [protected]

Update the scale with the current attributes

See also:

[setScale\(\)](#)

6.18.4.44 void QwtDial::rangeChange () [protected, virtual]

[QwtDoubleRange](#) update hook.

Reimplemented from [QwtDoubleRange](#).

6.18.4.45 void QwtDial::valueChange () [protected, virtual]

[QwtDoubleRange](#) update hook.

Reimplemented from [QwtAbstractSlider](#).

6.18.4.46 double QwtDial::getValue (const QPoint & pos) [protected, virtual]

Find the value for a given position

Parameters:

pos Position

Returns:

Value

Implements [QwtAbstractSlider](#).

6.18.4.47 void QwtDial::getScrollMode (const QPoint & pos, int & scrollMode, int & direction) [protected, virtual]

See [QwtAbstractSlider::getScrollMode\(\)](#)

Parameters:

pos point where the mouse was pressed

Return values:

scrollMode The scrolling mode

direction direction: 1, 0, or -1.

See also:

[QwtAbstractSlider::getScrollMode\(\)](#)


Implements [QwtAbstractSlider](#).

6.19 QwtDialNeedle Class Reference

Base class for needles that can be used in a [QwtDial](#).

```
#include <qwt_dial_needle.h>
```

Inheritance diagram for QwtDialNeedle:



Public Member Functions

- [QwtDialNeedle](#) ()
- virtual [~QwtDialNeedle](#) ()
- virtual void [draw](#) (QPainter *painter, const QPoint ¢er, int length, double direction, QPalette::ColorGroup cg=QPalette::Active) const=0
- virtual void [setPalette](#) (const QPalette &)
- const QPalette & [palette](#) () const

Static Protected Member Functions

- static void [drawKnob](#) (QPainter *, const QPoint &pos, int width, const QBrush &, bool sunken)

6.19.1 Detailed Description

Base class for needles that can be used in a [QwtDial](#).

[QwtDialNeedle](#) is a pointer that indicates a value by pointing to a specific direction.

Qwt is missing a set of good looking needles. Contributions are very welcome.

See also:

[QwtDial](#), [QwtCompass](#)

6.19.2 Constructor & Destructor Documentation

6.19.2.1 QwtDialNeedle::QwtDialNeedle ()

Constructor.

6.19.2.2 QwtDialNeedle::~~QwtDialNeedle () [virtual]

Destructor.

6.19.3 Member Function Documentation

6.19.3.1 virtual void QwtDialNeedle::draw (QPainter * painter, const QPoint & center, int length, double direction, QPalette::ColorGroup cg = QPalette::Active) const [pure virtual]

Draw the needle

Parameters:

- painter* Painter
- center* Center of the dial, start position for the needle
- length* Length of the needle
- direction* Direction of the needle, in degrees counter clockwise
- cg* Color group, used for painting

Implemented in [QwtDialSimpleNeedle](#), [QwtCompassMagnetNeedle](#), and [QwtCompassWindArrow](#).

6.19.3.2 void QwtDialNeedle::setPalette (const QPalette & palette) [virtual]

Sets the palette for the needle.

Parameters:

- palette* New Palette

6.19.3.3 const QPalette & QwtDialNeedle::palette () const

Returns:

the palette of the needle.

6.19.3.4 void QwtDialNeedle::drawKnob (QPainter *, const QPoint & pos, int width, const QBrush &, bool sunken) [static, protected]


Draw the knob.

6.20 QwtDialScaleDraw Class Reference

A special scale draw made for [QwtDial](#).

```
#include <qwt_dial.h>
```

Inheritance diagram for QwtDialScaleDraw:

**Public Member Functions**

- [QwtDialScaleDraw](#) ([QwtDial](#) *)
- virtual [QwtText](#) label (double value) const
- void [setPenWidth](#) (uint)
- uint [penWidth](#) () const

6.20.1 Detailed Description

A special scale draw made for [QwtDial](#).

See also:

[QwtDial](#), [QwtCompass](#)

6.20.2 Constructor & Destructor Documentation

6.20.2.1 QwtDialScaleDraw::QwtDialScaleDraw ([QwtDial](#) * *parent*) [explicit]

Constructor

Parameters:

parent Parent dial widget

6.20.3 Member Function Documentation

6.20.3.1 [QwtText](#) QwtDialScaleDraw::label (double *value*) const [virtual]

Call [QwtDial::scaleLabel](#) of the parent dial widget.

Parameters:

value Value to display

See also:

[QwtDial::scaleLabel\(\)](#)

Reimplemented from [QwtAbstractScaleDraw](#).

6.20.3.2 void QwtDialScaleDraw::setPenWidth (uint *penWidth*)

Set the pen width used for painting the scale

Parameters:

penWidth Pen width

See also:

[penWidth\(\)](#), [QwtDial::drawScale\(\)](#)

6.20.3.3 uint QwtDialScaleDraw::penWidth () const

Returns:

Pen width used for painting the scale

See also:


[setPenWidth](#), [QwtDial::drawScale\(\)](#)

6.21 QwtDialSimpleNeedle Class Reference

A needle for dial widgets.

```
#include <qwt_dial_needle.h>
```

Inheritance diagram for QwtDialSimpleNeedle:



Public Types

- enum [Style](#) {
 Arrow,
 Ray,
 TriangleStyle,
 ThinStyle,
 Style1,
 Style2,
 NoSymbol = -1,
 Ellipse,
 Rect,
 Diamond,
 Triangle,
 DTriangle,
 UTriangle,
 LTriangle,
 RTriangle,
 Cross,
 XCross,
 HLine,
 VLine,
 Star1,
 Star2,
 Hexagon,
 StyleCnt }

Public Member Functions

- [QwtDialSimpleNeedle](#) ([Style](#), bool hasKnob=true, const QColor &mid=Qt::gray, const QColor &base=Qt::darkGray)
- virtual void [draw](#) (QPainter *, const QPoint &, int length, double direction, QPalette::Color-Group=QPalette::Active) const

- void [setWidth](#) (int width)
- int [width](#) () const

Static Public Member Functions

- static void [drawArrowNeedle](#) (QPainter *, const QPalette &, QPalette::ColorGroup, const QPoint &, int length, int width, double direction, bool hasKnob)
- static void [drawRayNeedle](#) (QPainter *, const QPalette &, QPalette::ColorGroup, const QPoint &, int length, int width, double direction, bool hasKnob)

6.21.1 Detailed Description

A needle for dial widgets.

The following colors are used:

- QColorGroup::Mid
Pointer
- QColorGroup::base
Knob

See also:

[QwtDial](#), [QwtCompass](#)

6.21.2 Member Enumeration Documentation

6.21.2.1 enum [QwtDialSimpleNeedle::Style](#)

Style of the needle.

6.21.3 Constructor & Destructor Documentation

6.21.3.1 [QwtDialSimpleNeedle::QwtDialSimpleNeedle](#) (**Style** style, bool hasKnob = true, const QColor & mid = Qt::gray, const QColor & base = Qt::darkGray)

Constructor

Parameters:

- style* Style
- hasKnob* With/Without knob
- mid* Middle color
- base* Base color

6.21.4 Member Function Documentation

6.21.4.1 void [QwtDialSimpleNeedle::draw](#) (QPainter * painter, const QPoint & center, int length, double direction, QPalette::ColorGroup colorGroup = QPalette::Active) const [virtual]

Draw the needle

Parameters:

painter Painter
center Center of the dial, start position for the needle
length Length of the needle
direction Direction of the needle, in degrees counter clockwise
colorGroup Color group, used for painting

Implements [QwtDialNeedle](#).

6.21.4.2 void `QwtDialSimpleNeedle::drawArrowNeedle` (`QPainter * painter`, `const QPalette & palette`, `QPalette::ColorGroup colorGroup`, `const QPoint & center`, `int length`, `int width`, `double direction`, `bool hasKnob`) [`static`]

Draw a needle looking like an arrow

Parameters:

painter Painter
palette Palette
colorGroup Color group
center center of the needle
length Length of the needle
width Width of the needle
direction Current Direction
hasKnob With/Without knob

6.21.4.3 void `QwtDialSimpleNeedle::drawRayNeedle` (`QPainter * painter`, `const QPalette & palette`, `QPalette::ColorGroup colorGroup`, `const QPoint & center`, `int length`, `int width`, `double direction`, `bool hasKnob`) [`static`]

Draw a needle looking like a ray

Parameters:

painter Painter
palette Palette
colorGroup Color group
center center of the needle
length Length of the needle
width Width of the needle
direction Current Direction
hasKnob With/Without knob

6.21.4.4 void QwtDialSimpleNeedle::setWidth (int *width*)

Set the width of the needle

Parameters:

width Width

See also:

[width\(\)](#)

6.21.4.5 int QwtDialSimpleNeedle::width () const

Returns:

the width of the needle

See also:

[setWidth\(\)](#)

6.22 QwtDoubleInterval Class Reference

A class representing an interval.

```
#include <qwt_double_interval.h>
```

Public Types

- enum [BorderMode](#) {
 IncludeBorders = 0,
 ExcludeMinimum = 1,
 ExcludeMaximum = 2,
 ExcludeBorders = ExcludeMinimum | ExcludeMaximum }

Public Member Functions

- [QwtDoubleInterval](#) ()
- [QwtDoubleInterval](#) (double minValue, double maxValue, int borderFlags=IncludeBorders)
- void [setInterval](#) (double minValue, double maxValue, int borderFlags=IncludeBorders)
- [QwtDoubleInterval normalized](#) () const
- [QwtDoubleInterval inverted](#) () const
- [QwtDoubleInterval limited](#) (double minValue, double maxValue) const
- int [operator==](#) (const [QwtDoubleInterval](#) &) const
- int [operator!=](#) (const [QwtDoubleInterval](#) &) const
- void [setBorderFlags](#) (int)
- int [borderFlags](#) () const
- double [minValue](#) () const
- double [maxValue](#) () const
- double [width](#) () const

- void [setMinValue](#) (double)
- void [setMaxValue](#) (double)
- bool [contains](#) (double value) const
- bool [intersects](#) (const [QwtDoubleInterval](#) &) const
- [QwtDoubleInterval](#) [intersect](#) (const [QwtDoubleInterval](#) &) const
- [QwtDoubleInterval](#) [unite](#) (const [QwtDoubleInterval](#) &) const
- [QwtDoubleInterval](#) [operator|](#) (const [QwtDoubleInterval](#) &) const
- [QwtDoubleInterval](#) [operator&](#) (const [QwtDoubleInterval](#) &) const
- [QwtDoubleInterval](#) & [operator|=](#) (const [QwtDoubleInterval](#) &)
- [QwtDoubleInterval](#) & [operator&=](#) (const [QwtDoubleInterval](#) &)
- [QwtDoubleInterval](#) [extend](#) (double value) const
- [QwtDoubleInterval](#) [operator|](#) (double) const
- [QwtDoubleInterval](#) & [operator|=](#) (double)
- bool [isValid](#) () const
- bool [isNull](#) () const
- void [invalidate](#) ()
- [QwtDoubleInterval](#) [symmetrize](#) (double value) const

6.22.1 Detailed Description

A class representing an interval.

The interval is represented by 2 doubles, the lower and the upper limit.

6.22.2 Member Enumeration Documentation

6.22.2.1 enum [QwtDoubleInterval::BorderMode](#)

Flag indicating if a border is included/excluded from an interval

- [IncludeBorders](#)
min/max values are inside the interval
- [ExcludeMinimum](#)
min value is not included in the interval
- [ExcludeMaximum](#)
max value is not included in the interval
- [ExcludeBorders](#)
min/max values are not included in the interval

See also:

[setBorderMode\(\)](#), [testBorderMode\(\)](#)

6.22.3 Constructor & Destructor Documentation

6.22.3.1 QwtDoubleInterval::QwtDoubleInterval () [inline]

Default Constructor.

Creates an invalid interval [0.0, -1.0]

See also:

[setInterval\(\)](#), [isValid\(\)](#)

6.22.3.2 QwtDoubleInterval::QwtDoubleInterval (double *minValue*, double *maxValue*, int *borderFlags* = IncludeBorders) [inline]

Constructor

Build an interval with from min/max values

Parameters:

minValue Minimum value

maxValue Maximum value

borderFlags Include/Exclude borders

6.22.4 Member Function Documentation

6.22.4.1 void QwtDoubleInterval::setInterval (double *minValue*, double *maxValue*, int *borderFlags* = IncludeBorders) [inline]

Assign the limits of the interval

Parameters:

minValue Minimum value

maxValue Maximum value

borderFlags Include/Exclude borders

6.22.4.2 QwtDoubleInterval QwtDoubleInterval::normalized () const

Normalize the limits of the interval.

If [maxValue\(\)](#) < [minValue\(\)](#) the limits will be inverted.

Returns:

Normalized interval

See also:

[isValid\(\)](#), [inverted\(\)](#)

6.22.4.3 [QwtDoubleInterval](#) QwtDoubleInterval::inverted () const

Invert the limits of the interval

Returns:

Inverted interval

See also:

[normalized\(\)](#)

6.22.4.4 [QwtDoubleInterval](#) QwtDoubleInterval::limited (double *lowerBound*, double *upperBound*) const

Limit the interval, keeping the border modes

Parameters:

lowerBound Lower limit

upperBound Upper limit

Returns:

Limited interval

6.22.4.5 `int QwtDoubleInterval::operator==(const QwtDoubleInterval &) const` [inline]

Compare two intervals.

6.22.4.6 `int QwtDoubleInterval::operator!=(const QwtDoubleInterval &) const` [inline]

Compare two intervals.

6.22.4.7 `void QwtDoubleInterval::setBorderFlags (int borderFlags)` [inline]

Change the border flags

Parameters:

borderFlags Or'd BorderMode flags

See also:

[borderFlags\(\)](#)

6.22.4.8 `int QwtDoubleInterval::borderFlags () const` [inline]

Returns:

Border flags

See also:

[setBorderFlags\(\)](#)

6.22.4.9 `double QwtDoubleInterval::minValue () const` [inline]**Returns:**

Lower limit of the interval

6.22.4.10 `double QwtDoubleInterval::maxValue () const` [inline]**Returns:**

Upper limit of the interval

6.22.4.11 `double QwtDoubleInterval::width () const` [inline]

Return the width of an interval The width of invalid intervals is 0.0, otherwise the result is `maxValue() - minValue()`.

See also:

[isValid\(\)](#)

6.22.4.12 `void QwtDoubleInterval::setMinValue (double minValue)` [inline]

Assign the lower limit of the interval

Parameters:

minValue Minimum value

6.22.4.13 `void QwtDoubleInterval::setMaxValue (double maxValue)` [inline]

Assign the upper limit of the interval

Parameters:

maxValue Maximum value

6.22.4.14 `bool QwtDoubleInterval::contains (double value) const`

Test if a value is inside an interval

Parameters:

value Value

Returns:

true, if `value >= minValue() && value <= maxValue()`

6.22.4.15 `bool QwtDoubleInterval::intersects (const QwtDoubleInterval & other) const`

Test if two intervals overlap

6.22.4.16 [QwtDoubleInterval](#) `QwtDoubleInterval::intersect (const QwtDoubleInterval &) const`

Intersect 2 intervals.

6.22.4.17 [QwtDoubleInterval](#) `QwtDoubleInterval::unite (const QwtDoubleInterval &) const`

Unite 2 intervals.

6.22.4.18 [QwtDoubleInterval](#) `QwtDoubleInterval::operator| (const QwtDoubleInterval & interval) const` `[inline]`

Union of two intervals

See also:

[unite\(\)](#)

6.22.4.19 [QwtDoubleInterval](#) `QwtDoubleInterval::operator & (const QwtDoubleInterval & interval) const` `[inline]`

Intersection of two intervals

See also:

[intersect\(\)](#)

6.22.4.20 [QwtDoubleInterval](#) & `QwtDoubleInterval::operator|= (const QwtDoubleInterval &)`

Unites this interval with the given interval.

6.22.4.21 [QwtDoubleInterval](#) & `QwtDoubleInterval::operator &= (const QwtDoubleInterval &)`

Intersects this interval with the given interval.

6.22.4.22 [QwtDoubleInterval](#) `QwtDoubleInterval::extend (double value) const`

Extend the interval

If *value* is below `minValue`, *value* becomes the lower limit. If *value* is above `maxValue`, *value* becomes the upper limit.

`extend` has no effect for invalid intervals

Parameters:

value Value

See also:

[isValid\(\)](#)

6.22.4.23 [QwtDoubleInterval](#) `QwtDoubleInterval::operator| (double value) const` `[inline]`

Extend an interval

See also:

[extend\(\)](#)

6.22.4.24 `bool QwtDoubleInterval::isValid () const` [inline]

A interval is valid when `minValue() <= maxValue()`. In case of `QwtDoubleInterval::ExcludeBorders` it is true when `minValue() < maxValue()`

6.22.4.25 `bool QwtDoubleInterval::isNull () const` [inline]**Returns:**

true, if `isValid()` && (`minValue() >= maxValue()`)

6.22.4.26 `void QwtDoubleInterval::invalidate ()` [inline]

Invalidate the interval

The limits are set to interval [0.0, -1.0]

See also:

[isValid\(\)](#)

6.22.4.27 `QwtDoubleInterval QwtDoubleInterval::symmetrize (double value) const`

Adjust the limit that is closer to value, so that value becomes the center of the interval.

Parameters:

value Center

Returns:


Interval with value as center

6.23 QwtDoubleRange Class Reference

A class which controls a value within an interval.

```
#include <qwt_double_range.h>
```

Inheritance diagram for QwtDoubleRange:

**Public Member Functions**

- [QwtDoubleRange \(\)](#)

- virtual [~QwtDoubleRange](#) ()
- void [setRange](#) (double vmin, double vmax, double vstep=0.0, int pagesize=1)
- void [setValid](#) (bool)
- bool [isValid](#) () const
- virtual void [setValue](#) (double)
- double [value](#) () const
- void [setPeriodic](#) (bool tf)
- bool [periodic](#) () const
- void [setStep](#) (double)
- double [step](#) () const
- double [maxValue](#) () const
- double [minValue](#) () const
- int [pageSize](#) () const
- virtual void [incValue](#) (int)
- virtual void [incPages](#) (int)
- virtual void [fitValue](#) (double)

Protected Member Functions

- double [exactValue](#) () const
- double [exactPrevValue](#) () const
- double [prevValue](#) () const
- virtual void [valueChange](#) ()
- virtual void [stepChange](#) ()
- virtual void [rangeChange](#) ()

6.23.1 Detailed Description

A class which controls a value within an interval.

This class is useful as a base class or a member for sliders. It represents an interval of type double within which a value can be moved. The value can be either an arbitrary point inside the interval (see [QwtDoubleRange::setValue](#)), or it can be fitted into a step raster (see [QwtDoubleRange::fitValue](#) and [QwtDoubleRange::incValue](#)).

As a special case, a [QwtDoubleRange](#) can be periodic, which means that a value outside the interval will be mapped to a value inside the interval when [QwtDoubleRange::setValue\(\)](#), [QwtDoubleRange::fitValue\(\)](#), [QwtDoubleRange::incValue\(\)](#) or [QwtDoubleRange::incPages\(\)](#) are called.

6.23.2 Constructor & Destructor Documentation

6.23.2.1 QwtDoubleRange::QwtDoubleRange ()

The range is initialized to [0.0, 100.0], the step size to 1.0, and the value to 0.0.

6.23.2.2 QwtDoubleRange::~~QwtDoubleRange () [virtual]

Destroys the [QwtDoubleRange](#).

6.23.3 Member Function Documentation

6.23.3.1 void QwtDoubleRange::setRange (double *vmin*, double *vmax*, double *vstep* = 0.0, int *page-Size* = 1)

Specify range and step size.

Parameters:

- vmin* lower boundary of the interval
- vmax* higher boundary of the interval
- vstep* step width
- pageSize* page size in steps

Warning:

- A change of the range changes the value if it lies outside the new range. The current value will *not* be adjusted to the new step raster.
- $vmax < vmin$ is allowed.
- If the step size is left out or set to zero, it will be set to 1/100 of the interval length.
- If the step size has an absurd value, it will be corrected to a better one.

6.23.3.2 void QwtDoubleRange::setValid (bool)

Set the value to be valid/invalid.

Reimplemented in [QwtAbstractSlider](#).

6.23.3.3 bool QwtDoubleRange::isValid () const

Indicates if the value is valid.

Reimplemented in [QwtAbstractSlider](#).

6.23.3.4 void QwtDoubleRange::setValue (double *x*) [virtual]

Set a new value without adjusting to the step raster.

Parameters:

- x* new value

Warning:

The value is clipped when it lies outside the range. When the range is [QwtDoubleRange::periodic](#), it will be mapped to a point in the interval such that

```
new value := x + n * (max. value - min. value)
```

with an integer number *n*.

Reimplemented in [QwtAbstractSlider](#), and [QwtCounter](#).

6.23.3.5 double QwtDoubleRange::value () const

Returns the current value.

Reimplemented in [QwtCounter](#).

6.23.3.6 void QwtDoubleRange::setPeriodic (bool *tf*)

Make the range periodic.

When the range is periodic, the value will be set to a point inside the interval such that

```
point = value + n * width
```

if the user tries to set a new value which is outside the range. If the range is nonperiodic (the default), values outside the range will be clipped.

Parameters:

tf true for a periodic range

6.23.3.7 bool QwtDoubleRange::periodic () const

Returns true if the range is periodic.

See also:

[setPeriodic\(\)](#)

6.23.3.8 void QwtDoubleRange::setStep (double *vstep*)

Change the step raster.

Parameters:

vstep new step width

Warning:

The value will *not* be adjusted to the new step raster.

Reimplemented in [QwtCounter](#).

6.23.3.9 double QwtDoubleRange::step () const

Returns:

the step size

See also:

[setStep\(\)](#), [setRange\(\)](#)

Reimplemented in [QwtCounter](#).

6.23.3.10 double QwtDoubleRange::maxValue () const

Returns the value of the second border of the range.

maxValue returns the value which has been specified as the second parameter in [QwtDoubleRange::setRange](#).

See also:

[setRange\(\)](#)

6.23.3.11 double QwtDoubleRange::minValue () const

Returns the value at the first border of the range.

minValue returns the value which has been specified as the first parameter in [setRange\(\)](#).

See also:

[setRange\(\)](#)

6.23.3.12 int QwtDoubleRange::pageSize () const

Returns the page size in steps.

6.23.3.13 void QwtDoubleRange::incValue (int *nSteps*) [virtual]

Increment the value by a specified number of steps.

Parameters:

nSteps Number of steps to increment

Warning:

As a result of this operation, the new value will always be adjusted to the step raster.

Reimplemented in [QwtAbstractSlider](#).

6.23.3.14 void QwtDoubleRange::incPages (int *nPages*) [virtual]

Increment the value by a specified number of pages.

Parameters:

nPages Number of pages to increment. A negative number decrements the value.

Warning:

The Page size is specified in the constructor.

6.23.3.15 void QwtDoubleRange::fitValue (double x) [virtual]

Adjust the value to the closest point in the step raster.

Parameters:

x value

Warning:

The value is clipped when it lies outside the range. When the range is [QwtDoubleRange::periodic](#), it will be mapped to a point in the interval such that

```
new value := x + n * (max. value - min. value)
```

with an integer number *n*.

Reimplemented in [QwtAbstractSlider](#).

6.23.3.16 double QwtDoubleRange::exactValue () const [protected]

Returns the exact value.

The exact value is the value which [QwtDoubleRange::value](#) would return if the value were not adjusted to the step raster. It differs from the current value only if [QwtDoubleRange::fitValue](#) or [QwtDoubleRange::incValue](#) have been used before. This function is intended for internal use in derived classes.

6.23.3.17 double QwtDoubleRange::exactPrevValue () const [protected]

Returns the exact previous value.

6.23.3.18 double QwtDoubleRange::prevValue () const [protected]

Returns the previous value.

6.23.3.19 void QwtDoubleRange::valueChange () [protected, virtual]

Notify a change of value.

This virtual function is called whenever the value changes. The default implementation does nothing.

Reimplemented in [QwtAbstractSlider](#), [QwtDial](#), [QwtSlider](#), and [QwtWheel](#).

6.23.3.20 void QwtDoubleRange::stepChange () [protected, virtual]

Notify a change of the step size.

This virtual function is called whenever the step size changes. The default implementation does nothing.

6.23.3.21 void QwtDoubleRange::rangeChange () [protected, virtual]

Notify a change of the range.

This virtual function is called whenever the range changes. The default implementation does nothing.

Reimplemented in [QwtCounter](#), [QwtDial](#), and [QwtSlider](#).

6.24 QwtDynGridLayout Class Reference

The [QwtDynGridLayout](#) class lays out widgets in a grid, adjusting the number of columns and rows to the current size.

```
#include <qwt_dyngrid_layout.h>
```

Public Member Functions

- [QwtDynGridLayout](#) (QWidget *, int margin=0, int space=-1)
- [QwtDynGridLayout](#) (int space=-1)
- virtual [~QwtDynGridLayout](#) ()
- virtual void [invalidate](#) ()
- void [setMaxCols](#) (uint maxCols)
- uint [maxCols](#) () const
- uint [numRows](#) () const
- uint [numCols](#) () const
- virtual void [addItem](#) (QLayoutItem *)
- virtual QLayoutItem * [itemAt](#) (int index) const
- virtual QLayoutItem * [takeAt](#) (int index)
- virtual int [count](#) () const
- void [setExpandingDirections](#) (Qt::Orientations)
- virtual Qt::Orientations [expandingDirections](#) () const
- QList< QRect > [layoutItems](#) (const QRect &, uint numCols) const
- virtual int [maxItemWidth](#) () const
- virtual void [setGeometry](#) (const QRect &rect)
- virtual bool [hasHeightForWidth](#) () const
- virtual int [heightForWidth](#) (int) const
- virtual QSize [sizeHint](#) () const
- virtual bool [isEmpty](#) () const
- uint [itemCount](#) () const
- virtual uint [columnsForWidth](#) (int width) const

Protected Member Functions

- void [layoutGrid](#) (uint numCols, QwtArray< int > &rowHeight, QwtArray< int > &colWidth) const
- void [stretchGrid](#) (const QRect &rect, uint numCols, QwtArray< int > &rowHeight, QwtArray< int > &colWidth) const

6.24.1 Detailed Description

The [QwtDynGridLayout](#) class lays out widgets in a grid, adjusting the number of columns and rows to the current size.

[QwtDynGridLayout](#) takes the space it gets, divides it up into rows and columns, and puts each of the widgets it manages into the correct cell(s). It lays out as many number of columns as possible (limited by [maxCols\(\)](#)).

6.24.2 Constructor & Destructor Documentation

6.24.2.1 `QwtDynGridLayout::QwtDynGridLayout (QWidget * parent, int margin = 0, int spacing = -1)` `[explicit]`

Parameters:

parent Parent widget

margin Margin

spacing Spacing

6.24.2.2 `QwtDynGridLayout::QwtDynGridLayout (int spacing = -1)` `[explicit]`

Parameters:

spacing Spacing

6.24.2.3 `QwtDynGridLayout::~~QwtDynGridLayout ()` `[virtual]`

Destructor.

6.24.3 Member Function Documentation

6.24.3.1 `void QwtDynGridLayout::invalidate ()` `[virtual]`

Invalidate all internal caches.

6.24.3.2 `void QwtDynGridLayout::setMaxCols (uint maxCols)`

Limit the number of columns.

Parameters:

maxCols upper limit, 0 means unlimited

See also:

[maxCols\(\)](#)

6.24.3.3 `uint QwtDynGridLayout::maxCols () const`

Return the upper limit for the number of columns. 0 means unlimited, what is the default.

See also:

[setMaxCols\(\)](#)

6.24.3.4 `uint QwtDynGridLayout::numRows () const`

Returns:

Number of rows of the current layout.

See also:

[numCols\(\)](#)

Warning:

The number of rows might change whenever the geometry changes

6.24.3.5 `uint QwtDynGridLayout::numCols () const`

Returns:

Number of columns of the current layout.

See also:

[numRows\(\)](#)

Warning:

The number of columns might change whenever the geometry changes

6.24.3.6 `void QwtDynGridLayout::addItem (QLayoutItem *) [virtual]`

Adds item to the next free position.

6.24.3.7 `QLayoutItem * QwtDynGridLayout::itemAt (int index) const [virtual]`

Find the item at a specific index

Parameters:

index Index

See also:

[takeAt\(\)](#)

6.24.3.8 `QLayoutItem * QwtDynGridLayout::takeAt (int index) [virtual]`

Find the item at a specific index and remove it from the layout

Parameters:

index Index

See also:

[itemAt\(\)](#)

6.24.3.9 `int QwtDynGridLayout::count () const` [virtual]**Returns:**

Number of items in the layout

6.24.3.10 `void QwtDynGridLayout::setExpandingDirections (Qt::Orientations expanding)`

Set whether this layout can make use of more space than `sizeHint()`. A value of `Qt::Vertical` or `Qt::Horizontal` means that it wants to grow in only one dimension, while `Qt::Vertical | Qt::Horizontal` means that it wants to grow in both dimensions. The default value is 0.

Parameters:

expanding Or'd orientations

See also:

[expandingDirections\(\)](#)

6.24.3.11 `Qt::Orientations QwtDynGridLayout::expandingDirections () const` [virtual]

Returns whether this layout can make use of more space than `sizeHint()`. A value of `Qt::Vertical` or `Qt::Horizontal` means that it wants to grow in only one dimension, while `Qt::Vertical | Qt::Horizontal` means that it wants to grow in both dimensions.

See also:

[setExpandingDirections\(\)](#)

6.24.3.12 `QList< QRect > QwtDynGridLayout::layoutItems (const QRect & rect, uint numCols) const`

Calculate the geometries of the layout items for a layout with `numCols` columns and a given `rect`.

Parameters:

rect Rect where to place the items

numCols Number of columns

Returns:

item geometries

6.24.3.13 `int QwtDynGridLayout::maxItemWidth () const` [virtual]**Returns:**

the maximum width of all layout items

6.24.3.14 void QwtDynGridLayout::setGeometry (const QRect & *rect*) [virtual]

Reorganizes columns and rows and resizes managed widgets within the rectangle *rect*.

Parameters:

rect Layout geometry

6.24.3.15 bool QwtDynGridLayout::hasHeightForWidth () const [virtual]**Returns:**

true: [QwtDynGridLayout](#) implements heightForWidth.

See also:

[heightForWidth\(\)](#)

6.24.3.16 int QwtDynGridLayout::heightForWidth (int *width*) const [virtual]**Returns:**

The preferred height for this layout, given the width *w*.

See also:

[hasHeightForWidth\(\)](#)

6.24.3.17 QSize QwtDynGridLayout::sizeHint () const [virtual]

Return the size hint. If [maxCols\(\)](#) > 0 it is the size for a grid with [maxCols\(\)](#) columns, otherwise it is the size for a grid with only one row.

See also:

[maxCols\(\)](#), [setMaxCols\(\)](#)

6.24.3.18 bool QwtDynGridLayout::isEmpty () const [virtual]**Returns:**

true if this layout is empty.

6.24.3.19 uint QwtDynGridLayout::itemCount () const**Returns:**

number of layout items

6.24.3.20 `uint QwtDynGridLayout::columnsForWidth (int width) const` [virtual]

Calculate the number of columns for a given width. It tries to use as many columns as possible (limited by `maxCols()`)

Parameters:

width Available width for all columns

See also:

`maxCols()`, `setMaxCols()`

6.24.3.21 `void QwtDynGridLayout::layoutGrid (uint numCols, QwtArray< int > & rowHeight, QwtArray< int > & colWidth) const` [protected]

Calculate the dimensions for the columns and rows for a grid of `numCols` columns.

Parameters:

numCols Number of columns.

rowHeight Array where to fill in the calculated row heights.

colWidth Array where to fill in the calculated column widths.

6.24.3.22 `void QwtDynGridLayout::stretchGrid (const QRect & rect, uint numCols, QwtArray< int > & rowHeight, QwtArray< int > & colWidth) const` [protected]

Stretch columns in case of `expanding()` & `QSizePolicy::Horizontal` and rows in case of `expanding()` & `QSizePolicy::Vertical` to fill the entire `rect`. Rows and columns are stretched with the same factor.

See also:


`setExpanding()`, `expanding()`

6.25 QwtEventPattern Class Reference

A collection of event patterns.

```
#include <qwt_event_pattern.h>
```

Inheritance diagram for QwtEventPattern:



Public Types

- enum [MousePatternCode](#) {
 MouseSelect1,
 MouseSelect2,
 MouseSelect3,
 MouseSelect4,
 MouseSelect5,
 MouseSelect6,
 MousePatternCount }
- enum [KeyPatternCode](#) {
 KeySelect1,
 KeySelect2,
 KeyAbort,
 KeyLeft,
 KeyRight,
 KeyUp,
 KeyDown,
 KeyRedo,
 KeyUndo,
 KeyHome,
 KeyPatternCount }

Public Member Functions

- [QwtEventPattern](#) ()
- virtual [~QwtEventPattern](#) ()
- void [initMousePattern](#) (int numButtons)
- void [initKeyPattern](#) ()
- void [setMousePattern](#) (uint pattern, int button, int state=Qt::NoButton)
- void [setKeyPattern](#) (uint pattern, int key, int state=Qt::NoButton)
- void [setMousePattern](#) (const QwtArray< [MousePattern](#) > &)
- void [setKeyPattern](#) (const QwtArray< [KeyPattern](#) > &)
- const QwtArray< [MousePattern](#) > & [mousePattern](#) () const
- const QwtArray< [KeyPattern](#) > & [keyPattern](#) () const
- QwtArray< [MousePattern](#) > & [mousePattern](#) ()
- QwtArray< [KeyPattern](#) > & [keyPattern](#) ()
- bool [mouseMatch](#) (uint pattern, const QMouseEvent *) const
- bool [keyMatch](#) (uint pattern, const QKeyEvent *) const

Protected Member Functions

- virtual bool [mouseMatch](#) (const [MousePattern](#) &, const QMouseEvent *) const
- virtual bool [keyMatch](#) (const [KeyPattern](#) &, const QKeyEvent *) const

Classes

- class [KeyPattern](#)
A pattern for key events.
- class [MousePattern](#)
A pattern for mouse events.

6.25.1 Detailed Description

A collection of event patterns.

[QwtEventPattern](#) introduces an level of indirection for mouse and keyboard inputs. Those are represented by symbolic names, so the application code can be configured by individual mappings.

See also:

[QwtPicker](#), [QwtPickerMachine](#), [QwtPlotZoomer](#)

6.25.2 Member Enumeration Documentation

6.25.2.1 enum [QwtEventPattern::MousePatternCode](#)

Symbolic mouse input codes.

The default initialization for 3 button mice is:

- MouseSelect1
Qt::LeftButton
- MouseSelect2
Qt::RightButton
- MouseSelect3
Qt::MidButton
- MouseSelect4
Qt::LeftButton + Qt::ShiftButton
- MouseSelect5
Qt::RightButton + Qt::ShiftButton
- MouseSelect6
Qt::MidButton + Qt::ShiftButton

The default initialization for 2 button mice is:

- MouseSelect1
Qt::LeftButton
- MouseSelect2
Qt::RightButton

- MouseSelect3
Qt::LeftButton + Qt::AltButton
- MouseSelect4
Qt::LeftButton + Qt::ShiftButton
- MouseSelect5
Qt::RightButton + Qt::ShiftButton
- MouseSelect6
Qt::LeftButton + Qt::AltButton + Qt::ShiftButton

The default initialization for 1 button mice is:

- MouseSelect1
Qt::LeftButton
- MouseSelect2
Qt::LeftButton + Qt::ControlButton
- MouseSelect3
Qt::LeftButton + Qt::AltButton
- MouseSelect4
Qt::LeftButton + Qt::ShiftButton
- MouseSelect5
Qt::LeftButton + Qt::ControlButton + Qt::ShiftButton
- MouseSelect6
Qt::LeftButton + Qt::AltButton + Qt::ShiftButton

See also:

[initMousePattern\(\)](#)

6.25.2.2 enum QwtEventPattern::KeyPatternCode

Symbolic keyboard input codes.

Default initialization:

- KeySelect1
Qt::Key_Return
- KeySelect2
Qt::Key_Space
- KeyAbort
Qt::Key_Escape
- KeyLeft
Qt::Key_Left

- KeyRight
Qt::Key_Right
- KeyUp
Qt::Key_Up
- KeyDown
Qt::Key_Down
- KeyUndo
Qt::Key_Minus
- KeyRedo
Qt::Key_Plus
- KeyHome
Qt::Key_Escape

6.25.3 Constructor & Destructor Documentation

6.25.3.1 QwtEventPattern::QwtEventPattern ()

Constructor

See also:

[MousePatternCode](#), [KeyPatternCode](#)

6.25.3.2 QwtEventPattern::~~QwtEventPattern () [virtual]

Destructor.

6.25.4 Member Function Documentation

6.25.4.1 void QwtEventPattern::initMousePattern (int *numButtons*)

Set default mouse patterns, depending on the number of mouse buttons

Parameters:

numButtons Number of mouse buttons (<= 3)

See also:

[MousePatternCode](#)

6.25.4.2 void QwtEventPattern::initKeyPattern ()

Set default mouse patterns.

See also:

[KeyPatternCode](#)

6.25.4.3 `void QwtEventPattern::setMousePattern (uint pattern, int button, int state = Qt::NoButton)`

Change one mouse pattern

Parameters:

pattern Index of the pattern

button Button

state State

See also:

QMouseEvent

6.25.4.4 `void QwtEventPattern::setKeyPattern (uint pattern, int key, int state = Qt::NoButton)`

Change one key pattern

Parameters:

pattern Index of the pattern

key Key

state State

See also:

QKeyEvent

6.25.4.5 `void QwtEventPattern::setMousePattern (const QwtArray< MousePattern > &)`

Change the mouse event patterns.

6.25.4.6 `void QwtEventPattern::setKeyPattern (const QwtArray< KeyPattern > &)`

Change the key event patterns.

6.25.4.7 `const QwtArray< QwtEventPattern::MousePattern > & QwtEventPattern::mousePattern () const`

Return mouse patterns.

6.25.4.8 `const QwtArray< QwtEventPattern::KeyPattern > & QwtEventPattern::keyPattern () const`

Return key patterns.

6.25.4.9 `QwtArray< QwtEventPattern::MousePattern > & QwtEventPattern::mousePattern ()`

Return mouse patterns.

6.25.4.10 `QwtArray< QwtEventPattern::KeyPattern > & QwtEventPattern::keyPattern ()`

Return Key patterns.

6.25.4.11 `bool QwtEventPattern::mouseMatch (uint pattern, const QMouseEvent * e) const`

Compare a mouse event with an event pattern.

A mouse event matches the pattern when both have the same button value and in the state value the same key flags (Qt::KeyButtonMask) are set.

Parameters:

pattern Index of the event pattern

e Mouse event

Returns:

true if matches

See also:

[keyMatch\(\)](#)

6.25.4.12 `bool QwtEventPattern::keyMatch (uint pattern, const QKeyEvent * e) const`

Compare a key event with an event pattern.

A key event matches the pattern when both have the same key value and in the state value the same key flags (Qt::KeyButtonMask) are set.

Parameters:

pattern Index of the event pattern

e Key event

Returns:

true if matches

See also:

[mouseMatch\(\)](#)

6.25.4.13 `bool QwtEventPattern::mouseMatch (const MousePattern & pattern, const QMouseEvent * e) const` [protected, virtual]

Compare a mouse event with an event pattern.

A mouse event matches the pattern when both have the same button value and in the state value the same key flags (Qt::KeyButtonMask) are set.

Parameters:

pattern Mouse event pattern

e Mouse event

Returns:

true if matches

See also:

[keyMatch\(\)](#)

6.25.4.14 `bool QwtEventPattern::keyMatch (const KeyPattern & pattern, const QKeyEvent * e)`
const [protected, virtual]

Compare a key event with an event pattern.

A key event matches the pattern when both have the same key value and in the state value the same key flags (Qt::KeyButtonMask) are set.

Parameters:

pattern Key event pattern

e Key event

Returns:

true if matches

See also:

[mouseMatch\(\)](#)

6.26 QwtEventPattern::KeyPattern Class Reference

A pattern for key events.

```
#include <qwt_event_pattern.h>
```

Public Member Functions

- **KeyPattern** (int k=0, int st=Qt::NoButton)

Public Attributes

- int **key**
- int **state**

6.26.1 Detailed Description

A pattern for key events.

6.27 QwtEventPattern::MousePattern Class Reference

A pattern for mouse events.

```
#include <qwt_event_pattern.h>
```

Public Member Functions

- **MousePattern** (int btn=Qt::NoButton, int st=Qt::NoButton)

Public Attributes

- int **button**
- int **state**

6.27.1 Detailed Description

A pattern for mouse events.

6.28 QwtIntervalData Class Reference

Series of samples of a value and an interval.

```
#include <qwt_interval_data.h>
```

Public Member Functions

- [QwtIntervalData](#) ()
- [QwtIntervalData](#) (const QwtArray< [QwtDoubleInterval](#) > &, const QwtArray< double > &)
- [~QwtIntervalData](#) ()
- void [setData](#) (const QwtArray< [QwtDoubleInterval](#) > &, const QwtArray< double > &)
- size_t [size](#) () const
- const [QwtDoubleInterval](#) & [interval](#) (size_t i) const
- double [value](#) (size_t i) const
- [QwtDoubleRect](#) [boundingRect](#) () const

6.28.1 Detailed Description

Series of samples of a value and an interval.

[QwtIntervalData](#) is a series of samples of a value and an interval. F.e. error bars are built from samples [x, y1-y2], while a histogram might consist of [x1-x2, y] samples.

6.28.2 Constructor & Destructor Documentation**6.28.2.1 QwtIntervalData::QwtIntervalData ()**

Constructor.

6.28.2.2 QwtIntervalData::QwtIntervalData (const QwtArray< [QwtDoubleInterval](#) > &, const QwtArray< double > &)

Constructor.

6.28.2.3 QwtIntervalData::~~QwtIntervalData ()

Destructor.

6.28.3 Member Function Documentation

6.28.3.1 `void QwtIntervalData::setData (const QwtArray< QwtDoubleInterval > &, const QwtArray< double > &)`

Assign samples.

6.28.3.2 `size_t QwtIntervalData::size () const` [*inline*]

Returns:

Number of samples

6.28.3.3 `const QwtDoubleInterval & QwtIntervalData::interval (size_t i) const` [*inline*]

Interval of a sample

Parameters:

i Sample index

Returns:

Interval

See also:

[value\(\)](#), [size\(\)](#)

6.28.3.4 `double QwtIntervalData::value (size_t i) const` [*inline*]

Value of a sample

Parameters:

i Sample index

Returns:

Value

See also:

[interval\(\)](#), [size\(\)](#)

6.28.3.5 `QwtDoubleRect QwtIntervalData::boundingRect () const`

Calculate the bounding rectangle of the samples

The x coordinates of the rectangle are built from the intervals, the y coordinates from the values.

Returns:


Bounding rectangle

6.29 QwtKnob Class Reference

The Knob Widget.

```
#include <qwt_knob.h>
```

Inheritance diagram for QwtKnob:



Public Types

- enum [Symbol](#) {
Line,
Dot }

Public Member Functions

- [QwtKnob](#) (QWidget *parent=NULL)
- virtual [~QwtKnob](#) ()
- void [setKnobWidth](#) (int w)
- int [knobWidth](#) () const
- void [setTotalAngle](#) (double angle)
- double [totalAngle](#) () const
- void [setBorderWidth](#) (int bw)
- int [borderWidth](#) () const
- void [setSymbol](#) (Symbol)
- [Symbol](#) [symbol](#) () const
- virtual QSize [sizeHint](#) () const
- virtual QSize [minimumSizeHint](#) () const
- void [setScaleDraw](#) (QwtRoundScaleDraw *)
- const [QwtRoundScaleDraw](#) * [scaleDraw](#) () const
- [QwtRoundScaleDraw](#) * [scaleDraw](#) ()

Protected Member Functions

- virtual void [paintEvent](#) (QPaintEvent *e)
- virtual void [resizeEvent](#) (QResizeEvent *e)
- void [draw](#) (QPainter *p, const QRect &ur)
- void [drawKnob](#) (QPainter *p, const QRect &r)
- void [drawMarker](#) (QPainter *p, double arc, const QColor &c)

6.29.1 Detailed Description

The Knob Widget.

The [QwtKnob](#) widget imitates look and behaviour of a volume knob on a radio. It contains a scale around the knob which is set up automatically or can be configured manually (see [QwtAbstractScale](#)). Automatic scrolling is enabled when the user presses a mouse button on the scale. For a description of signals, slots and other members, see [QwtAbstractSlider](#).

See also:

[QwtAbstractSlider](#) and [QwtAbstractScale](#) for the descriptions of the inherited members.

6.29.2 Member Enumeration Documentation

6.29.2.1 enum [QwtKnob::Symbol](#)

Symbol

See also:

[QwtKnob::QwtKnob\(\)](#)

6.29.3 Constructor & Destructor Documentation

6.29.3.1 [QwtKnob::QwtKnob \(QWidget * *parent* = NULL\)](#) [explicit]

Constructor

Parameters:

parent Parent widget

6.29.3.2 [QwtKnob::~~QwtKnob \(\)](#) [virtual]

Destructor.

6.29.4 Member Function Documentation

6.29.4.1 void [QwtKnob::setKnobWidth \(int *w*\)](#)

Change the knob's width.

The specified width must be ≥ 5 , or it will be clipped.

Parameters:

w New width

6.29.4.2 int [QwtKnob::knobWidth \(\)](#) const

Return the width of the knob.

6.29.4.3 void QwtKnob::setTotalAngle (double *angle*)

Set the total angle by which the knob can be turned.

Parameters:

angle Angle in degrees.

The default angle is 270 degrees. It is possible to specify an angle of more than 360 degrees so that the knob can be turned several times around its axis.

6.29.4.4 double QwtKnob::totalAngle () const

Return the total angle.

6.29.4.5 void QwtKnob::setBorderWidth (int *bw*)

Set the knob's border width.

Parameters:

bw new border width

6.29.4.6 int QwtKnob::borderWidth () const

Return the border width.

6.29.4.7 void QwtKnob::setSymbol ([QwtKnob::Symbol](#) *s*)

Set the symbol of the knob.

See also:

[symbol\(\)](#)

6.29.4.8 [QwtKnob::Symbol](#) QwtKnob::symbol () const**Returns:**

symbol of the knob

See also:

[setSymbol\(\)](#)

6.29.4.9 QSize QwtKnob::sizeHint () const [virtual]**Returns:**

[minimumSizeHint\(\)](#)

6.29.4.10 `QSize QwtKnob::minimumSizeHint () const` [virtual]

Return a minimum size hint.

Warning:

The return value of `QwtKnob::minimumSizeHint()` depends on the font and the scale.

6.29.4.11 `void QwtKnob::setScaleDraw (QwtRoundScaleDraw * scaleDraw)`

Change the scale draw of the knob

For changing the labels of the scales, it is necessary to derive from `QwtRoundScaleDraw` and overload `QwtRoundScaleDraw::label()`.

See also:

[scaleDraw\(\)](#)

6.29.4.12 `const QwtRoundScaleDraw * QwtKnob::scaleDraw () const`**Returns:**

the scale draw of the knob

See also:

[setScaleDraw\(\)](#)

6.29.4.13 `QwtRoundScaleDraw * QwtKnob::scaleDraw ()`**Returns:**

the scale draw of the knob

See also:

[setScaleDraw\(\)](#)

6.29.4.14 `void QwtKnob::paintEvent (QPaintEvent * e)` [protected, virtual]

Repaint the knob

Parameters:

e Paint event

6.29.4.15 `void QwtKnob::resizeEvent (QResizeEvent * e)` [protected, virtual]

Qt Resize Event

6.29.4.16 void QwtKnob::draw (QPainter * *painter*, const QRect & *rect*) [protected]

Repaint the knob

Parameters:

painter Painter

rect Update rectangle

6.29.4.17 void QwtKnob::drawKnob (QPainter * *painter*, const QRect & *r*) [protected]

Draw the knob.

Parameters:

painter painter

r Bounding rectangle of the knob (without scale)

6.29.4.18 void QwtKnob::drawMarker (QPainter * *p*, double *arc*, const QColor & *c*) [protected]

Draw the marker at the knob's front.

Parameters:

p Painter

arc Angle of the marker

c Marker color

6.30 QwtLegend Class Reference

The legend widget.

```
#include <qwt_legend.h>
```

Public Types

- enum [LegendDisplayPolicy](#) {
 NoIdentifier = 0,
 FixedIdentifier = 1,
 AutoIdentifier = 2 }
- enum [LegendItemMode](#) {
 ReadOnlyItem,
 ClickableItem,
 CheckableItem }

Public Member Functions

- [QwtLegend](#) (QWidget *parent=NULL)
- virtual [~QwtLegend](#) ()
- void [setDisplayPolicy](#) ([LegendDisplayPolicy](#) policy, int mode)
- [LegendDisplayPolicy](#) [displayPolicy](#) () const
- void [setItemMode](#) ([LegendItemMode](#))
- [LegendItemMode](#) [itemMode](#) () const
- int [identifierMode](#) () const
- QWidget * [contentsWidget](#) ()
- const QWidget * [contentsWidget](#) () const
- void [insert](#) (const [QwtLegendItemManager](#) *, QWidget *)
- void [remove](#) (const [QwtLegendItemManager](#) *)
- QWidget * [find](#) (const [QwtLegendItemManager](#) *) const
- [QwtLegendItemManager](#) * [find](#) (const QWidget *) const
- virtual QList< QWidget * > [legendItems](#) () const
- void [clear](#) ()
- bool [isEmpty](#) () const
- uint [itemCount](#) () const
- virtual bool [eventFilter](#) (QObject *, QEvent *)
- virtual QSize [sizeHint](#) () const
- virtual int [heightForWidth](#) (int w) const
- QScrollBar * [horizontalScrollBar](#) () const
- QScrollBar * [verticalScrollBar](#) () const

Protected Member Functions

- virtual void [resizeEvent](#) (QResizeEvent *)
- virtual void [layoutContents](#) ()

6.30.1 Detailed Description

The legend widget.

The [QwtLegend](#) widget is a tabular arrangement of legend items. Legend items might be any type of widget, but in general they will be a [QwtLegendItem](#).

See also:

[QwtLegendItem](#), [QwtLegendItemManager](#) [QwtPlot](#)

6.30.2 Member Enumeration Documentation

6.30.2.1 enum [QwtLegend::LegendDisplayPolicy](#)

Display policy.

- NoIdentifier

The client code is responsible how to display of each legend item. The Qwt library will not interfere.

- FixedIdentifier

All legend items are displayed with the [QwtLegendItem::IdentifierMode](#) to be passed in 'mode'.

- AutoIdentifier

Each legend item is displayed with a mode that is a bitwise or of

- [QwtLegendItem::ShowLine](#) (if its curve is drawn with a line) and
- [QwtLegendItem::ShowSymbol](#) (if its curve is drawn with symbols) and
- [QwtLegendItem::ShowText](#) (if the has a title).

Default is AutoIdentifier.

See also:

[setDisplayPolicy\(\)](#), [displayPolicy\(\)](#), [QwtLegendItem::IdentifierMode](#)

6.30.2.2 enum [QwtLegend::LegendItemMode](#)

Interaction mode for the legend items.

- ReadOnlyItem

The legend item is not interactive, like a label

- ClickableItem

The legend item is clickable, like a push button

- CheckableItem

The legend item is checkable, like a checkable button

Default is ReadOnlyItem.

See also:

[setItemMode\(\)](#), [itemMode\(\)](#), [QwtLegendItem::IdentifierMode](#) [QwtLegendItem::clicked\(\)](#), [QwtLegendItem::checked\(\)](#), [QwtPlot::legendClicked\(\)](#), [QwtPlot::legendChecked\(\)](#)

6.30.3 Constructor & Destructor Documentation

6.30.3.1 [QwtLegend::QwtLegend \(QWidget *parent = NULL\) \[explicit\]](#)

Constructor

Parameters:

parent Parent widget

6.30.3.2 [QwtLegend::~QwtLegend \(\) \[virtual\]](#)

Destructor.

6.30.4 Member Function Documentation

6.30.4.1 void QwtLegend::setDisplayPolicy ([LegendDisplayPolicy](#) policy, int mode)

Set the legend display policy to:

Parameters:

policy Legend display policy

mode Identifier mode (or'd ShowLine, ShowSymbol, ShowText)

See also:

[displayPolicy\(\)](#), [LegendDisplayPolicy](#)

6.30.4.2 [QwtLegend::LegendDisplayPolicy](#) QwtLegend::displayPolicy () const

Returns:

the legend display policy. Default is LegendDisplayPolicy::Auto.

See also:

[setDisplayPolicy\(\)](#), [LegendDisplayPolicy](#)

6.30.4.3 void QwtLegend::setItemMode ([LegendItemMode](#))

See also:

[LegendItemMode](#)

6.30.4.4 [QwtLegend::LegendItemMode](#) QwtLegend::itemMode () const

See also:

[LegendItemMode](#)

6.30.4.5 int QwtLegend::identifierMode () const

Returns:

the IdentifierMode to be used in combination with LegendDisplayPolicy::Fixed.

Default is ShowLine | ShowSymbol | ShowText.

6.30.4.6 QWidget * QwtLegend::contentsWidget ()

The contents widget is the only child of the viewport() and the parent widget of all legend items.

6.30.4.7 const QWidget * QwtLegend::contentsWidget () const

The contents widget is the only child of the viewport() and the parent widget of all legend items.

6.30.4.8 void QwtLegend::insert (const [QwtLegendItemManager](#) * *plotItem*, QWidget * *legendItem*)

Insert a new item for a plot item

Parameters:

plotItem Plot item
legendItem New legend item

Note:

The parent of item will be changed to [QwtLegend::contentsWidget\(\)](#)

6.30.4.9 void QwtLegend::remove (const [QwtLegendItemManager](#) * *plotItem*)

Find the corresponding item for a plotItem and remove it from the item list.

Parameters:

plotItem Plot item

6.30.4.10 QWidget * QwtLegend::find (const [QwtLegendItemManager](#) * *plotItem*) const

Find the widget that represents a plot item

Parameters:

plotItem Plot item

Returns:

Widget on the legend, or NULL

6.30.4.11 [QwtLegendItemManager](#) * QwtLegend::find (const QWidget * *legendItem*) const

Find the widget that represents a plot item

Parameters:

legendItem Legend item

Returns:

Widget on the legend, or NULL

6.30.4.12 QList< QWidget * > QwtLegend::legendItems () const [virtual]

Return a list of all legend items.

6.30.4.13 void QwtLegend::clear ()

Remove all items.

6.30.4.14 `bool QwtLegend::isEmpty () const`

Return true, if there are no legend items.

6.30.4.15 `uint QwtLegend::itemCount () const`

Return the number of legend items.

6.30.4.16 `bool QwtLegend::eventFilter (QObject * o, QEvent * e) [virtual]`

Filter layout related events of [QwtLegend::contentsWidget\(\)](#).

Parameters:

- o* Object to be filtered
- e* Event

6.30.4.17 `QSize QwtLegend::sizeHint () const [virtual]`

Return a size hint.

6.30.4.18 `int QwtLegend::heightForWidth (int width) const [virtual]`**Returns:**

The preferred height, for the width w.

Parameters:

- width* Width

6.30.4.19 `QScrollBar * QwtLegend::horizontalScrollBar () const`**Returns:**

Horizontal scrollbar

See also:

[verticalScrollBar\(\)](#)

6.30.4.20 `QScrollBar * QwtLegend::verticalScrollBar () const`**Returns:**

Vertical scrollbar

See also:

[horizontalScrollBar\(\)](#)

6.30.4.21 void QwtLegend::resizeEvent (QResizeEvent * e) [protected, virtual]

Resize event

Parameters:

e Resize event

6.30.4.22 void QwtLegend::layoutContents () [protected, virtual]


Adjust contents widget and item layout to the size of the viewport().

6.31 QwtLegendItem Class Reference

A legend label.

```
#include <qwt_legend_item.h>
```

Inheritance diagram for QwtLegendItem:



Public Types

- enum IdentifierMode {
 - NoIdentifier = 0,
 - ShowLine = 1,
 - ShowSymbol = 2,
 - ShowText = 4 }

Public Slots

- void setChecked (bool on)

Signals

- void clicked ()
- void pressed ()
- void released ()
- void checked (bool)

Public Member Functions

- QwtLegendItem (QWidget *parent=0)
- QwtLegendItem (const QwtSymbol &, const QPen &, const QwtText &, QWidget *parent=0)
- virtual ~QwtLegendItem ()
- virtual void setText (const QwtText &)

- void [setItemMode](#) (QwtLegend::LegendItemMode)
- [QwtLegend::LegendItemMode itemMode](#) () const
- void [setIdentifierMode](#) (int)
- int [identifierMode](#) () const
- void [setIdentifierWidth](#) (int width)
- int [identifierWidth](#) () const
- void [setSpacing](#) (int spacing)
- int [spacing](#) () const
- void [setSymbol](#) (const QwtSymbol &)
- const [QwtSymbol & symbol](#) () const
- void [setCurvePen](#) (const QPen &)
- const QPen & [curvePen](#) () const
- virtual void [drawIdentifier](#) (QPainter *, const QRect &) const
- virtual void [drawItem](#) (QPainter *p, const QRect &) const
- virtual QSize [sizeHint](#) () const
- bool [isChecked](#) () const

Protected Member Functions

- void [setDown](#) (bool)
- bool [isDown](#) () const
- virtual void [paintEvent](#) (QPaintEvent *)
- virtual void [mousePressEvent](#) (QMouseEvent *)
- virtual void [mouseReleaseEvent](#) (QMouseEvent *)
- virtual void [keyPressEvent](#) (QKeyEvent *)
- virtual void [keyReleaseEvent](#) (QKeyEvent *)
- virtual void [drawText](#) (QPainter *, const QRect &)

6.31.1 Detailed Description

A legend label.

[QwtLegendItem](#) represents a curve on a legend. It displays an curve identifier with an explaining text. The identifier might be a combination of curve symbol and line. In readonly mode it behaves like a label, otherwise like an unstylish push button.

See also:

[QwtLegend](#), [QwtPlotCurve](#)

6.31.2 Member Enumeration Documentation

6.31.2.1 enum [QwtLegendItem::IdentifierMode](#)

Identifier mode.

Default is ShowLine | ShowText

See also:

[identifierMode\(\)](#), [setIdentifierMode\(\)](#)

6.31.3 Constructor & Destructor Documentation

6.31.3.1 QwtLegendItem::QwtLegendItem (QWidget * *parent* = 0) [explicit]

Parameters:

parent Parent widget

6.31.3.2 QwtLegendItem::QwtLegendItem (const QwtSymbol & *symbol*, const QPen & *curvePen*, const QwtText & *text*, QWidget * *parent* = 0) [explicit]

Parameters:

symbol Curve symbol

curvePen Curve pen

text Label text

parent Parent widget

6.31.3.3 QwtLegendItem::~~QwtLegendItem () [virtual]

Destructor.

6.31.4 Member Function Documentation

6.31.4.1 void QwtLegendItem::setText (const QwtText & *text*) [virtual]

Set the text to the legend item

Parameters:

text Text label

See also:

[QwtTextLabel::text\(\)](#)

Reimplemented from [QwtTextLabel](#).

6.31.4.2 void QwtLegendItem::setItemMode (QwtLegend::LegendItemMode *mode*)

Set the item mode The default is QwtLegend::ReadOnlyItem

Parameters:

mode Item mode

See also:

[itemMode\(\)](#)

6.31.4.3 QwtLegend::LegendItemMode QwtLegendItem::itemMode () const

Return the item mode

See also:

[setItemMode\(\)](#)

6.31.4.4 void QwtLegendItem::setIdentifierMode (int *mode*)

Set identifier mode. Default is ShowLine | ShowText.

Parameters:

mode Or'd values of IdentifierMode

See also:

[identifierMode\(\)](#)

6.31.4.5 int QwtLegendItem::identifierMode () const

Or'd values of IdentifierMode.

See also:

[setIdentifierMode\(\)](#), [IdentifierMode](#)

6.31.4.6 void QwtLegendItem::setIdentifierWidth (int *width*)

Set the width for the identifier Default is 8 pixels

Parameters:

width New width

See also:

[identifierMode\(\)](#), [identifierWidth\(\)](#)

6.31.4.7 int QwtLegendItem::identifierWidth () const

Return the width of the identifier

See also:

[setIdentifierWidth\(\)](#)

6.31.4.8 void QwtLegendItem::setSpacing (int *spacing*)

Change the spacing

Parameters:

spacing Spacing

See also:

[spacing\(\)](#), [identifierWidth\(\)](#), [QwtTextLabel::margin\(\)](#)

6.31.4.9 int QwtLegendItem::spacing () const

Return the spacing

See also:

[setSpacing\(\)](#), [identifierWidth\(\)](#), [QwtTextLabel::margin\(\)](#)

6.31.4.10 void QwtLegendItem::setSymbol (const QwtSymbol & symbol)

Set curve symbol.

Parameters:

symbol Symbol

See also:

[symbol\(\)](#)

6.31.4.11 const QwtSymbol & QwtLegendItem::symbol () const

Returns:

The curve symbol.

See also:

[setSymbol\(\)](#)

6.31.4.12 void QwtLegendItem::setCurvePen (const QPen & pen)

Set curve pen.

Parameters:

pen Curve pen

See also:

[curvePen\(\)](#)

6.31.4.13 const QPen & QwtLegendItem::curvePen () const

Returns:

The curve pen.

See also:

[setCurvePen\(\)](#)

6.31.4.14 void QwtLegendItem::drawIdentifier (QPainter * *painter*, const QRect & *rect*) const [virtual]

Paint the identifier to a given rect.

Parameters:

painter Painter

rect Rect where to paint

6.31.4.15 void QwtLegendItem::drawItem (QPainter * *painter*, const QRect & *rect*) const [virtual]

Draw the legend item to a given rect.

Parameters:

painter Painter

rect Rect where to paint the button

6.31.4.16 QSize QwtLegendItem::sizeHint () const [virtual]

Return a size hint.

Reimplemented from [QwtTextLabel](#).

6.31.4.17 bool QwtLegendItem::isChecked () const

Return true, if the item is checked.

6.31.4.18 void QwtLegendItem::setChecked (bool *on*) [slot]

Check/Uncheck a the item

Parameters:

on check/uncheck

See also:

[setItemMode\(\)](#)

6.31.4.19 void QwtLegendItem::clicked () [signal]

Signal, when the legend item has been clicked.

6.31.4.20 void QwtLegendItem::pressed () [signal]

Signal, when the legend item has been pressed.

6.31.4.21 void QwtLegendItem::released () [signal]

Signal, when the legend item has been released.

6.31.4.22 void QwtLegendItem::checked (bool) [signal]

Signal, when the legend item has been toggled.

6.31.4.23 void QwtLegendItem::setDown (bool) [protected]

Set the item being down.

6.31.4.24 bool QwtLegendItem::isDown () const [protected]

Return true, if the item is down.

6.31.4.25 void QwtLegendItem::paintEvent (QPaintEvent *) [protected, virtual]

Paint event.

Reimplemented from [QwtTextLabel](#).

6.31.4.26 void QwtLegendItem::mousePressEvent (QMouseEvent *) [protected, virtual]

Handle mouse press events.

6.31.4.27 void QwtLegendItem::mouseReleaseEvent (QMouseEvent *) [protected, virtual]

Handle mouse release events.

6.31.4.28 void QwtLegendItem::keyPressEvent (QKeyEvent *) [protected, virtual]

Handle key press events.

6.31.4.29 void QwtLegendItem::keyReleaseEvent (QKeyEvent *) [protected, virtual]

Handle key release events.

6.31.4.30 void QwtLegendItem::drawText (QPainter *, const QRect &) [protected, virtual]

Redraw the text.


Reimplemented from [QwtTextLabel](#).

6.32 QwtLegendItemManager Class Reference

Abstract API to bind plot items to the legend.

```
#include <qwt_legend_itemmanager.h>
```

Inheritance diagram for QwtLegendItemManager:



Public Member Functions

- [QwtLegendItemManager \(\)](#)
- virtual [~QwtLegendItemManager \(\)](#)
- virtual void [updateLegend \(QwtLegend *legend\) const=0](#)
- virtual [QWidget * legendItem \(\) const=0](#)

6.32.1 Detailed Description

Abstract API to bind plot items to the legend.

6.32.2 Constructor & Destructor Documentation

6.32.2.1 [QwtLegendItemManager::QwtLegendItemManager \(\)](#) [inline]

Constructor.

6.32.2.2 [virtual QwtLegendItemManager::~~QwtLegendItemManager \(\)](#) [inline, virtual]

Destructor.

6.32.3 Member Function Documentation

6.32.3.1 [virtual void QwtLegendItemManager::updateLegend \(QwtLegend * legend\) const](#) [pure virtual]

Update the widget that represents the item on the legend

Parameters:

legend Legend

See also:

[legendItem\(\)](#)

Implemented in [QwtPlotCurve](#), and [QwtPlotItem](#).

6.32.3.2 virtual QWidget* QwtLegendItemManager::legendItem () const [pure virtual]

Allocate the widget that represents the item on the legend

Returns:

Allocated widget

See also:

[updateLegend\(\)](#) QwtLegend()


Implemented in [QwtPlotItem](#).

6.33 QwtLinearColorMap Class Reference

[QwtLinearColorMap](#) builds a color map from color stops.

```
#include <qwt_color_map.h>
```

Inheritance diagram for QwtLinearColorMap:



Public Types

- enum [Mode](#) {
 - FixedColors,**
 - ScaledColors,**
 - RotateNeedle,**
 - RotateScale }**

Public Member Functions

- [QwtLinearColorMap](#) ([QwtColorMap::Format](#)=[QwtColorMap::RGB](#))
- [QwtLinearColorMap](#) (const QColor &from, const QColor &to, [QwtColorMap::Format](#)=[QwtColorMap::RGB](#))
- [QwtLinearColorMap](#) (const [QwtLinearColorMap](#) &)
- virtual [~QwtLinearColorMap](#) ()
- [QwtLinearColorMap](#) & [operator=](#) (const [QwtLinearColorMap](#) &)
- virtual [QwtColorMap](#) * [copy](#) () const
- void [setMode](#) ([Mode](#))
- [Mode](#) [mode](#) () const
- void [setColorInterval](#) (const QColor &color1, const QColor &color2)
- void [addColorStop](#) (double value, const QColor &)
- [QwtArray](#)< double > [colorStops](#) () const
- QColor [color1](#) () const
- QColor [color2](#) () const
- virtual [QRgb](#) [rgb](#) (const [QwtDoubleInterval](#) &, double value) const
- virtual unsigned char [colorIndex](#) (const [QwtDoubleInterval](#) &, double value) const

6.33.1 Detailed Description

[QwtLinearColorMap](#) builds a color map from color stops.

A color stop is a color at a specific position. The valid range for the positions is [0.0, 1.0]. When mapping a value into a color it is translated into this interval. If `mode() == FixedColors` the color is calculated from the next lower color stop. If `mode() == ScaledColors` the color is calculated by interpolating the colors of the adjacent stops.

6.33.2 Member Enumeration Documentation

6.33.2.1 enum [QwtLinearColorMap::Mode](#)

Mode of color map

See also:

[setMode\(\)](#), [mode\(\)](#)

6.33.3 Constructor & Destructor Documentation

6.33.3.1 [QwtLinearColorMap::QwtLinearColorMap](#) ([QwtColorMap::Format](#) *format* = `QwtColorMap::RGB`)

Build a color map with two stops at 0.0 and 1.0. The color at 0.0 is `Qt::blue`, at 1.0 it is `Qt::yellow`.

Parameters:

format Preferred format of the color map

6.33.3.2 [QwtLinearColorMap::QwtLinearColorMap](#) (const [QColor](#) & *color1*, const [QColor](#) & *color2*, [QwtColorMap::Format](#) *format* = `QwtColorMap::RGB`)

Build a color map with two stops at 0.0 and 1.0.

Parameters:

color1 Color used for the minimum value of the value interval

color2 Color used for the maximum value of the value interval

format Preferred format of the color map

6.33.3.3 [QwtLinearColorMap::QwtLinearColorMap](#) (const [QwtLinearColorMap](#) &)

Copy constructor.

6.33.3.4 [QwtLinearColorMap::~QwtLinearColorMap](#) () [virtual]

Destructor.

6.33.4 Member Function Documentation

6.33.4.1 [QwtLinearColorMap](#) & [QwtLinearColorMap::operator=](#) (const [QwtLinearColorMap](#) &)

Assignment operator.

6.33.4.2 `QwtColorMap * QwtLinearColorMap::copy () const` [virtual]

Clone the color map.

Implements [QwtColorMap](#).

6.33.4.3 `void QwtLinearColorMap::setMode (Mode mode)`

Set the mode of the color map.

FixedColors means the color is calculated from the next lower color stop. ScaledColors means the color is calculated by interpolating the colors of the adjacent stops.

See also:

[mode\(\)](#)

6.33.4.4 `QwtLinearColorMap::Mode QwtLinearColorMap::mode () const`

Returns:

Mode of the color map

See also:

[setMode\(\)](#)

6.33.4.5 `void QwtLinearColorMap::setColorInterval (const QColor & color1, const QColor & color2)`

Set the color range

Add stops at 0.0 and 1.0.

Parameters:

color1 Color used for the minimum value of the value interval

color2 Color used for the maximum value of the value interval

See also:

[color1\(\)](#), [color2\(\)](#)

6.33.4.6 `void QwtLinearColorMap::addColorStop (double value, const QColor & color)`

Add a color stop

The value has to be in the range [0.0, 1.0]. F.e. a stop at position 17.0 for a range [10.0,20.0] must be passed as: $(17.0 - 10.0) / (20.0 - 10.0)$

Parameters:

value Value between [0.0, 1.0]

color Color stop

6.33.4.7 `QwtArray< double > QwtLinearColorMap::colorStops () const`

Return all positions of color stops in increasing order

6.33.4.8 `QColor QwtLinearColorMap::color1 () const`**Returns:**

the first color of the color range

See also:

[setColorInterval\(\)](#)

6.33.4.9 `QColor QwtLinearColorMap::color2 () const`**Returns:**

the second color of the color range

See also:

[setColorInterval\(\)](#)

6.33.4.10 `QRgb QwtLinearColorMap::rgb (const QwtDoubleInterval & interval, double value) const` [virtual]

Map a value of a given interval into a rgb value

Parameters:

interval Range for all values

value Value to map into a rgb value

Implements [QwtColorMap](#).

6.33.4.11 `unsigned char QwtLinearColorMap::colorIndex (const QwtDoubleInterval & interval, double value) const` [virtual]

Map a value of a given interval into a color index, between 0 and 255

Parameters:

interval Range for all values

value Value to map into a color index


Implements [QwtColorMap](#).

6.34 QwtLinearScaleEngine Class Reference

A scale engine for linear scales.

```
#include <qwt_scale_engine.h>
```

Inheritance diagram for QwtLinearScaleEngine:



Public Member Functions

- virtual void [autoScale](#) (int maxSteps, double &x1, double &x2, double &stepSize) const
- virtual [QwtScaleDiv divideScale](#) (double x1, double x2, int numMajorSteps, int numMinorSteps, double stepSize=0.0) const
- virtual [QwtScaleTransformation * transformation](#) () const

Protected Member Functions

- [QwtDoubleInterval align](#) (const [QwtDoubleInterval](#) &, double stepSize) const

6.34.1 Detailed Description

A scale engine for linear scales.

The step size will fit into the pattern $\{1, 2, 5\} \cdot 10^n$, where n is an integer.

6.34.2 Member Function Documentation

6.34.2.1 void [QwtLinearScaleEngine::autoScale](#) (int *maxNumSteps*, double & *x1*, double & *x2*, double & *stepSize*) const [virtual]

Align and divide an interval

Parameters:

- maxNumSteps* Max. number of steps
- x1* First limit of the interval (In/Out)
- x2* Second limit of the interval (In/Out)
- stepSize* Step size (Out)

See also:

[setAttribute\(\)](#)

Implements [QwtScaleEngine](#).

6.34.2.2 QwtScaleDiv `QwtLinearScaleEngine::divideScale (double x1, double x2, int maxMajSteps, int maxMinSteps, double stepSize = 0.0) const` [virtual]

Calculate a scale division.

Parameters:

x1 First interval limit

x2 Second interval limit

maxMajSteps Maximum for the number of major steps

maxMinSteps Maximum number of minor steps

stepSize Step size. If `stepSize == 0`, the `scaleEngine` calculates one.

See also:

`QwtScaleEngine::stepSize()`, `QwtScaleEngine::subDivide()`

Implements [QwtScaleEngine](#).

6.34.2.3 QwtScaleTransformation * `QwtLinearScaleEngine::transformation () const` [virtual]

Return a transformation, for linear scales

Implements [QwtScaleEngine](#).

6.34.2.4 QwtDoubleInterval `QwtLinearScaleEngine::align (const QwtDoubleInterval & interval, double stepSize) const` [protected]

Align an interval to a step size.

The limits of an interval are aligned that both are integer multiples of the step size.

Parameters:

interval Interval

stepSize Step size

Returns:


Aligned interval

6.35 QwtLog10ScaleEngine Class Reference

A scale engine for logarithmic (base 10) scales.

```
#include <qwt_scale_engine.h>
```

Inheritance diagram for `QwtLog10ScaleEngine`:



Public Member Functions

- virtual void [autoScale](#) (int maxSteps, double &x1, double &x2, double &stepSize) const
- virtual [QwtScaleDiv divideScale](#) (double x1, double x2, int numMajorSteps, int numMinorSteps, double stepSize=0.0) const
- virtual [QwtScaleTransformation * transformation](#) () const

Protected Member Functions

- [QwtDoubleInterval log10](#) (const [QwtDoubleInterval](#) &) const
- [QwtDoubleInterval pow10](#) (const [QwtDoubleInterval](#) &) const

6.35.1 Detailed Description

A scale engine for logarithmic (base 10) scales.

The step size is measured in **decades** and the major step size will be adjusted to fit the pattern $\{1, 2, 3, 5\} \cdot 10^n$, where n is a natural number including zero.

Warning:

the step size as well as the margins are measured in **decades**.

6.35.2 Member Function Documentation**6.35.2.1 void QwtLog10ScaleEngine::autoScale (int *maxNumSteps*, double & *x1*, double & *x2*, double & *stepSize*) const** [virtual]

Align and divide an interval

Parameters:

- maxNumSteps* Max. number of steps
- x1* First limit of the interval (In/Out)
- x2* Second limit of the interval (In/Out)
- stepSize* Step size (Out)

See also:

[QwtScaleEngine::setAttribute\(\)](#)

Implements [QwtScaleEngine](#).

6.35.2.2 QwtScaleDiv QwtLog10ScaleEngine::divideScale (double *x1*, double *x2*, int *maxMajSteps*, int *maxMinSteps*, double *stepSize* = 0.0) const [virtual]

Calculate a scale division.

Parameters:

- x1* First interval limit
- x2* Second interval limit

maxMajSteps Maximum for the number of major steps
maxMinSteps Maximum number of minor steps
stepSize Step size. If `stepSize == 0`, the `scaleEngine` calculates one.

See also:

`QwtScaleEngine::stepSize()`, `QwtLog10ScaleEngine::subDivide()`

Implements [QwtScaleEngine](#).

6.35.2.3 [QwtScaleTransformation](#) * `QwtLog10ScaleEngine::transformation () const` [virtual]

Return a transformation, for logarithmic (base 10) scales

Implements [QwtScaleEngine](#).

6.35.2.4 [QwtDoubleInterval](#) `QwtLog10ScaleEngine::log10 (const QwtDoubleInterval & interval) const` [protected]

Return the interval [`log10(interval.minValue())`, `log10(interval.maxValue)`]

6.35.2.5 [QwtDoubleInterval](#) `QwtLog10ScaleEngine::pow10 (const QwtDoubleInterval & interval) const` [protected]


Return the interval [`pow10(interval.minValue())`, `pow10(interval.maxValue)`]

6.36 QwtMagnifier Class Reference

[QwtMagnifier](#) provides zooming, by magnifying in steps.

```
#include <qwt_magnifier.h>
```

Inheritance diagram for [QwtMagnifier](#):



Public Member Functions

- [QwtMagnifier](#) (`QWidget *`)
- virtual `~QwtMagnifier ()`
- `QWidget *` [parentWidget \(\)](#)
- const `QWidget *` [parentWidget \(\) const](#)
- void [setEnabled \(bool\)](#)
- bool [isEnabled \(\) const](#)
- void [setMouseFactor \(double\)](#)
- double [mouseFactor \(\) const](#)
- void [setMouseButton \(int button, int buttonState=Qt::NoButton\)](#)
- void [getMouseButton \(int &button, int &buttonState\) const](#)

- void [setWheelFactor](#) (double)
- double [wheelFactor](#) () const
- void [setWheelButtonState](#) (int buttonState)
- int [wheelButtonState](#) () const
- void [setKeyFactor](#) (double)
- double [keyFactor](#) () const
- void [setZoomInKey](#) (int key, int modifiers)
- void [getZoomInKey](#) (int &key, int &modifiers) const
- void [setZoomOutKey](#) (int key, int modifiers)
- void [getZoomOutKey](#) (int &key, int &modifiers) const
- virtual bool [eventFilter](#) (QObject *, QEvent *)

Protected Member Functions

- virtual void [rescale](#) (double factor)=0
- virtual void [widgetMouseEvent](#) (QMouseEvent *)
- virtual void [widgetMouseReleaseEvent](#) (QMouseEvent *)
- virtual void [widgetMouseMoveEvent](#) (QMouseEvent *)
- virtual void [widgetWheelEvent](#) (QWheelEvent *)
- virtual void [widgetKeyPressEvent](#) (QKeyEvent *)
- virtual void [widgetKeyReleaseEvent](#) (QKeyEvent *)

6.36.1 Detailed Description

[QwtMagnifier](#) provides zooming, by magnifying in steps.

Using [QwtMagnifier](#) a plot can be zoomed in/out in steps using keys, the mouse wheel or moving a mouse button in vertical direction.

6.36.2 Constructor & Destructor Documentation

6.36.2.1 [QwtMagnifier::QwtMagnifier \(QWidget * parent\)](#) [explicit]

Constructor

Parameters:

parent Widget to be magnified

6.36.2.2 [QwtMagnifier::~~QwtMagnifier \(\)](#) [virtual]

Destructor.

6.36.3 Member Function Documentation

6.36.3.1 [QWidget * QwtMagnifier::parentWidget \(\)](#)

Returns:

Parent widget, where the rescaling happens

6.36.3.2 `const QWidget * QwtMagnifier::parentWidget () const`

Returns:

Parent widget, where the rescaling happens

6.36.3.3 `void QwtMagnifier::setEnabled (bool on)`

En/disable the magnifier.

When enabled is true an event filter is installed for the observed widget, otherwise the event filter is removed.

Parameters:

on true or false

See also:

[isEnabled\(\)](#), [eventFilter\(\)](#)

6.36.3.4 `bool QwtMagnifier::isEnabled () const`

Returns:

true when enabled, false otherwise

See also:

[setEnabled\(\)](#), [eventFilter\(\)](#)

6.36.3.5 `void QwtMagnifier::setMouseFactor (double factor)`

Change the mouse factor.

The mouse factor defines the ratio between the current range on the parent widget and the zoomed range for each vertical mouse movement. The default value is 0.95.

Parameters:

factor Wheel factor

See also:

[mouseFactor\(\)](#), [setMouseButton\(\)](#), [setWheelFactor\(\)](#), [setKeyFactor\(\)](#)

6.36.3.6 `double QwtMagnifier::mouseFactor () const`

Returns:

Mouse factor

See also:

[setMouseFactor\(\)](#)

6.36.3.7 void QwtMagnifier::setMouseButton (int *button*, int *buttonState* = Qt::NoButton)

Assign the mouse button, that is used for zooming in/out. The default value is Qt::RightButton.

Parameters:

button Button

buttonState Button state

See also:

[getMouseButton\(\)](#)

6.36.3.8 void QwtMagnifier::getMouseButton (int & *button*, int & *buttonState*) const**See also:**

[setMouseButton\(\)](#)

6.36.3.9 void QwtMagnifier::setWheelFactor (double *factor*)

Change the wheel factor.

The wheel factor defines the ratio between the current range on the parent widget and the zoomed range for each step of the wheel. The default value is 0.9.

Parameters:

factor Wheel factor

See also:

[wheelFactor\(\)](#), [setWheelButtonState\(\)](#), [setMouseFactor\(\)](#), [setKeyFactor\(\)](#)

6.36.3.10 double QwtMagnifier::wheelFactor () const**Returns:**

Wheel factor

See also:

[setWheelFactor\(\)](#)

6.36.3.11 void QwtMagnifier::setWheelButtonState (int *buttonState*)

Assign a mandatory button state for zooming in/out using the wheel. The default button state is Qt::NoButton.

Parameters:

buttonState Button state

See also:

[wheelButtonState\(\)](#)

6.36.3.12 `int QwtMagnifier::wheelButtonState () const`**Returns:**

Wheel button state

See also:

[setWheelButtonState\(\)](#)

6.36.3.13 `void QwtMagnifier::setKeyFactor (double factor)`

Change the key factor.

The key factor defines the ratio between the current range on the parent widget and the zoomed range for each key press of the zoom in/out keys. The default value is 0.9.

Parameters:

factor Key factor

See also:

[keyFactor\(\)](#), [setZoomInKey\(\)](#), [setZoomOutKey\(\)](#), [setWheelFactor](#), [setMouseFactor\(\)](#)

6.36.3.14 `double QwtMagnifier::keyFactor () const`**Returns:**

Key factor

See also:

[setKeyFactor\(\)](#)

6.36.3.15 `void QwtMagnifier::setZoomInKey (int key, int modifiers)`

Assign the key, that is used for zooming in. The default combination is Qt::Key_Plus + Qt::NoModifier.

Parameters:

key

modifiers

See also:

[getZoomInKey\(\)](#), [setZoomOutKey\(\)](#)

6.36.3.16 `void QwtMagnifier::getZoomInKey (int & key, int & modifiers) const`**See also:**

[setZoomInKey\(\)](#)

6.36.3.17 void QwtMagnifier::setZoomOutKey (int *key*, int *modifiers*)

Assign the key, that is used for zooming out. The default combination is Qt::Key_Minus + Qt::NoModifier.

Parameters:

key
modifiers

See also:

[getZoomOutKey\(\)](#), [setZoomOutKey\(\)](#)

6.36.3.18 void QwtMagnifier::getZoomOutKey (int & *key*, int & *modifiers*) const**See also:**

[setZoomOutKey\(\)](#)

6.36.3.19 bool QwtMagnifier::eventFilter (QObject * *o*, QEvent * *e*) [virtual]

Event filter.

When [isEnabled\(\)](#) the mouse events of the observed widget are filtered.

See also:

[widgetKeyPressEvent\(\)](#), [widgetMousePressEvent\(\)](#), [widgetMouseReleaseEvent\(\)](#), [widgetMouseMoveEvent\(\)](#), [widgetWheelEvent\(\)](#), [widgetKeyReleaseEvent\(\)](#)

6.36.3.20 virtual void QwtMagnifier::rescale (double *factor*) [protected, pure virtual]

Rescale the parent widget

Parameters:

factor Scale factor

Implemented in [QwtPlotMagnifier](#).

6.36.3.21 void QwtMagnifier::widgetMousePressEvent (QMouseEvent * *me*) [protected, virtual]

Handle a mouse press event for the observed widget.

Parameters:

me Mouse event

See also:

[eventFilter\(\)](#), [widgetMouseReleaseEvent\(\)](#), [widgetMouseMoveEvent\(\)](#)

6.36.3.22 void QwtMagnifier::widgetMouseEvent (QMouseEvent *) [protected, virtual]

Handle a mouse release event for the observed widget.

See also:

[eventFilter\(\)](#), [widgetMouseEvent\(\)](#), [widgetMouseMoveEvent\(\)](#),

6.36.3.23 void QwtMagnifier::widgetMouseMoveEvent (QMouseEvent * *me*) [protected, virtual]

Handle a mouse move event for the observed widget.

Parameters:

me Mouse event

See also:

[eventFilter\(\)](#), [widgetMouseEvent\(\)](#), [widgetMouseReleaseEvent\(\)](#),

6.36.3.24 void QwtMagnifier::widgetWheelEvent (QWheelEvent * *we*) [protected, virtual]

Handle a wheel event for the observed widget.

Parameters:

we Wheel event

See also:

[eventFilter\(\)](#)

6.36.3.25 void QwtMagnifier::widgetKeyPressEvent (QKeyEvent * *ke*) [protected, virtual]

Handle a key press event for the observed widget.

Parameters:

ke Key event

See also:

[eventFilter\(\)](#), [widgetKeyReleaseEvent\(\)](#)

6.36.3.26 void QwtMagnifier::widgetKeyReleaseEvent (QKeyEvent *) [protected, virtual]

Handle a key release event for the observed widget.

Parameters:

ke Key event

See also:


[eventFilter\(\)](#), [widgetKeyReleaseEvent\(\)](#)

6.37 QwtMathMLTextEngine Class Reference

Text Engine for the MathML renderer of the Qt solutions package.

```
#include <qwt_mathml_text_engine.h>
```

Inheritance diagram for QwtMathMLTextEngine:



Public Member Functions

- [QwtMathMLTextEngine \(\)](#)
- virtual [~QwtMathMLTextEngine \(\)](#)
- virtual int [heightForWidth](#) (const QFont &font, int flags, const QString &text, int width) const
- virtual QSize [textSize](#) (const QFont &font, int flags, const QString &text) const
- virtual void [draw](#) (QPainter *painter, const QRect &rect, int flags, const QString &text) const
- virtual bool [mightRender](#) (const QString &) const
- virtual void [textMargins](#) (const QFont &, const QString &, int &left, int &right, int &top, int &bottom) const

6.37.1 Detailed Description

Text Engine for the MathML renderer of the Qt solutions package.

The Qt Solution package includes a renderer for MathML <http://www.trolltech.com/products/qt/addon/solution> that is available for owners of a commercial Qt license. You need a version ≥ 2.1 , that is only available for Qt4.

To enable MathML support the following code needs to be added to the application:

```
#include <qwt_mathml_text_engine.h>
```

```
QwtText::setTextEngine(QwtText::MathMLText, new QwtMathMLTextEngine());
```

See also:

[QwtTextEngine](#), [QwtText::setTextEngine](#)

Warning:

Unfortunately the MathML renderer doesn't support rotating of texts.

6.37.2 Constructor & Destructor Documentation

6.37.2.1 QwtMathMLTextEngine::QwtMathMLTextEngine ()

Constructor.

6.37.2.2 QwtMathMLTextEngine::~~QwtMathMLTextEngine () [virtual]

Destructor.

6.37.3 Member Function Documentation

6.37.3.1 int QwtMathMLTextEngine::heightForWidth (const QFont & *font*, int *flags*, const QString & *text*, int *width*) const [virtual]

Find the height for a given width

Parameters:

font Font of the text

flags Bitwise OR of the flags used like in QPainter::drawText

text Text to be rendered

width Width

Returns:

Calculated height

Implements [QwtTextEngine](#).

6.37.3.2 QSize QwtMathMLTextEngine::textSize (const QFont & *font*, int *flags*, const QString & *text*) const [virtual]

Returns the size, that is needed to render text

Parameters:

font Font of the text

flags Bitwise OR of the flags used like in QPainter::drawText

text Text to be rendered

Returns:

Calculated size

Implements [QwtTextEngine](#).

6.37.3.3 void QwtMathMLTextEngine::draw (QPainter * *painter*, const QRect & *rect*, int *flags*, const QString & *text*) const [virtual]

Draw the text in a clipping rectangle

Parameters:

painter Painter

rect Clipping rectangle

flags Bitwise OR of the flags like in for QPainter::drawText

text Text to be rendered

Implements [QwtTextEngine](#).

6.37.3.4 `bool QwtMathMLTextEngine::mightRender (const QString & text) const` [virtual]

Test if a string can be rendered by [QwtMathMLTextEngine](#)

Parameters:

text Text to be tested

Returns:

true, if text begins with "<math>".

Implements [QwtTextEngine](#).

6.37.3.5 `void QwtMathMLTextEngine::textMargins (const QFont &, const QString &, int & left, int & right, int & top, int & bottom) const` [virtual]

Return margins around the texts

Parameters:

left Return 0

right Return 0

top Return 0

bottom Return 0

Implements [QwtTextEngine](#).

6.38 QwtMetricsMap Class Reference

A Map to translate between layout, screen and paint device metrics.

```
#include <qwt_layout_metrics.h>
```

Public Member Functions

- `bool isIdentity () const`
- `void setMetrics (const QPaintDevice *layoutMetrics, const QPaintDevice *deviceMetrics)`
- `int layoutToDeviceX (int x) const`
- `int deviceToLayoutX (int x) const`
- `int screenToLayoutX (int x) const`
- `int layoutToScreenX (int x) const`
- `int layoutToDeviceY (int y) const`
- `int deviceToLayoutY (int y) const`
- `int screenToLayoutY (int y) const`
- `int layoutToScreenY (int y) const`
- `QPoint layoutToDevice (const QPoint &, const QPainter *=&NULL) const`
- `QPoint deviceToLayout (const QPoint &, const QPainter *=&NULL) const`
- `QPoint screenToLayout (const QPoint &) const`
- `QPoint layoutToScreen (const QPoint &point) const`
- `QSize layoutToDevice (const QSize &) const`
- `QSize deviceToLayout (const QSize &) const`

- QSize **screenToLayout** (const QSize &) const
- QSize **layoutToScreen** (const QSize &) const
- QRect **layoutToDevice** (const QRect &, const QPainter *=*NULL*) const
- QRect **deviceToLayout** (const QRect &, const QPainter *=*NULL*) const
- QRect **screenToLayout** (const QRect &) const
- QRect **layoutToScreen** (const QRect &) const
- QwtPolygon **layoutToDevice** (const QwtPolygon &, const QPainter *=*NULL*) const
- QwtPolygon **deviceToLayout** (const QwtPolygon &, const QPainter *=*NULL*) const

Static Public Member Functions

- static QwtPolygon [translate](#) (const QMatrix &, const QwtPolygon &)
- static QRect [translate](#) (const QMatrix &, const QRect &)

6.38.1 Detailed Description

A Map to translate between layout, screen and paint device metrics.

Qt3 supports painting in integer coordinates only. Therefore it is not possible to scale the layout in screen coordinates to layouts in higher resolutions (f.e printing) without losing the higher precision. [QwtMetricsMap](#) is used to incorporate the various widget attributes (always in screen resolution) into the layout/printing code of [QwtPlot](#).

Qt4 is able to paint floating point based coordinates, what makes it possible always to render in screen coordinates (with a common scale factor). [QwtMetricsMap](#) will be obsolete as soon as Qt3 support has been dropped (Qwt 6.x).

6.38.2 Member Function Documentation

6.38.2.1 QwtPolygon QwtMetricsMap::translate (const QMatrix & *m*, const QwtPolygon & *pa*) [static]

Wrapper for QMatrix::map.

Parameters:

- m* Matrix
- pa* Polygon to translate

Returns:

Translated polygon

6.38.2.2 QRect QwtMetricsMap::translate (const QMatrix & *m*, const QRect & *rect*) [static]

Wrapper for QMatrix::mapRect.

Parameters:

- m* Matrix
- rect* Rectangle to translate

Returns:

Translated rectangle

6.39 QwtPainter Class Reference

A collection of QPainter workarounds.

```
#include <qwt_painter.h>
```

Static Public Member Functions

- static void [setMetricsMap](#) (const QPainter *layout, const QPainter *device)
- static void [setMetricsMap](#) (const QwtMetricsMap &)
- static void [resetMetricsMap](#) ()
- static const [QwtMetricsMap](#) & [metricsMap](#) ()
- static void [setDeviceClipping](#) (bool)
- static bool [deviceClipping](#) ()
- static const QRect & [deviceClipRect](#) ()
- static void [setClipRect](#) (QPainter *, const QRect &)
- static void [drawText](#) (QPainter *, int x, int y, const QString &)
- static void [drawText](#) (QPainter *, const QPoint &, const QString &)
- static void [drawText](#) (QPainter *, int x, int y, int w, int h, int flags, const QString &)
- static void [drawText](#) (QPainter *, const QRect &, int flags, const QString &)
- static void [drawSimpleRichText](#) (QPainter *, const QRect &, int flags, QTextDocument &)
- static void [drawRect](#) (QPainter *, int x, int y, int w, int h)
- static void [drawRect](#) (QPainter *, const QRect &rect)
- static void [fillRect](#) (QPainter *, const QRect &, const QBrush &)
- static void [drawEllipse](#) (QPainter *, const QRect &)
- static void [drawPie](#) (QPainter *, const QRect &r, int a, int alen)
- static void [drawLine](#) (QPainter *, int x1, int y1, int x2, int y2)
- static void [drawLine](#) (QPainter *, const QPoint &p1, const QPoint &p2)
- static void [drawPolygon](#) (QPainter *, const QwtPolygon &pa)
- static void [drawPolyline](#) (QPainter *, const QwtPolygon &pa)
- static void [drawPoint](#) (QPainter *, int x, int y)
- static void [drawRoundFrame](#) (QPainter *, const QRect &, int width, const QPalette &, bool sunken)
- static void [drawFocusRect](#) (QPainter *, QWidget *)
- static void [drawFocusRect](#) (QPainter *, QWidget *, const QRect &)
- static void [drawColorBar](#) (QPainter *painter, const QwtColorMap &, const QwtDoubleInterval &, const QwtScaleMap &, Qt::Orientation, const QRect &)
- static QPen [scaledPen](#) (const QPen &)

6.39.1 Detailed Description

A collection of QPainter workarounds.

1) Clipping to coordinate system limits (Qt3 only)

On X11 pixel coordinates are stored in shorts. Qt produces overruns when mapping QCOORDS to shorts.

2) Scaling to device metrics

QPainter scales fonts, line and fill patterns to the metrics of the paint device. Other values like the geometries of rects, points remain device independent. To enable a device independent widget implementation, [QwtPainter](#) adds scaling of these geometries. (Unfortunately QPainter::scale scales both types of paintings, so the objects of the first type would be scaled twice).

6.39.2 Member Function Documentation

6.39.2.1 void QPainter::setMetricsMap (const QPainterDevice * layout, const QPainterDevice * device) [static]

Scale all [QwtPainter](#) drawing operations using the ratio $\text{QwtPaintMetrics}(\text{from}).\text{logicalDpiX}() / \text{QwtPaintMetrics}(\text{to}).\text{logicalDpiX}()$ and $\text{QwtPaintMetrics}(\text{from}).\text{logicalDpiY}() / \text{QwtPaintMetrics}(\text{to}).\text{logicalDpiY}()$

See also:

[QwtPainter::resetScaleMetrics\(\)](#), [QwtPainter::scaleMetricsX\(\)](#), [QwtPainter::scaleMetricsY\(\)](#)

6.39.2.2 void QPainter::setMetricsMap (const QwtMetricsMap & map) [static]

Change the metrics map

See also:

[QwtPainter::resetMetricsMap\(\)](#), [QwtPainter::metricsMap\(\)](#)

6.39.2.3 void QPainter::resetMetricsMap () [static]

Reset the metrics map to the ratio 1:1

See also:

[QwtPainter::setMetricsMap\(\)](#), [QwtPainter::resetMetricsMap\(\)](#)

6.39.2.4 const QwtMetricsMap & QPainter::metricsMap () [static]

Returns:

Metrics map

6.39.2.5 void QPainter::setDeviceClipping (bool enable) [static]

En/Disable device clipping.

On X11 the default for device clipping is enabled, otherwise it is disabled.

See also:

[QwtPainter::deviceClipping\(\)](#)

6.39.2.6 `bool QwtPainter::deviceClipping ()` [*inline, static*]

Returns whether device clipping is enabled. On X11 the default is enabled, otherwise it is disabled.

See also:

[QwtPainter::setDeviceClipping\(\)](#)

6.39.2.7 `const QRect & QwtPainter::deviceClipRect ()` [*static*]

Returns rect for device clipping

See also:

[QwtPainter::setDeviceClipping\(\)](#)

6.39.2.8 `void QwtPainter::setClipRect (QPainter * painter, const QRect & rect)` [*static*]

Wrapper for QPainter::setClipRect()

6.39.2.9 `void QwtPainter::drawText (QPainter * painter, int x, int y, const QString & text)` [*static*]

Wrapper for QPainter::drawText()

6.39.2.10 `void QwtPainter::drawText (QPainter * painter, const QPoint & pos, const QString & text)` [*static*]

Wrapper for QPainter::drawText()

6.39.2.11 `void QwtPainter::drawText (QPainter * painter, int x, int y, int w, int h, int flags, const QString & text)` [*static*]

Wrapper for QPainter::drawText()

6.39.2.12 `void QwtPainter::drawText (QPainter * painter, const QRect & rect, int flags, const QString & text)` [*static*]

Wrapper for QPainter::drawText()

6.39.2.13 `void QwtPainter::drawSimpleRichText (QPainter * painter, const QRect & rect, int flags, QTextDocument & text)` [*static*]

Wrapper for QSimpleRichText::draw()

6.39.2.14 `void QwtPainter::drawRect (QPainter * painter, int x, int y, int w, int h)` [*static*]

Wrapper for QPainter::drawRect()

6.39.2.15 `void QwtPainter::drawRect (QPainter * painter, const QRect & rect)` [*static*]

Wrapper for QPainter::drawRect()

6.39.2.16 void QwtPainter::fillRect (QPainter * *painter*, const QRect & *rect*, const QBrush & *brush*)
[static]

Wrapper for QPainter::fillRect()

6.39.2.17 void QwtPainter::drawEllipse (QPainter * *painter*, const QRect & *rect*) [static]

Wrapper for QPainter::drawEllipse()

6.39.2.18 void QwtPainter::drawPie (QPainter * *painter*, const QRect & *rect*, int *a*, int *alen*)
[static]

Wrapper for QPainter::drawPie()

6.39.2.19 void QwtPainter::drawLine (QPainter * *painter*, int *x1*, int *y1*, int *x2*, int *y2*) [static]

Wrapper for QPainter::drawLine()

6.39.2.20 void QwtPainter::drawLine (QPainter *, const QPoint & *p1*, const QPoint & *p2*)
[inline, static]

Wrapper for QPainter::drawLine().

6.39.2.21 void QwtPainter::drawPolygon (QPainter * *painter*, const QwtPolygon & *pa*)
[static]

Wrapper for QPainter::drawPolygon()

6.39.2.22 void QwtPainter::drawPolyline (QPainter * *painter*, const QwtPolygon & *pa*)
[static]

Wrapper for QPainter::drawPolyline()

6.39.2.23 void QwtPainter::drawPoint (QPainter * *painter*, int *x*, int *y*) [static]

Wrapper for QPainter::drawPoint()

6.39.2.24 void QwtPainter::drawRoundFrame (QPainter *, const QRect &, int *width*, const QPalette &, bool *sunken*) [static]

Draw a round frame.

6.39.2.25 QPen QwtPainter::scaledPen (const QPen & *pen*) [static]

Scale a pen according to the layout metrics.

The width of non cosmetic pens is scaled from screen to layout metrics, so that they look similar on paint devices with different resolutions.

Parameters:

pen Unscaled pen

Returns:

Scaled pen

6.40 QwtPanner Class Reference

[QwtPanner](#) provides panning of a widget.

```
#include <qwt_panner.h>
```

Inheritance diagram for QwtPanner:

**Signals**

- void [panned](#) (int dx, int dy)
- void [moved](#) (int dx, int dy)

Public Member Functions

- [QwtPanner](#) (QWidget *parent)
- virtual [~QwtPanner](#) ()
- void [setEnabled](#) (bool)
- bool [isEnabled](#) () const
- void [setMouseButton](#) (int button, int buttonState=Qt::NoButton)
- void [getMouseButton](#) (int &button, int &buttonState) const
- void [setAbortKey](#) (int key, int state=Qt::NoButton)
- void [getAbortKey](#) (int &key, int &state) const
- void [setCursor](#) (const QCursor &)
- const QCursor [cursor](#) () const
- void [setOrientations](#) (Qt::Orientations)
- Qt::Orientations [orientations](#) () const
- bool [isOrientationEnabled](#) (Qt::Orientation) const
- virtual bool [eventFilter](#) (QObject *, QEvent *)

Protected Member Functions

- virtual void [widgetMouseEvent](#) (QMouseEvent *)
- virtual void [widgetMousePressEvent](#) (QMouseEvent *)
- virtual void [widgetMouseMoveEvent](#) (QMouseEvent *)
- virtual void [widgetKeyPressEvent](#) (QKeyEvent *)
- virtual void [widgetKeyReleaseEvent](#) (QKeyEvent *)
- virtual void [paintEvent](#) (QPaintEvent *)

6.40.1 Detailed Description

[QwtPanner](#) provides panning of a widget.

[QwtPanner](#) grabs the contents of a widget, that can be dragged in all directions. The offset between the start and the end position is emitted by the panned signal.

[QwtPanner](#) grabs the content of the widget into a pixmap and moves the pixmap around, without initiating any repaint events for the widget. Areas, that are not part of content are not painted while panning in process. This makes panning fast enough for widgets, where repaints are too slow for mouse movements.

For widgets, where repaints are very fast it might be better to implement panning manually by mapping mouse events into paint events.

6.40.2 Constructor & Destructor Documentation

6.40.2.1 QwtPanner::QwtPanner (QWidget *parent)

Creates an panner that is enabled for the left mouse button.

Parameters:

parent Parent widget to be panned

6.40.2.2 QwtPanner::~QwtPanner () [virtual]

Destructor.

6.40.3 Member Function Documentation

6.40.3.1 void QwtPanner::setEnabled (bool on)

En/disable the panner.

When enabled is true an event filter is installed for the observed widget, otherwise the event filter is removed.

Parameters:

on true or false

See also:

[isEnabled\(\)](#), [eventFilter\(\)](#)

6.40.3.2 bool QwtPanner::isEnabled () const

Returns:

true when enabled, false otherwise

See also:

[setEnabled](#), [eventFilter\(\)](#)

6.40.3.3 void QwtPanner::setMouseButton (int *button*, int *buttonState* = Qt::NoButton)

Change the mouse button The defaults are Qt::LeftButton and Qt::NoButton

6.40.3.4 void QwtPanner::getMouseButton (int & *button*, int & *buttonState*) const

Get the mouse button.

6.40.3.5 void QwtPanner::setAbortKey (int *key*, int *state* = Qt::NoButton)

Change the abort key The defaults are Qt::Key_Escape and Qt::NoButton

Parameters:

key Key (See Qt::Keycode)

state State

6.40.3.6 void QwtPanner::getAbortKey (int & *key*, int & *state*) const

Get the abort key.

6.40.3.7 void QwtPanner::setCursor (const QCursor & *cursor*)

Change the cursor, that is active while panning The default is the cursor of the parent widget.

Parameters:

cursor New cursor

See also:

[setCursor\(\)](#)

6.40.3.8 const QCursor QwtPanner::cursor () const**Returns:**

Cursor that is active while panning

See also:

[setCursor\(\)](#)

6.40.3.9 void QwtPanner::setOrientations (Qt::Orientations *o*)

Set the orientations, where panning is enabled The default value is in both directions: Qt::Horizontal | Qt::Vertical

/param o Orientation

6.40.3.10 Qt::Orientations QwtPanner::orientations () const

Return the orientation, where paning is enabled.

6.40.3.11 bool QwtPanner::isOrientationEnabled (Qt::Orientation *o*) const

Return true if a orientation is enabled

See also:

[orientations\(\)](#), [setOrientations\(\)](#)

6.40.3.12 bool QwtPanner::eventFilter (QObject * *o*, QEvent * *e*) [virtual]

Event filter.

When [isEnabled\(\)](#) the mouse events of the observed widget are filtered.

See also:

[widgetMouseEvent\(\)](#), [widgetMouseReleaseEvent\(\)](#), [widgetMouseMoveEvent\(\)](#)

6.40.3.13 void QwtPanner::panned (int *dx*, int *dy*) [signal]

Signal emitted, when panning is done

Parameters:

dx Offset in horizontal direction

dy Offset in vertical direction

6.40.3.14 void QwtPanner::moved (int *dx*, int *dy*) [signal]

Signal emitted, while the widget moved, but panning is not finished.

Parameters:

dx Offset in horizontal direction

dy Offset in vertical direction

6.40.3.15 void QwtPanner::widgetMouseEvent (QMouseEvent * *me*) [protected, virtual]

Handle a mouse press event for the observed widget.

Parameters:

me Mouse event

See also:

[eventFilter\(\)](#), [widgetMouseReleaseEvent\(\)](#), [widgetMouseMoveEvent\(\)](#),

6.40.3.16 void QwtPanner::widgetMouseEvent (QMouseEvent * *me*) [protected, virtual]

Handle a mouse release event for the observed widget.

Parameters:

me Mouse event

See also:

[eventFilter\(\)](#), [widgetMouseEvent\(\)](#), [widgetMouseMoveEvent\(\)](#),

6.40.3.17 void QwtPanner::widgetMouseMoveEvent (QMouseEvent * *me*) [protected, virtual]

Handle a mouse move event for the observed widget.

Parameters:

me Mouse event

See also:

[eventFilter\(\)](#), [widgetMouseEvent\(\)](#), [widgetMouseReleaseEvent\(\)](#)

6.40.3.18 void QwtPanner::widgetKeyPressEvent (QKeyEvent * *ke*) [protected, virtual]

Handle a key press event for the observed widget.

Parameters:

ke Key event

See also:

[eventFilter\(\)](#), [widgetKeyReleaseEvent\(\)](#)

6.40.3.19 void QwtPanner::widgetKeyReleaseEvent (QKeyEvent *) [protected, virtual]

Handle a key release event for the observed widget.

See also:

[eventFilter\(\)](#), [widgetKeyReleaseEvent\(\)](#)

6.40.3.20 void QwtPanner::paintEvent (QPaintEvent * *pe*) [protected, virtual]

Paint event.

Repaint the grabbed pixmap on its current position and fill the empty spaces by the background of the parent widget.

Parameters:


pe Paint event

6.41 QwtPicker Class Reference

[QwtPicker](#) provides selections on a widget.

```
#include <qwt_picker.h>
```

Inheritance diagram for QwtPicker:



Public Types

- enum [SelectionType](#) {
 NoSelection = 0,
 PointSelection = 1,
 RectSelection = 2,
 PolygonSelection = 4 }
- enum [RectSelectionType](#) {
 CornerToCorner = 64,
 CenterToCorner = 128,
 CenterToRadius = 256 }
- enum [SelectionMode](#) {
 ClickSelection = 1024,
 DragSelection = 2048 }
- enum [RubberBand](#) {
 NoRubberBand = 0,
 HLineRubberBand,
 VLineRubberBand,
 CrossRubberBand,
 RectRubberBand,
 EllipseRubberBand,
 PolygonRubberBand,
 UserRubberBand = 100 }
- enum [DisplayMode](#) {
 AlwaysOff,
 AlwaysOn,
 ActiveOnly,
 ImageMode = 1,
 ContourMode = 2 }

- enum [ResizeMode](#) {
 Stretch,
 KeepSize }

Signals

- void [selected](#) (const QwtPolygon &pa)
- void [appended](#) (const QPoint &pos)
- void [moved](#) (const QPoint &pos)
- void [changed](#) (const QwtPolygon &pa)

Public Member Functions

- [QwtPicker](#) (QWidget *parent)
- [QwtPicker](#) (int selectionFlags, [RubberBand](#) rubberBand, [DisplayMode](#) trackerMode, QWidget *)
- virtual [~QwtPicker](#) ()
- virtual void [setSelectionFlags](#) (int)
- int [selectionFlags](#) () const
- virtual void [setRubberBand](#) ([RubberBand](#))
- [RubberBand](#) [rubberBand](#) () const
- virtual void [setTrackerMode](#) ([DisplayMode](#))
- [DisplayMode](#) [trackerMode](#) () const
- virtual void [setResizeMode](#) ([ResizeMode](#))
- [ResizeMode](#) [resizeMode](#) () const
- virtual void [setRubberBandPen](#) (const QPen &)
- QPen [rubberBandPen](#) () const
- virtual void [setTrackerPen](#) (const QPen &)
- QPen [trackerPen](#) () const
- virtual void [setTrackerFont](#) (const QFont &)
- QFont [trackerFont](#) () const
- bool [isEnabled](#) () const
- virtual void [setEnabled](#) (bool)
- bool [isActive](#) () const
- virtual bool [eventFilter](#) (QObject *, QEvent *)
- QWidget * [parentWidget](#) ()
- const QWidget * [parentWidget](#) () const
- virtual QRect [pickRect](#) () const
- const QwtPolygon & [selection](#) () const
- virtual void [drawRubberBand](#) (QPainter *) const
- virtual void [drawTracker](#) (QPainter *) const
- virtual [QwtText](#) [trackerText](#) (const QPoint &pos) const
- QPoint [trackerPosition](#) () const
- QRect [trackerRect](#) (const QFont &) const

Protected Member Functions

- virtual bool [accept](#) (QwtPolygon &selection) const
- virtual void [transition](#) (const QEvent *)
- virtual void [begin](#) ()
- virtual void [append](#) (const QPoint &)
- virtual void [move](#) (const QPoint &)
- virtual bool [end](#) (bool ok=true)
- virtual void [reset](#) ()
- virtual void [widgetMouseEvent](#) (QMouseEvent *)
- virtual void [widgetMouseReleaseEvent](#) (QMouseEvent *)
- virtual void [widgetMouseDoubleClickEvent](#) (QMouseEvent *)
- virtual void [widgetMouseMoveEvent](#) (QMouseEvent *)
- virtual void [widgetWheelEvent](#) (QWheelEvent *)
- virtual void [widgetKeyPressEvent](#) (QKeyEvent *)
- virtual void [widgetKeyReleaseEvent](#) (QKeyEvent *)
- virtual void [widgetLeaveEvent](#) (QEvent *)
- virtual void [stretchSelection](#) (const QSize &oldSize, const QSize &newSize)
- virtual [QwtPickerMachine](#) * [stateMachine](#) (int) const
- virtual void [updateDisplay](#) ()
- const QWidget * [rubberBandWidget](#) () const
- const QWidget * [trackerWidget](#) () const

6.41.1 Detailed Description

[QwtPicker](#) provides selections on a widget.

[QwtPicker](#) filters all mouse and keyboard events of a widget and translates them into an array of selected points. Depending on the [QwtPicker::SelectionType](#) the selection might be a single point, a rectangle or a polygon. The selection process is supported by optional rubberbands (rubberband selection) and position trackers.

[QwtPicker](#) is useful for widgets where the event handlers can't be overloaded, like for components of composite widgets. It offers alternative handlers for mouse and key events.

Example

```
#include <qwt_picker.h>

QwtPicker *picker = new QwtPicker(widget);
picker->setTrackerMode(QwtPicker::ActiveOnly);
connect(picker, SIGNAL(selected(const QwtPolygon &)), ...);

// emit the position of clicks on widget
picker->setSelectionFlags(QwtPicker::PointSelection | QwtPicker::ClickSelection);

...

// now select rectangles
picker->setSelectionFlags(QwtPicker::RectSelection | QwtPicker::DragSelection);
picker->setRubberBand(QwtPicker::RectRubberBand);
```

The selection process uses the commands [begin\(\)](#), [append\(\)](#), [move\(\)](#) and [end\(\)](#). [append\(\)](#) adds a new point to the selection, [move\(\)](#) changes the position of the latest point.

The commands are initiated from a small state machine ([QwtPickerMachine](#)) that translates mouse and key events. There are a couple of predefined state machines for point, rect and polygon selections. The [selectionFlags\(\)](#) control which one should be used. It is possible to use other machines by overloading [stateMachine\(\)](#).

The picker is active ([isActive\(\)](#)), between [begin\(\)](#) and [end\(\)](#). In active state the rubberband is displayed, and the tracker is visible in case of [trackerMode](#) is `ActiveOnly` or `AlwaysOn`.

The cursor can be moved using the arrow keys. All selections can be aborted using the abort key. ([QwtEventPattern::KeyPatternCode](#))

Warning:

In case of `QWidget::NoFocus` the focus policy of the observed widget is set to `QWidget::WheelFocus` and mouse tracking will be manipulated for `ClickSelection` while the picker is active, or if [trackerMode\(\)](#) is `AlwaysOn`.

6.41.2 Member Enumeration Documentation

6.41.2.1 enum [QwtPicker::SelectionType](#)

This enum type describes the type of a selection. It can be or'd with [QwtPicker::RectSelectionType](#) and [QwtPicker::SelectionMode](#) and passed to [QwtPicker::setSelectionFlags\(\)](#)

- `NoSelection`
Selection is disabled. Note this is different to the disabled state, as you might have a tracker.
- `PointSelection`
Select a single point.
- `RectSelection`
Select a rectangle.
- `PolygonSelection`
Select a polygon.

The default value is `NoSelection`.

See also:

[QwtPicker::setSelectionFlags\(\)](#), [QwtPicker::selectionFlags\(\)](#)

6.41.2.2 enum [QwtPicker::RectSelectionType](#)

Selection subtype for `RectSelection` This enum type describes the type of rectangle selections. It can be or'd with [QwtPicker::RectSelectionType](#) and [QwtPicker::SelectionMode](#) and passed to [QwtPicker::setSelectionFlags\(\)](#).

- `CornerToCorner`
The first and the second selected point are the corners of the rectangle.
- `CenterToCorner`
The first point is the center, the second a corner of the rectangle.

- CenterToRadius

The first point is the center of a quadrat, calculated by the maximum of the x- and y-distance.

The default value is CornerToCorner.

See also:

[QwtPicker::setSelectionFlags\(\)](#), [QwtPicker::selectionFlags\(\)](#)

6.41.2.3 enum [QwtPicker::SelectionMode](#)

Values of this enum type or'd together with a SelectionType value identifies which state machine should be used for the selection.

The default value is ClickSelection.

See also:

[stateMachine\(\)](#)

6.41.2.4 enum [QwtPicker::RubberBand](#)

Rubberband style

- NoRubberBand
No rubberband.
- HLineRubberBand & PointSelection
A horizontal line.
- VLineRubberBand & PointSelection
A vertical line.
- CrossRubberBand & PointSelection
A horizontal and a vertical line.
- RectRubberBand & RectSelection
A rectangle.
- EllipseRubberBand & RectSelection
An ellipse.
- PolygonRubberBand & PolygonSelection
A polygon.
- UserRubberBand
Values \geq UserRubberBand can be used to define additional rubber bands.

The default value is NoRubberBand.

See also:

[QwtPicker::setRubberBand\(\)](#), [QwtPicker::rubberBand\(\)](#)

6.41.2.5 enum [QwtPicker::DisplayMode](#)

- AlwaysOff
Display never.
- AlwaysOn
Display always.
- ActiveOnly
Display only when the selection is active.

See also:

[QwtPicker::setTrackerMode\(\)](#), [QwtPicker::trackerMode\(\)](#), [QwtPicker::isActive\(\)](#)

6.41.2.6 enum [QwtPicker::ResizeMode](#)

Controls what to do with the selected points of an active selection when the observed widget is resized.

- Stretch
All points are scaled according to the new size,
- KeepSize
All points remain unchanged.

The default value is Stretch.

See also:

[QwtPicker::setResizeMode\(\)](#), [QwtPicker::resize\(\)](#)

6.41.3 Constructor & Destructor Documentation

6.41.3.1 [QwtPicker::QwtPicker \(QWidget *parent\)](#) [explicit]

Constructor

Creates an picker that is enabled, but where selection flag is set to NoSelection, rubberband and tracker are disabled.

Parameters:

parent Parent widget, that will be observed

6.41.3.2 [QwtPicker::QwtPicker \(int selectionFlags, RubberBand rubberBand, DisplayMode trackerMode, QWidget *parent\)](#) [explicit]

Constructor

Parameters:

selectionFlags Or'd value of SelectionType, RectSelectionType and SelectionMode

rubberBand Rubberband style

trackerMode Tracker mode

parent Parent widget, that will be observed

6.41.3.3 QwtPicker::~~QwtPicker () [virtual]

Destructor.

6.41.4 Member Function Documentation

6.41.4.1 void QwtPicker::setSelectionFlags (int *flags*) [virtual]

Set the selection flags

Parameters:

flags Or'd value of SelectionType, RectSelectionType and SelectionMode. The default value is No-Selection.

See also:

[selectionFlags\(\)](#), [SelectionType](#), [RectSelectionType](#), [SelectionMode](#)

Reimplemented in [QwtPlotZoomer](#).

6.41.4.2 int QwtPicker::selectionFlags () const

Returns:

Selection flags, an Or'd value of SelectionType, RectSelectionType and SelectionMode.

See also:

[setSelectionFlags\(\)](#), [SelectionType](#), [RectSelectionType](#), [SelectionMode](#)

6.41.4.3 void QwtPicker::setRubberBand (**RubberBand** *rubberBand*) [virtual]

Set the rubberband style

Parameters:

rubberBand Rubberband style The default value is NoRubberBand.

See also:

[rubberBand\(\)](#), [RubberBand](#), [setRubberBandPen\(\)](#)

6.41.4.4 **QwtPicker::RubberBand** QwtPicker::rubberBand () const

Returns:

Rubberband style

See also:

[setRubberBand\(\)](#), [RubberBand](#), [rubberBandPen\(\)](#)

6.41.4.5 void QwtPicker::setTrackerMode ([DisplayMode mode](#)) [virtual]

Set the display mode of the tracker.

A tracker displays information about current position of the cursor as a string. The display mode controls if the tracker has to be displayed whenever the observed widget has focus and cursor (`AlwaysOn`), never (`AlwaysOff`), or only when the selection is active (`ActiveOnly`).

Parameters:

mode Tracker display mode

Warning:

In case of `AlwaysOn`, `mouseTracking` will be enabled for the observed widget.

See also:

[trackerMode\(\)](#), [DisplayMode](#)

6.41.4.6 [QwtPicker::DisplayMode](#) QwtPicker::trackerMode () const**Returns:**

Tracker display mode

See also:

[setTrackerMode\(\)](#), [DisplayMode](#)

6.41.4.7 void QwtPicker::setSizeMode ([SizeMode mode](#)) [virtual]

Set the resize mode.

The resize mode controls what to do with the selected points of an active selection when the observed widget is resized.

Stretch means the points are scaled according to the new size, `KeepSize` means the points remain unchanged.

The default mode is `Stretch`.

Parameters:

mode Resize mode

See also:

[resizeMode\(\)](#), [SizeMode](#)

6.41.4.8 [QwtPicker::SizeMode](#) QwtPicker::resizeMode () const**Returns:**

Resize mode

See also:

[setSizeMode\(\)](#), [SizeMode](#)

6.41.4.9 void QwtPicker::setRubberBandPen (const QPen & *pen*) [virtual]

Set the pen for the rubberband

Parameters:

pen Rubberband pen

See also:

[rubberBandPen\(\)](#), [setRubberBand\(\)](#)

6.41.4.10 QPen QwtPicker::rubberBandPen () const**Returns:**

Rubberband pen

See also:

[setRubberBandPen\(\)](#), [rubberBand\(\)](#)

6.41.4.11 void QwtPicker::setTrackerPen (const QPen & *pen*) [virtual]

Set the pen for the tracker

Parameters:

pen Tracker pen

See also:

[trackerPen\(\)](#), [setTrackerMode\(\)](#), [setTrackerFont\(\)](#)

6.41.4.12 QPen QwtPicker::trackerPen () const**Returns:**

Tracker pen

See also:

[setTrackerPen\(\)](#), [trackerMode\(\)](#), [trackerFont\(\)](#)

6.41.4.13 void QwtPicker::setTrackerFont (const QFont & *font*) [virtual]

Set the font for the tracker

Parameters:

font Tracker font

See also:

[trackerFont\(\)](#), [setTrackerMode\(\)](#), [setTrackerPen\(\)](#)

6.41.4.14 QFont QwtPicker::trackerFont () const**Returns:**

Tracker font

See also:

[setTrackerFont\(\)](#), [trackerMode\(\)](#), [trackerPen\(\)](#)

6.41.4.15 bool QwtPicker::isEnabled () const**Returns:**

true when enabled, false otherwise

See also:

[setEnabled\(\)](#), [eventFilter\(\)](#)

6.41.4.16 void QwtPicker::setEnabled (bool *enabled*) [virtual]

En/disable the picker.

When *enabled* is true an event filter is installed for the observed widget, otherwise the event filter is removed.

Parameters:

enabled true or false

See also:

[isEnabled\(\)](#), [eventFilter\(\)](#)

6.41.4.17 bool QwtPicker::isActive () const

A picker is active between [begin\(\)](#) and [end\(\)](#).

Returns:

true if the selection is active.

6.41.4.18 bool QwtPicker::eventFilter (QObject * *o*, QEvent * *e*) [virtual]

Event filter.

When [isEnabled\(\)](#) == true all events of the observed widget are filtered. Mouse and keyboard events are translated into `widgetMouse-` and `widgetKey-` and `widgetWheel-`events. Paint and Resize events are handled to keep rubberband and tracker up to date.

See also:

[event\(\)](#), [widgetMousePressEvent\(\)](#), [widgetMouseReleaseEvent\(\)](#), [widgetMouseDoubleClickEvent\(\)](#), [widgetMouseMoveEvent\(\)](#), [widgetWheelEvent\(\)](#), [widgetKeyPressEvent\(\)](#), [widgetKeyReleaseEvent\(\)](#)

6.41.4.19 `QWidget * QwtPicker::parentWidget ()`

Return the parent widget, where the selection happens.

6.41.4.20 `const QWidget * QwtPicker::parentWidget () const`

Return the parent widget, where the selection happens.

6.41.4.21 `QRect QwtPicker::pickRect () const` [virtual]

Find the area of the observed widget, where selection might happen.

Returns:

`QFrame::contentsRect()` if it is a `QFrame`, `QWidget::rect()` otherwise.

6.41.4.22 `const QwtPolygon & QwtPicker::selection () const`

Return Selected points.

6.41.4.23 `void QwtPicker::drawRubberBand (QPainter * painter) const` [virtual]

Draw a rubberband , depending on `rubberBand()` and `selectionFlags()`

Parameters:

painter Painter, initialized with clip rect

See also:

[rubberBand\(\)](#), [RubberBand](#), [selectionFlags\(\)](#)

6.41.4.24 `void QwtPicker::drawTracker (QPainter * painter) const` [virtual]

Draw the tracker

Parameters:

painter Painter

See also:

[trackerRect\(\)](#), [trackerText\(\)](#)

6.41.4.25 `QwtText QwtPicker::trackerText (const QPoint & pos) const` [virtual]

Return the label for a position.

In case of `HLineRubberBand` the label is the value of the y position, in case of `VLineRubberBand` the value of the x position. Otherwise the label contains x and y position separated by a ',' .

The format for the string conversion is "%d".

Parameters:

pos Position

Returns:

Converted position as string

Reimplemented in [QwtPlotPicker](#).

6.41.4.26 QPoint QwtPicker::trackerPosition () const**Returns:**

Current position of the tracker

6.41.4.27 QRect QwtPicker::trackerRect (const QFont & font) const

Calculate the bounding rectangle for the tracker text from the current position of the tracker

Parameters:

font Font of the tracker text

Returns:

Bounding rectangle of the tracker text

See also:

[trackerPosition\(\)](#)

6.41.4.28 void QwtPicker::selected (const QwtPolygon & pa) [signal]

A signal emitting the selected points, at the end of a selection.

Parameters:

pa Selected points

6.41.4.29 void QwtPicker::appended (const QPoint & pos) [signal]

A signal emitted when a point has been appended to the selection

Parameters:

pos Position of the appended point.

See also:

[append\(\). moved\(\)](#)

6.41.4.30 void QwtPicker::moved (const QPoint & *pos*) [signal]

A signal emitted whenever the last appended point of the selection has been moved.

Parameters:

pos Position of the moved last point of the selection.

See also:

[move\(\)](#), [appended\(\)](#)

6.41.4.31 void QwtPicker::changed (const QwtPolygon & *pa*) [signal]

A signal emitted when the active selection has been changed. This might happen when the observed widget is resized.

Parameters:

pa Changed selection

See also:

[stretchSelection\(\)](#)

6.41.4.32 bool QwtPicker::accept (QwtPolygon & *selection*) const [protected, virtual]

Validate and fixup the selection.

Accepts all selections unmodified

Parameters:

selection Selection to validate and fixup

Returns:

true, when accepted, false otherwise

Reimplemented in [QwtPlotZoomer](#).

6.41.4.33 void QwtPicker::transition (const QEvent * *e*) [protected, virtual]

Passes an event to the state machine and executes the resulting commands. Append and Move commands use the current position of the cursor (QCursor::pos()).

Parameters:

e Event

6.41.4.34 void QwtPicker::begin () [protected, virtual]

Open a selection setting the state to active

See also:

[isActive\(\)](#), [end\(\)](#), [append\(\)](#), [move\(\)](#)

Reimplemented in [QwtPlotZoomer](#).

6.41.4.35 void QwtPicker::append (const QPoint & pos) [protected, virtual]

Append a point to the selection and update rubberband and tracker. The [appended\(\)](#) signal is emitted.

Parameters:

pos Additional point

See also:

[isActive\(\)](#), [begin\(\)](#), [end\(\)](#), [move\(\)](#), [appended\(\)](#)

Reimplemented in [QwtPlotPicker](#).

6.41.4.36 void QwtPicker::move (const QPoint & pos) [protected, virtual]

Move the last point of the selection The [moved\(\)](#) signal is emitted.

Parameters:

pos New position

See also:

[isActive\(\)](#), [begin\(\)](#), [end\(\)](#), [append\(\)](#)

Reimplemented in [QwtPlotPicker](#).

6.41.4.37 bool QwtPicker::end (bool ok = true) [protected, virtual]

Close a selection setting the state to inactive.

The selection is validated and maybe fixed by [QwtPicker::accept\(\)](#).

Parameters:

ok If true, complete the selection and emit a selected signal otherwise discard the selection.

Returns:

true if the selection is accepted, false otherwise

See also:

[isActive\(\)](#), [begin\(\)](#), [append\(\)](#), [move\(\)](#), [selected\(\)](#), [accept\(\)](#)

Reimplemented in [QwtPlotPicker](#), and [QwtPlotZoomer](#).

6.41.4.38 void QwtPicker::reset () [protected, virtual]

Reset the state machine and terminate ([end\(false\)](#)) the selection

6.41.4.39 void QwtPicker::widgetMouseEvent (QMouseEvent * e) [protected, virtual]

Handle a mouse press event for the observed widget.

Begin and/or end a selection depending on the selection flags.

See also:

[QwtPicker](#), [selectionFlags\(\)](#)
[eventFilter\(\)](#), [widgetMouseReleaseEvent\(\)](#), [widgetMouseDoubleClickEvent\(\)](#), [widgetMouseMoveEvent\(\)](#), [widgetWheelEvent\(\)](#), [widgetKeyPressEvent\(\)](#), [widgetKeyReleaseEvent\(\)](#)

6.41.4.40 void QwtPicker::widgetMouseReleaseEvent (QMouseEvent * e) [protected, virtual]

Handle a mouse release event for the observed widget.

End a selection depending on the selection flags.

See also:

[QwtPicker](#), [selectionFlags\(\)](#)
[eventFilter\(\)](#), [widgetMousePressEvent\(\)](#), [widgetMouseDoubleClickEvent\(\)](#), [widgetMouseMoveEvent\(\)](#), [widgetWheelEvent\(\)](#), [widgetKeyPressEvent\(\)](#), [widgetKeyReleaseEvent\(\)](#)

Reimplemented in [QwtPlotZoomer](#).

6.41.4.41 void QwtPicker::widgetMouseDoubleClickEvent (QMouseEvent * me) [protected, virtual]

Handle mouse double click event for the observed widget.

Empty implementation, does nothing.

See also:

[eventFilter\(\)](#), [widgetMousePressEvent\(\)](#), [widgetMouseReleaseEvent\(\)](#), [widgetMouseMoveEvent\(\)](#), [widgetWheelEvent\(\)](#), [widgetKeyPressEvent\(\)](#), [widgetKeyReleaseEvent\(\)](#)

6.41.4.42 void QwtPicker::widgetMouseMoveEvent (QMouseEvent * e) [protected, virtual]

Handle a mouse move event for the observed widget.

Move the last point of the selection in case of [isActive\(\)](#) == true

See also:

[eventFilter\(\)](#), [widgetMousePressEvent\(\)](#), [widgetMouseReleaseEvent\(\)](#), [widgetMouseDoubleClickEvent\(\)](#), [widgetWheelEvent\(\)](#), [widgetKeyPressEvent\(\)](#), [widgetKeyReleaseEvent\(\)](#)

6.41.4.43 void QwtPicker::widgetWheelEvent (QWheelEvent * e) [protected, virtual]

Handle a wheel event for the observed widget.

Move the last point of the selection in case of [isActive\(\)](#) == true

See also:

[eventFilter\(\)](#), [widgetMousePressEvent\(\)](#), [widgetMouseReleaseEvent\(\)](#), [widgetMouseDoubleClickEvent\(\)](#), [widgetMouseMoveEvent\(\)](#), [widgetKeyPressEvent\(\)](#), [widgetKeyReleaseEvent\(\)](#)

6.41.4.44 void QwtPicker::widgetKeyPressEvent (QKeyEvent * ke) [protected, virtual]

Handle a key press event for the observed widget.

Selections can be completely done by the keyboard. The arrow keys move the cursor, the abort key aborts a selection. All other keys are handled by the current state machine.

See also:

[QwtPicker](#), [selectionFlags\(\)](#)
[eventFilter\(\)](#), [widgetMousePressEvent\(\)](#), [widgetMouseReleaseEvent\(\)](#), [widgetMouseDoubleClickEvent\(\)](#), [widgetMouseMoveEvent\(\)](#), [widgetWheelEvent\(\)](#), [widgetKeyReleaseEvent\(\)](#), [stateMachine\(\)](#), [QwtEventPattern::KeyPatternCode](#)

Reimplemented in [QwtPlotZoomer](#).

6.41.4.45 void QwtPicker::widgetKeyReleaseEvent (QKeyEvent * ke) [protected, virtual]

Handle a key release event for the observed widget.

Passes the event to the state machine.

See also:

[eventFilter\(\)](#), [widgetMousePressEvent\(\)](#), [widgetMouseReleaseEvent\(\)](#), [widgetMouseDoubleClickEvent\(\)](#), [widgetMouseMoveEvent\(\)](#), [widgetWheelEvent\(\)](#), [widgetKeyPressEvent\(\)](#), [stateMachine\(\)](#)

6.41.4.46 void QwtPicker::widgetLeaveEvent (QEvent *) [protected, virtual]

Handle a leave event for the observed widget.

See also:

[eventFilter\(\)](#), [widgetMousePressEvent\(\)](#), [widgetMouseReleaseEvent\(\)](#), [widgetMouseDoubleClickEvent\(\)](#), [widgetWheelEvent\(\)](#), [widgetKeyPressEvent\(\)](#), [widgetKeyReleaseEvent\(\)](#)

6.41.4.47 void QwtPicker::stretchSelection (const QSize & oldSize, const QSize & newSize) [protected, virtual]

Scale the selection by the ratios of oldSize and newSize The [changed\(\)](#) signal is emitted.

Parameters:

oldSize Previous size

newSize Current size

See also:

[ResizeMode](#), [setResizeMode\(\)](#), [resizeMode\(\)](#)

6.41.4.48 `QwtPickerMachine * QwtPicker::stateMachine (int flags) const` [protected, virtual]

Create a state machine depending on the selection flags.

- PointSelection | ClickSelection
QwtPickerClickPointMachine()
- PointSelection | DragSelection
QwtPickerDragPointMachine()
- RectSelection | ClickSelection
QwtPickerClickRectMachine()
- RectSelection | DragSelection
QwtPickerDragRectMachine()
- PolygonSelection
QwtPickerPolygonMachine()

See also:

[setSelectionFlags\(\)](#)

6.41.4.49 `void QwtPicker::updateDisplay ()` [protected, virtual]

Update the state of rubberband and tracker label.

6.41.4.50 `const QWidget * QwtPicker::rubberBandWidget () const` [protected]

Returns:

Widget displaying the rubberband

6.41.4.51 `const QWidget * QwtPicker::trackerWidget () const` [protected]

Returns:


Widget displaying the tracker text

6.42 QwtPickerClickPointMachine Class Reference

A state machine for point selections.

```
#include <qwt_picker_machine.h>
```

Inheritance diagram for QwtPickerClickPointMachine:



Public Member Functions

- virtual CommandList [transition](#) (const [QwtEventPattern](#) &, const [QEvent](#) *)

6.42.1 Detailed Description

A state machine for point selections.

Pressing [QwtEventPattern::MouseSelect1](#) or [QwtEventPattern::KeySelect1](#) selects a point.

See also:

[QwtEventPattern::MousePatternCode](#), [QwtEventPattern::KeyPatternCode](#)

6.42.2 Member Function Documentation**6.42.2.1 QwtPickerMachine::CommandList QwtPickerClickPointMachine::transition (const [QwtEventPattern](#) &, const [QEvent](#) *) [virtual]**

Transition.


Implements [QwtPickerMachine](#).

6.43 QwtPickerClickRectMachine Class Reference

A state machine for rectangle selections.

```
#include <qwt_picker_machine.h>
```

Inheritance diagram for [QwtPickerClickRectMachine](#):

**Public Member Functions**

- virtual CommandList [transition](#) (const [QwtEventPattern](#) &, const [QEvent](#) *)

6.43.1 Detailed Description

A state machine for rectangle selections.

Pressing [QwtEventPattern::MouseSelect1](#) starts the selection, releasing it selects the first point. Pressing it again selects the second point and terminates the selection. Pressing [QwtEventPattern::KeySelect1](#) also starts the selection, a second press selects the first point. A third one selects the second point and terminates the selection.

See also:

[QwtEventPattern::MousePatternCode](#), [QwtEventPattern::KeyPatternCode](#)

6.43.2 Member Function Documentation

6.43.2.1 QwtPickerMachine::CommandList QwtPickerClickRectMachine::transition (const QwtEventPattern &, const QEvent *) [virtual]

Transition.


Implements [QwtPickerMachine](#).

6.44 QwtPickerDragPointMachine Class Reference

A state machine for point selections.

```
#include <qwt_picker_machine.h>
```

Inheritance diagram for QwtPickerDragPointMachine:



Public Member Functions

- virtual CommandList [transition](#) (const [QwtEventPattern](#) &, const QEvent *)

6.44.1 Detailed Description

A state machine for point selections.

Pressing [QwtEventPattern::MouseSelect1](#) or [QwtEventPattern::KeySelect1](#) starts the selection, releasing [QwtEventPattern::MouseSelect1](#) or a second press of [QwtEventPattern::KeySelect1](#) terminates it.

6.44.2 Member Function Documentation

6.44.2.1 QwtPickerMachine::CommandList QwtPickerDragPointMachine::transition (const QwtEventPattern &, const QEvent *) [virtual]

Transition.


Implements [QwtPickerMachine](#).

6.45 QwtPickerDragRectMachine Class Reference

A state machine for rectangle selections.

```
#include <qwt_picker_machine.h>
```

Inheritance diagram for QwtPickerDragRectMachine:



Public Member Functions

- virtual CommandList [transition](#) (const [QwtEventPattern](#) &, const [QEvent](#) *)

6.45.1 Detailed Description

A state machine for rectangle selections.

Pressing [QwtEventPattern::MouseDown1](#) selects the first point, releasing it the second point. Pressing [QwtEventPattern::KeySelect1](#) also selects the first point, a second press selects the second point and terminates the selection.

See also:

[QwtEventPattern::MousePatternCode](#), [QwtEventPattern::KeyPatternCode](#)

6.45.2 Member Function Documentation

6.45.2.1 [QwtPickerMachine::CommandList](#) [QwtPickerDragRectMachine::transition](#) (const [QwtEventPattern](#) &, const [QEvent](#) *) [virtual]

Transition.


Implements [QwtPickerMachine](#).

6.46 QwtPickerMachine Class Reference

A state machine for [QwtPicker](#) selections.

```
#include <qwt_picker_machine.h>
```

Inheritance diagram for [QwtPickerMachine](#):



Public Types

- enum [Command](#) {
Begin,
Append,
Move,
End }
- typedef `QList< Command >` **CommandList**

Public Member Functions

- virtual [~QwtPickerMachine](#) ()
- virtual CommandList [transition](#) (const [QwtEventPattern](#) &, const [QEvent](#) *)=0
- void [reset](#) ()
- int [state](#) () const
- void [setState](#) (int)

Protected Member Functions

- [QwtPickerMachine](#) ()

6.46.1 Detailed Description

A state machine for [QwtPicker](#) selections.

[QwtPickerMachine](#) accepts key and mouse events and translates them into selection commands.

See also:

[QwtEventPattern::MousePatternCode](#), [QwtEventPattern::KeyPatternCode](#)

6.46.2 Member Enumeration Documentation

6.46.2.1 enum [QwtPickerMachine::Command](#)

Commands - the output of the state machine.

6.46.3 Constructor & Destructor Documentation

6.46.3.1 [QwtPickerMachine::~~QwtPickerMachine](#) () [virtual]

Destructor.

6.46.3.2 [QwtPickerMachine::QwtPickerMachine](#) () [protected]

Constructor.

6.46.4 Member Function Documentation

6.46.4.1 virtual CommandList [QwtPickerMachine::transition](#) (const [QwtEventPattern](#) &, const [QEvent](#) *) [pure virtual]

Transition.

Implemented in [QwtPickerClickPointMachine](#), [QwtPickerDragPointMachine](#), [QwtPickerClickRectMachine](#), [QwtPickerDragRectMachine](#), and [QwtPickerPolygonMachine](#).

6.46.4.2 void [QwtPickerMachine::reset](#) ()

Set the current state to 0.

6.46.4.3 int QwtPickerMachine::state () const

Return the current state.

6.46.4.4 void QwtPickerMachine::setState (int)


Change the current state.

6.47 QwtPickerPolygonMachine Class Reference

A state machine for polygon selections.

```
#include <qwt_picker_machine.h>
```

Inheritance diagram for QwtPickerPolygonMachine:

**Public Member Functions**

- virtual CommandList [transition](#) (const [QwtEventPattern](#) &, const QEvent *)

6.47.1 Detailed Description

A state machine for polygon selections.

Pressing [QwtEventPattern::MouseSelect1](#) or [QwtEventPattern::KeySelect1](#) starts the selection and selects the first point, or appends a point. Pressing [QwtEventPattern::MouseSelect2](#) or [QwtEventPattern::KeySelect2](#) appends the last point and terminates the selection.

See also:

[QwtEventPattern::MousePatternCode](#), [QwtEventPattern::KeyPatternCode](#)

6.47.2 Member Function Documentation**6.47.2.1 QwtPickerMachine::CommandList QwtPickerPolygonMachine::transition (const [QwtEventPattern](#) &, const QEvent *) [virtual]**

Transition.


Implements [QwtPickerMachine](#).

6.48 QwtPlainTextEngine Class Reference

A text engine for plain texts.

```
#include <qwt_text_engine.h>
```

Inheritance diagram for QwtPlainTextEngine:



Public Member Functions

- [QwtPlainTextEngine \(\)](#)
- virtual [~QwtPlainTextEngine \(\)](#)
- virtual int [heightForWidth](#) (const QFont &font, int flags, const QString &text, int width) const
- virtual QSize [textSize](#) (const QFont &font, int flags, const QString &text) const
- virtual void [draw](#) (QPainter *painter, const QRect &rect, int flags, const QString &text) const
- virtual bool [mightRender](#) (const QString &) const
- virtual void [textMargins](#) (const QFont &, const QString &, int &left, int &right, int &top, int &bottom) const

6.48.1 Detailed Description

A text engine for plain texts.

[QwtPlainTextEngine](#) renders texts using the basic Qt classes QPainter and QFontMetrics.

6.48.2 Constructor & Destructor Documentation

6.48.2.1 QwtPlainTextEngine::QwtPlainTextEngine ()

Constructor.

6.48.2.2 QwtPlainTextEngine::~~QwtPlainTextEngine () [virtual]

Destructor.

6.48.3 Member Function Documentation

6.48.3.1 int QwtPlainTextEngine::heightForWidth (const QFont & font, int flags, const QString & text, int width) const [virtual]

Find the height for a given width

Parameters:

font Font of the text

flags Bitwise OR of the flags used like in QPainter::drawText

text Text to be rendered

width Width

Returns:

Calculated height

Implements [QwtTextEngine](#).

6.48.3.2 QSize QwtPlainTextEngine::textSize (const QFont & *font*, int *flags*, const QString & *text*) const [virtual]

Returns the size, that is needed to render text

Parameters:

font Font of the text
flags Bitwise OR of the flags used like in QPainter::drawText
text Text to be rendered

Returns:

Calculated size

Implements [QwtTextEngine](#).

6.48.3.3 void QwtPlainTextEngine::draw (QPainter * *painter*, const QRect & *rect*, int *flags*, const QString & *text*) const [virtual]

Draw the text in a clipping rectangle.

A wrapper for QPainter::drawText.

Parameters:

painter Painter
rect Clipping rectangle
flags Bitwise OR of the flags used like in QPainter::drawText
text Text to be rendered

Implements [QwtTextEngine](#).

6.48.3.4 bool QwtPlainTextEngine::mightRender (const QString &) const [virtual]

Test if a string can be rendered by this text engine.

Returns:

Always true. All texts can be rendered by [QwtPlainTextEngine](#)

Implements [QwtTextEngine](#).

6.48.3.5 void QwtPlainTextEngine::textMargins (const QFont & *font*, const QString &, int & *left*, int & *right*, int & *top*, int & *bottom*) const [virtual]

Return margins around the texts

Parameters:

font Font of the text
left Return 0
right Return 0
top Return value for the top margin
bottom Return value for the bottom margin

Implements [QwtTextEngine](#).

6.49 QwtPlot Class Reference

A 2-D plotting widget.

```
#include <qwt_plot.h>
```

Inheritance diagram for QwtPlot:



Public Types

- enum [Axis](#) {
 yLeft,
 yRight,
 xBottom,
 xTop,
 axisCnt }
- enum [LegendPosition](#) {
 LeftLegend,
 RightLegend,
 BottomLegend,
 TopLegend,
 ExternalLegend }

Public Slots

- virtual void [clear](#) ()
- virtual void [replot](#) ()
- void [autoRefresh](#) ()

Signals

- void [legendClicked](#) ([QwtPlotItem](#) *plotItem)
- void [legendChecked](#) ([QwtPlotItem](#) *plotItem, bool on)

Public Member Functions

- [QwtPlot](#) (QWidget *p=NULL)
- [QwtPlot](#) (const [QwtText](#) &title, QWidget *p=NULL)
- virtual [~QwtPlot](#) ()
- void **applyProperties** (const QString &)
- QString **grabProperties** () const
- void [setAutoReplot](#) (bool tf=true)
- bool [autoReplot](#) () const

- void `print` (QPaintDevice &p, const `QwtPlotPrintFilter` &=`QwtPlotPrintFilter`()) const
- virtual void `print` (QPainter *, const QRect &rect, const `QwtPlotPrintFilter` &=`QwtPlotPrintFilter`()) const
- `QwtPlotLayout` * `plotLayout` ()
- const `QwtPlotLayout` * `plotLayout` () const
- void `setMargin` (int margin)
- int `margin` () const
- void `setTitle` (const QString &)
- void `setTitle` (const `QwtText` &t)
- `QwtText` `title` () const
- `QwtTextLabel` * `titleLabel` ()
- const `QwtTextLabel` * `titleLabel` () const
- `QwtPlotCanvas` * `canvas` ()
- const `QwtPlotCanvas` * `canvas` () const
- void `setCanvasBackground` (const QColor &c)
- const QColor & `canvasBackground` () const
- void `setCanvasLineWidth` (int w)
- int `canvasLineWidth` () const
- virtual `QwtScaleMap` `canvasMap` (int axisId) const
- double `invTransform` (int axisId, int pos) const
- int `transform` (int axisId, double value) const
- `QwtScaleEngine` * `axisScaleEngine` (int axisId)
- const `QwtScaleEngine` * `axisScaleEngine` (int axisId) const
- void `setAxisScaleEngine` (int axisId, `QwtScaleEngine` *)
- void `setAxisAutoScale` (int axisId)
- bool `axisAutoScale` (int axisId) const
- void `enableAxis` (int axisId, bool tf=true)
- bool `axisEnabled` (int axisId) const
- void `setAxisFont` (int axisId, const QFont &f)
- QFont `axisFont` (int axisId) const
- void `setAxisScale` (int axisId, double min, double max, double step=0)
- void `setAxisScaleDiv` (int axisId, const `QwtScaleDiv` &)
- void `setAxisScaleDraw` (int axisId, `QwtScaleDraw` *)
- double `axisStepSize` (int axisId) const
- const `QwtScaleDiv` * `axisScaleDiv` (int axisId) const
- `QwtScaleDiv` * `axisScaleDiv` (int axisId)
- const `QwtScaleDraw` * `axisScaleDraw` (int axisId) const
- `QwtScaleDraw` * `axisScaleDraw` (int axisId)
- const `QwtScaleWidget` * `axisWidget` (int axisId) const
- `QwtScaleWidget` * `axisWidget` (int axisId)
- void `setAxisLabelAlignment` (int axisId, Qt::Alignment)
- void `setAxisLabelRotation` (int axisId, double rotation)
- void `setAxisTitle` (int axisId, const QString &)
- void `setAxisTitle` (int axisId, const `QwtText` &)
- `QwtText` `axisTitle` (int axisId) const
- void `setAxisMaxMinor` (int axisId, int maxMinor)
- int `axisMaxMajor` (int axisId) const
- void `setAxisMaxMajor` (int axisId, int maxMajor)
- int `axisMaxMinor` (int axisId) const
- void `insertLegend` (`QwtLegend` *, `LegendPosition`=`QwtPlot::RightLegend`, double ratio=-1.0)

- [QwtLegend * legend \(\)](#)
- [const QwtLegend * legend \(\) const](#)
- [virtual void polish \(\)](#)
- [virtual QSize sizeHint \(\) const](#)
- [virtual QSize minimumSizeHint \(\) const](#)
- [virtual void updateLayout \(\)](#)
- [virtual void drawCanvas \(QPainter *\)](#)
- [void updateAxes \(\)](#)
- [virtual bool event \(QEvent *\)](#)

Protected Slots

- [virtual void legendItemClicked \(\)](#)
- [virtual void legendItemChecked \(bool\)](#)

Protected Member Functions

- [virtual void drawItems \(QPainter *, const QRect &, const QwtScaleMap maps\[axisCnt\], const QwtPlotPrintFilter &\) const](#)
- [virtual void updateTabOrder \(\)](#)
- [virtual void resizeEvent \(QResizeEvent *e\)](#)
- [virtual void printLegendItem \(QPainter *, const QWidget *, const QRect &\) const](#)
- [virtual void printTitle \(QPainter *, const QRect &\) const](#)
- [virtual void printScale \(QPainter *, int axisId, int startDist, int endDist, int baseDist, const QRect &\) const](#)
- [virtual void printCanvas \(QPainter *, const QRect &boundingRect, const QRect &canvasRect, const QwtScaleMap maps\[axisCnt\], const QwtPlotPrintFilter &\) const](#)
- [virtual void printLegend \(QPainter *, const QRect &\) const](#)

Static Protected Member Functions

- [static bool axisValid \(int axisId\)](#)

6.49.1 Detailed Description

A 2-D plotting widget.

[QwtPlot](#) is a widget for plotting two-dimensional graphs. An unlimited number of plot items can be displayed on its canvas. Plot items might be curves ([QwtPlotCurve](#)), markers ([QwtPlotMarker](#)), the grid ([QwtPlotGrid](#)), or anything else derived from [QwtPlotItem](#). A plot can have up to four axes, with each plot item attached to an x- and a y axis. The scales at the axes can be explicitly set ([QwtScaleDiv](#)), or are calculated from the plot items, using algorithms ([QwtScaleEngine](#)) which can be configured separately for each axis.

Example

The following example shows (schematically) the most simple way to use [QwtPlot](#). By default, only the left and bottom axes are visible and their scales are computed automatically.

```
#include <qwt_plot.h>
#include <qwt_plot_curve.h>

QwtPlot *myPlot = new QwtPlot("Two Curves", parent);

// add curves
QwtPlotCurve *curve1 = new QwtPlotCurve("Curve 1");
QwtPlotCurve *curve2 = new QwtPlotCurve("Curve 2");

// copy the data into the curves
curve1->setData(...);
curve2->setData(...);

curve1->attach(myPlot);
curve2->attach(myPlot);

// finally, refresh the plot
myPlot->replot();
```

6.49.2 Member Enumeration Documentation

6.49.2.1 enum [QwtPlot::Axis](#)

Axis index

- `yLeft`
- `yRight`
- `xBottom`
- `xTop`

6.49.2.2 enum [QwtPlot::LegendPosition](#)

Position of the legend, relative to the canvas.

- `LeftLegend`
The legend will be left from the `yLeft` axis.
- `RightLegend`
The legend will be right from the `yLeft` axis.
- `BottomLegend`
The legend will be right below the `xBottom` axis.
- `TopLegend`
The legend will be between `xTop` axis and the title.
- `ExternalLegend`
External means that only the content of the legend will be handled by [QwtPlot](#), but not its geometry. This might be interesting if an application wants to have a legend in an external window (or on the canvas).

Note:

In case of `ExternalLegend`, the legend is not printed by `print()`.

See also:

[insertLegend\(\)](#)

6.49.3 Constructor & Destructor Documentation

6.49.3.1 QwtPlot::QwtPlot (QWidget * *parent* = NULL) [explicit]

Constructor.

Parameters:

parent Parent widget

6.49.3.2 QwtPlot::QwtPlot (const QwtText & *title*, QWidget * *parent* = NULL) [explicit]

Constructor.

Parameters:

title Title text

parent Parent widget

6.49.3.3 QwtPlot::~~QwtPlot () [virtual]

Destructor.

6.49.4 Member Function Documentation

6.49.4.1 void QwtPlot::setAutoReplot (bool *tf* = true)

Set or reset the autoReplot option.

If the autoReplot option is set, the plot will be updated implicitly by manipulating member functions. Since this may be time-consuming, it is recommended to leave this option switched off and call [replot\(\)](#) explicitly if necessary.

The autoReplot option is set to false by default, which means that the user has to call [replot\(\)](#) in order to make changes visible.

Parameters:

tf true or false. Defaults to true.

See also:

[replot\(\)](#)

6.49.4.2 bool QwtPlot::autoReplot () const

Returns:

true if the autoReplot option is set.

6.49.4.3 `void QwtPlot::print (QPaintDevice & paintDev, const QwtPlotPrintFilter & pfilter = QwtPlotPrintFilter ()) const`

Print the plot to a QPaintDevice (QPrinter) This function prints the contents of a QwtPlot instance to QPaintDevice object. The size is derived from its device metrics.

Parameters:

paintDev device to paint on, often a printer

pfilter print filter

See also:

[QwtPlotPrintFilter](#)

6.49.4.4 `void QwtPlot::print (QPainter * painter, const QRect & plotRect, const QwtPlotPrintFilter & pfilter = QwtPlotPrintFilter ()) const` [virtual]

Paint the plot into a given rectangle. Paint the contents of a QwtPlot instance into a given rectangle.

Parameters:

painter Painter

plotRect Bounding rectangle

pfilter Print filter

See also:

[QwtPlotPrintFilter](#)

6.49.4.5 `QwtPlotLayout * QwtPlot::plotLayout ()`

Returns:

the plot's title

6.49.4.6 `const QwtPlotLayout * QwtPlot::plotLayout () const`

Returns:

the plot's titel label.

6.49.4.7 `void QwtPlot::setMargin (int margin)`

Change the margin of the plot. The margin is the space around all components.

Parameters:

margin new margin

See also:

[QwtPlotLayout::setMargin\(\)](#), [margin\(\)](#), [plotLayout\(\)](#)

6.49.4.8 `int QwtPlot::margin () const`**Returns:**

margin

See also:

[setMargin\(\)](#), [QwtPlotLayout::margin\(\)](#), [plotLayout\(\)](#)

6.49.4.9 `void QwtPlot::setTitle (const QString & title)`

Change the plot's title

Parameters:

title New title

6.49.4.10 `void QwtPlot::setTitle (const QwtText & title)`

Change the plot's title

Parameters:

title New title

6.49.4.11 `QwtText QwtPlot::title () const`**Returns:**

the plot's title

6.49.4.12 `QwtTextLabel * QwtPlot::titleLabel ()`**Returns:**

the plot's titel label.

6.49.4.13 `const QwtTextLabel * QwtPlot::titleLabel () const`**Returns:**

the plot's titel label.

6.49.4.14 `QwtPlotCanvas * QwtPlot::canvas ()`**Returns:**

the plot's canvas

6.49.4.15 `const QwtPlotCanvas * QwtPlot::canvas () const`**Returns:**

the plot's canvas

6.49.4.16 `void QwtPlot::setCanvasBackground (const QColor & c)`

Change the background of the plotting area.

Sets *c* to `QColorGroup::Background` of all colorgroups of the palette of the canvas. Using `canvas()->setPalette()` is a more powerful way to set these colors.

Parameters:

c new background color

6.49.4.17 `const QColor & QwtPlot::canvasBackground () const`

Nothing else than: `canvas()->palette().color(QPalette::Normal, QColorGroup::Background)`;

Returns:

the background color of the plotting area.

6.49.4.18 `void QwtPlot::setCanvasLineWidth (int w)`

Change the border width of the plotting area Nothing else than `canvas()->setLineWidth(w)`, left for compatibility only.

Parameters:

w new border width

6.49.4.19 `int QwtPlot::canvasLineWidth () const`

Nothing else than: `canvas()->lineWidth()`, left for compatibility only.

Returns:

the border width of the plotting area

6.49.4.20 `QwtScaleMap QwtPlot::canvasMap (int axisId) const` [virtual]**Parameters:**

axisId Axis

Returns:

Map for the axis on the canvas. With this map pixel coordinates can translated to plot coordinates and vice versa.

See also:

[QwtScaleMap](#), [transform\(\)](#), [invTransform\(\)](#)

6.49.4.21 double QwtPlot::invTransform (int *axisId*, int *pos*) const

Transform the x or y coordinate of a position in the drawing region into a value.

Parameters:

axisId axis index
pos position

Warning:

The position can be an x or a y coordinate, depending on the specified axis.

6.49.4.22 int QwtPlot::transform (int *axisId*, double *value*) const

Transform a value into a coordinate in the plotting region.

Parameters:

axisId axis index
value value

Returns:

X or y coordinate in the plotting region corresponding to the value.

6.49.4.23 [QwtScaleEngine](#) * QwtPlot::axisScaleEngine (int *axisId*)**Parameters:**

axisId axis index

Returns:

Scale engine for a specific axis

6.49.4.24 const [QwtScaleEngine](#) * QwtPlot::axisScaleEngine (int *axisId*) const**Parameters:**

axisId axis index

Returns:

Scale engine for a specific axis

6.49.4.25 void QwtPlot::setAxisScaleEngine (int *axisId*, [QwtScaleEngine](#) * *scaleEngine*)

Change the scale engine for an axis

Parameters:

axisId axis index
scaleEngine Scale engine

See also:

[axisScaleEngine\(\)](#)

6.49.4.26 void QwtPlot::setAxisAutoScale (int *axisId*)

Enable autoscaling for a specified axis.

This member function is used to switch back to autoscaling mode after a fixed scale has been set. Autoscaling is enabled by default.

Parameters:

axisId axis index

See also:

[QwtPlot::setAxisScale\(\)](#), [QwtPlot::setAxisScaleDiv\(\)](#)

6.49.4.27 bool QwtPlot::axisAutoScale (int *axisId*) const**Returns:**

`true` if autoscaling is enabled

Parameters:

axisId axis index

6.49.4.28 void QwtPlot::enableAxis (int *axisId*, bool *tf* = `true`)

Enable or disable a specified axis.

When an axis is disabled, this only means that it is not visible on the screen. Curves, markers and can be attached to disabled axes, and transformation of screen coordinates into values works as normal.

Only `xBottom` and `yLeft` are enabled by default.

Parameters:

axisId axis index

tf `true` (enabled) or `false` (disabled)

6.49.4.29 bool QwtPlot::axisEnabled (int *axisId*) const**Returns:**

`true` if a specified axis is enabled

Parameters:

axisId axis index

6.49.4.30 void QwtPlot::setAxisFont (int *axisId*, const QFont & *f*)

Change the font of an axis.

Parameters:

axisId axis index

f font

Warning:

This function changes the font of the tick labels, not of the axis title.

6.49.4.31 QFont QwtPlot::axisFont (int *axisId*) const**Returns:**

the font of the scale labels for a specified axis

Parameters:

axisId axis index

6.49.4.32 void QwtPlot::setAxisScale (int *axisId*, double *min*, double *max*, double *stepSize* = 0)

Disable autoscaling and specify a fixed scale for a selected axis.

Parameters:

axisId axis index

min

max minimum and maximum of the scale

stepSize Major step size. If `step == 0`, the step size is calculated automatically using the max-Major setting.

See also:

[setAxisMaxMajor\(\)](#), [setAxisAutoScale\(\)](#)

6.49.4.33 void QwtPlot::setAxisScaleDiv (int *axisId*, const [QwtScaleDiv](#) & *scaleDiv*)

Disable autoscaling and specify a fixed scale for a selected axis.

Parameters:

axisId axis index

scaleDiv Scale division

See also:

[setAxisScale\(\)](#), [setAxisAutoScale\(\)](#)

6.49.4.34 void QwtPlot::setAxisScaleDraw (int *axisId*, [QwtScaleDraw](#) * *scaleDraw*)

Set a scale draw.

Parameters:

axisId axis index

scaleDraw object responsible for drawing scales.

By passing *scaleDraw* it is possible to extend [QwtScaleDraw](#) functionality and let it take place in [QwtPlot](#). Please note that *scaleDraw* has to be created with `new` and will be deleted by the corresponding [QwtScale](#) member (like a child object).

See also:

[QwtScaleDraw](#), [QwtScaleWidget](#)

Warning:

The attributes of *scaleDraw* will be overwritten by those of the previous [QwtScaleDraw](#).

6.49.4.35 `double QwtPlot::axisStepSize (int axisId) const`

Return the step size parameter, that has been set in `setAxisScale`. This doesn't need to be the step size of the current scale.

Parameters:

axisId axis index

Returns:

step size parameter value

See also:

[setAxisScale\(\)](#)

6.49.4.36 `const QwtScaleDiv * QwtPlot::axisScaleDiv (int axisId) const`

Return the scale division of a specified axis.

`axisScaleDiv(axisId)->lowerBound()`, `axisScaleDiv(axisId)->upperBound()` are the current limits of the axis scale.

Parameters:

axisId axis index

Returns:

Scale division

See also:

[QwtScaleDiv](#), [setAxisScaleDiv\(\)](#)

6.49.4.37 `QwtScaleDiv * QwtPlot::axisScaleDiv (int axisId)`

Return the scale division of a specified axis.

`axisScaleDiv(axisId)->lowerBound()`, `axisScaleDiv(axisId)->upperBound()` are the current limits of the axis scale.

Parameters:

axisId axis index

Returns:

Scale division

See also:

[QwtScaleDiv](#), [setAxisScaleDiv\(\)](#)

6.49.4.38 `const QwtScaleDraw * QwtPlot::axisScaleDraw (int axisId) const`**Returns:**

the scale draw of a specified axis

Parameters:

axisId axis index

Returns:

specified scaleDraw for axis, or NULL if axis is invalid.

See also:

[QwtScaleDraw](#)

6.49.4.39 `QwtScaleDraw * QwtPlot::axisScaleDraw (int axisId)`**Returns:**

the scale draw of a specified axis

Parameters:

axisId axis index

Returns:

specified scaleDraw for axis, or NULL if axis is invalid.

See also:

[QwtScaleDraw](#)

6.49.4.40 `const QwtScaleWidget * QwtPlot::axisWidget (int axisId) const`**Returns:**

specified axis, or NULL if axisId is invalid.

Parameters:

axisId axis index

6.49.4.41 [QwtScaleWidget](#) * [QwtPlot::axisWidget](#) (int *axisId*)**Returns:**

specified axis, or NULL if *axisId* is invalid.

Parameters:

axisId axis index

6.49.4.42 void [QwtPlot::setAxisLabelAlignment](#) (int *axisId*, Qt::Alignment *alignment*)

Change the alignment of the tick labels

Parameters:

axisId axis index

alignment Or'd Qt::AlignmentFlags <see qnamespace.h>

See also:

[QwtScaleDraw::setLabelAlignment\(\)](#)

6.49.4.43 void [QwtPlot::setAxisLabelRotation](#) (int *axisId*, double *rotation*)

Rotate all tick labels

Parameters:

axisId axis index

rotation Angle in degrees. When changing the label rotation, the label alignment might be adjusted too.

See also:

[QwtScaleDraw::setLabelRotation\(\)](#), [setAxisLabelAlignment\(\)](#)

6.49.4.44 void [QwtPlot::setAxisTitle](#) (int *axisId*, const QString & *title*)

Change the title of a specified axis.

Parameters:

axisId axis index

title axis title

6.49.4.45 void [QwtPlot::setAxisTitle](#) (int *axisId*, const [QwtText](#) & *title*)

Change the title of a specified axis.

Parameters:

axisId axis index

title axis title

6.49.4.46 [QwtText](#) QwtPlot::axisTitle (int *axisId*) const**Returns:**

the title of a specified axis

Parameters:

axisId axis index

6.49.4.47 void QwtPlot::setAxisMaxMinor (int *axisId*, int *maxMinor*)

Set the maximum number of minor scale intervals for a specified axis

Parameters:

axisId axis index

maxMinor maximum number of minor steps

See also:

[axisMaxMinor\(\)](#)

6.49.4.48 int QwtPlot::axisMaxMajor (int *axisId*) const**Returns:**

the maximum number of major ticks for a specified axis

Parameters:

axisId axis index sa [setAxisMaxMajor\(\)](#)

6.49.4.49 void QwtPlot::setAxisMaxMajor (int *axisId*, int *maxMajor*)

Set the maximum number of major scale intervals for a specified axis

Parameters:

axisId axis index

maxMajor maximum number of major steps

See also:

[axisMaxMajor\(\)](#)

6.49.4.50 int QwtPlot::axisMaxMinor (int *axisId*) const**Returns:**

the maximum number of minor ticks for a specified axis

Parameters:

axisId axis index sa [setAxisMaxMinor\(\)](#)

6.49.4.51 void `QwtPlot::insertLegend (QwtLegend * legend, QwtPlot::LegendPosition pos = QwtPlot::RightLegend, double ratio = -1.0)`

Insert a legend.

If the position legend is `QwtPlot::LeftLegend` or `QwtPlot::RightLegend` the legend will be organized in one column from top to down. Otherwise the legend items will be placed in a table with a best fit number of columns from left to right.

If `pos != QwtPlot::ExternalLegend` the plot widget will become parent of the legend. It will be deleted when the plot is deleted, or another legend is set with `insertLegend()`.

Parameters:

legend Legend

pos The legend's position. For top/left position the number of columns will be limited to 1, otherwise it will be set to unlimited.

ratio Ratio between legend and the bounding rect of title, canvas and axes. The legend will be shrunk if it would need more space than the given ratio. The ratio is limited to]0.0 .. 1.0]. In case of ≤ 0.0 it will be reset to the default ratio. The default vertical/horizontal ratio is 0.33/0.5.

See also:

[legend\(\)](#), [QwtPlotLayout::legendPosition\(\)](#), [QwtPlotLayout::setLegendPosition\(\)](#)

6.49.4.52 `QwtLegend * QwtPlot::legend ()`

Returns:

the plot's legend

See also:

[insertLegend\(\)](#)

6.49.4.53 `const QwtLegend * QwtPlot::legend () const`

Returns:

the plot's legend

See also:

[insertLegend\(\)](#)

6.49.4.54 void `QwtPlot::polish ()` [virtual]

Polish.

6.49.4.55 `QSize QwtPlot::sizeHint () const` [virtual]

Return sizeHint

See also:

[minimumSizeHint\(\)](#)

6.49.4.56 `QSize QwtPlot::minimumSizeHint () const` [virtual]

Return a minimum size hint.

6.49.4.57 `void QwtPlot::updateLayout ()` [virtual]

Adjust plot content to its current size.

See also:

[resizeEvent\(\)](#)

6.49.4.58 `void QwtPlot::drawCanvas (QPainter * painter)` [virtual]

Redraw the canvas.

Parameters:

painter Painter used for drawing

Warning:

`drawCanvas` calls `drawItems` what is also used for printing. Applications that like to add individual plot items better overload [drawItems\(\)](#)

See also:

[drawItems\(\)](#)

6.49.4.59 `void QwtPlot::updateAxes ()`

Rebuild the scales.

6.49.4.60 `bool QwtPlot::event (QEvent *)` [virtual]

Adds handling of layout requests.

6.49.4.61 `void QwtPlot::legendClicked (QwtPlotItem * plotItem)` [signal]

A signal which is emitted when the user has clicked on a legend item, which is in `QwtLegend::Clickable-Item` mode.

Parameters:

plotItem Corresponding plot item of the selected legend item

Note:

clicks are disabled as default

See also:

[QwtLegend::setItemMode\(\)](#), [QwtLegend::itemMode\(\)](#)

6.49.4.62 void QwtPlot::legendChecked (QwtPlotItem * *plotItem*, bool *on*) [signal]

A signal which is emitted when the user has clicked on a legend item, which is in QwtLegend::Checkable-Item mode

Parameters:

plotItem Corresponding plot item of the selected legend item
on True when the legend item is checked

Note:

clicks are disabled as default

See also:

[QwtLegend::setItemMode\(\)](#), [QwtLegend::itemMode\(\)](#)

6.49.4.63 void QwtPlot::clear () [virtual, slot]

Remove all curves and markers

Deprecated

Use [QwtPlotDeict::detachItems](#) instead

6.49.4.64 void QwtPlot::replot () [virtual, slot]

Redraw the plot.

If the `autoReplot` option is not set (which is the default) or if any curves are attached to raw data, the plot has to be refreshed explicitly in order to make changes visible.

See also:

[setAutoReplot\(\)](#)

Warning:

Calls [canvas\(\)->repaint](#), take care of infinite recursions

6.49.4.65 void QwtPlot::autoRefresh () [slot]

Replots the plot if [QwtPlot::autoReplot\(\)](#) is true.

6.49.4.66 void QwtPlot::legendItemClicked () [protected, virtual, slot]

Called internally when the legend has been clicked on. Emits a [legendClicked\(\)](#) signal.

6.49.4.67 void QwtPlot::legendItemChecked (bool *on*) [protected, virtual, slot]

Called internally when the legend has been checked. Emits a [legendClicked\(\)](#) signal.

6.49.4.68 `bool QwtPlot::axisValid (int axisId)` [static, protected]

Returns:

true if the specified axis exists, otherwise false

Parameters:

axisId axis index

6.49.4.69 `void QwtPlot::drawItems (QPainter * painter, const QRect & rect, const QwtScaleMap map[axisCnt], const QwtPlotPrintFilter & pfilter) const` [protected, virtual]

Redraw the canvas items.

Parameters:

painter Painter used for drawing

rect Bounding rectangle where to paint

map QwtPlot::axisCnt maps, mapping between plot and paint device coordinates

pfilter Plot print filter

6.49.4.70 `void QwtPlot::updateTabOrder ()` [protected, virtual]

Update the focus tab order

The order is changed so that the canvas will be in front of the first legend item, or behind the last legend item - depending on the position of the legend.

6.49.4.71 `void QwtPlot::resizeEvent (QResizeEvent * e)` [protected, virtual]

Resize and update internal layout

Parameters:

e Resize event

6.49.4.72 `void QwtPlot::printLegendItem (QPainter * painter, const QWidget * w, const QRect & rect) const` [protected, virtual]

Print the legend item into a given rectangle.

Parameters:

painter Painter

w Widget representing a legend item

rect Bounding rectangle

6.49.4.73 void QwtPlot::printTitle (QPainter * *painter*, const QRect & *rect*) const [protected, virtual]

Print the title into a given rectangle.

Parameters:

painter Painter
rect Bounding rectangle

6.49.4.74 void QwtPlot::printScale (QPainter * *painter*, int *axisId*, int *startDist*, int *endDist*, int *baseDist*, const QRect & *rect*) const [protected, virtual]

Paint a scale into a given rectangle. Paint the scale into a given rectangle.

Parameters:

painter Painter
axisId Axis
startDist Start border distance
endDist End border distance
baseDist Base distance
rect Bounding rectangle

6.49.4.75 void QwtPlot::printCanvas (QPainter * *painter*, const QRect & *boundingRect*, const QRect & *canvasRect*, const QwtScaleMap *map*[axisCnt], const QwtPlotPrintFilter & *pfilter*) const [protected, virtual]

Print the canvas into a given rectangle.

Parameters:

painter Painter
map Maps mapping between plot and paint device coordinates
boundingRect Bounding rectangle
canvasRect Canvas rectangle
pfilter Print filter

See also:

[QwtPlotPrintFilter](#)

6.49.4.76 void QwtPlot::printLegend (QPainter * *painter*, const QRect & *rect*) const [protected, virtual]

Print the legend into a given rectangle.

Parameters:

painter Painter
rect Bounding rectangle

6.50 QwtPlotCanvas Class Reference

Canvas of a [QwtPlot](#).

```
#include <qwt_plot_canvas.h>
```

Public Types

- enum [PaintAttribute](#) {
 PaintCached = 1,
 PaintPacked = 2,
 PaintFiltered = 1,
 ClipPolygons = 2,
 PaintUsingTextFont = 1,
 PaintUsingTextColor = 2,
 PaintBackground = 4 }
- enum [FocusIndicator](#) {
 NoFocusIndicator,
 CanvasFocusIndicator,
 ItemFocusIndicator }

Public Member Functions

- [QwtPlotCanvas](#) ([QwtPlot](#) *)
- virtual [~QwtPlotCanvas](#) ()
- [QwtPlot](#) * [plot](#) ()
- const [QwtPlot](#) * [plot](#) () const
- void [setFocusIndicator](#) ([FocusIndicator](#))
- [FocusIndicator](#) [focusIndicator](#) () const
- void [setPaintAttribute](#) ([PaintAttribute](#), bool on=true)
- bool [testPaintAttribute](#) ([PaintAttribute](#)) const
- [QPixmap](#) * [paintCache](#) ()
- const [QPixmap](#) * [paintCache](#) () const
- void [invalidatePaintCache](#) ()
- void [replot](#) ()

Protected Member Functions

- virtual void [hideEvent](#) ([QHideEvent](#) *)
- virtual void [paintEvent](#) ([QPaintEvent](#) *)
- virtual void [drawContents](#) ([QPainter](#) *)
- virtual void [drawFocusIndicator](#) ([QPainter](#) *)
- void [drawCanvas](#) ([QPainter](#) *painter=NULL)

6.50.1 Detailed Description

Canvas of a [QwtPlot](#).

See also:

[QwtPlot](#)

6.50.2 Member Enumeration Documentation

6.50.2.1 enum [QwtPlotCanvas::PaintAttribute](#)

Paint attributes.

- [PaintCached](#)
Paint double buffered and reuse the content of the pixmap buffer for some spontaneous repaints that happen when a plot gets unhidden, deiconified or changes the focus. Disabling the cache will improve the performance for incremental paints (using [QwtPlotCurve::draw](#)).
- [PaintPacked](#)
Suppress system background repaints and paint it together with the canvas contents. Painting packed might avoid flickering for expensive repaints, when there is a notable gap between painting the background and the plot contents.

The default setting enables [PaintCached](#) and [PaintPacked](#)

See also:

[setPaintAttribute\(\)](#), [testPaintAttribute\(\)](#), [paintCache\(\)](#)

6.50.2.2 enum [QwtPlotCanvas::FocusIndicator](#)

Focus indicator.

- [NoFocusIndicator](#)
Don't paint a focus indicator
- [CanvasFocusIndicator](#)
The focus is related to the complete canvas. Paint the focus indicator using [paintFocus\(\)](#)
- [ItemFocusIndicator](#)
The focus is related to an item (curve, point, ...) on the canvas. It is up to the application to display a focus indication using f.e. highlighting.

See also:

[setFocusIndicator\(\)](#), [focusIndicator\(\)](#), [paintFocus\(\)](#)

6.50.3 Constructor & Destructor Documentation

6.50.3.1 [QwtPlotCanvas::QwtPlotCanvas \(QwtPlot *\)](#) [explicit]

Sets a cross cursor, enables [QwtPlotCanvas::PaintCached](#).

6.50.3.2 `QwtPlotCanvas::~~QwtPlotCanvas ()` [virtual]

Destructor.

6.50.4 Member Function Documentation**6.50.4.1** `QwtPlot * QwtPlotCanvas::plot ()`

Return parent plot widget.

6.50.4.2 `const QwtPlot * QwtPlotCanvas::plot () const`

Return parent plot widget.

6.50.4.3 `void QwtPlotCanvas::setFocusIndicator (FocusIndicator focusIndicator)`

Set the focus indicator

See also:

[FocusIndicator](#), [focusIndicator\(\)](#)

6.50.4.4 `QwtPlotCanvas::FocusIndicator QwtPlotCanvas::focusIndicator () const`

Returns:

Focus indicator

See also:

[FocusIndicator](#), [setFocusIndicator\(\)](#)

6.50.4.5 `void QwtPlotCanvas::setPaintAttribute (PaintAttribute attribute, bool on = true)`

Changing the paint attributes.

Parameters:

attribute Paint attribute

on On/Off

The default setting enables PaintCached and PaintPacked

See also:

[testPaintAttribute\(\)](#), [drawCanvas\(\)](#), [drawContents\(\)](#), [paintCache\(\)](#)

6.50.4.6 `bool QwtPlotCanvas::testPaintAttribute (PaintAttribute attribute) const`

Test whether a paint attribute is enabled

Parameters:

attribute Paint attribute

Returns:

true if the attribute is enabled

See also:

[setPaintAttribute\(\)](#)

6.50.4.7 `QPixmap * QwtPlotCanvas::paintCache ()`

Return the paint cache, might be null.

6.50.4.8 `const QPixmap * QwtPlotCanvas::paintCache () const`

Return the paint cache, might be null.

6.50.4.9 `void QwtPlotCanvas::invalidatePaintCache ()`

Invalidate the internal paint cache.

6.50.4.10 `void QwtPlotCanvas::replot ()`

Invalidate the paint cache and repaint the canvas

See also:

[invalidatePaintCache\(\)](#)

6.50.4.11 `void QwtPlotCanvas::hideEvent (QHideEvent * event) [protected, virtual]`

Hide event

Parameters:

event Hide event

6.50.4.12 `void QwtPlotCanvas::paintEvent (QPaintEvent * event) [protected, virtual]`

Paint event

Parameters:

event Paint event

6.50.4.13 void QwtPlotCanvas::drawContents (QPainter * *painter*) [protected, virtual]

Redraw the canvas, and focus rect

Parameters:

painter Painter

6.50.4.14 void QwtPlotCanvas::drawFocusIndicator (QPainter * *painter*) [protected, virtual]

Draw the focus indication

Parameters:

painter Painter

6.50.4.15 void QwtPlotCanvas::drawCanvas (QPainter * *painter* = NULL) [protected]

Draw the the canvas

Paints all plot items to the contentsRect(), using [QwtPlot::drawCanvas](#) and updates the paint cache.

Parameters:

painter Painter

See also:


[QwtPlot::drawCanvas\(\)](#), [setPaintAttributes\(\)](#), [testPaintAttributes\(\)](#)

6.51 QwtPlotCurve Class Reference

A plot item, that represents a series of points.

```
#include <qwt_plot_curve.h>
```

Inheritance diagram for QwtPlotCurve:

**Public Types**

- enum [CurveType](#) {
 Yfx,
 Xfy }

- enum [CurveStyle](#) {
NoCurve,
Lines,
Sticks,
Steps,
Dots,
UserCurve = 100 }
- enum [CurveAttribute](#) {
Inverted = 1,
Fitted = 2 }
- enum [PaintAttribute](#) {
PaintCached = 1,
PaintPacked = 2,
PaintFiltered = 1,
ClipPolygons = 2,
PaintUsingTextFont = 1,
PaintUsingTextColor = 2,
PaintBackground = 4 }

Public Member Functions

- [QwtPlotCurve](#) ()
- [QwtPlotCurve](#) (const [QwtText](#) &title)
- [QwtPlotCurve](#) (const [QString](#) &title)
- virtual [~QwtPlotCurve](#) ()
- virtual int [rtti](#) () const
- void [setCurveType](#) ([CurveType](#))
- [CurveType](#) [curveType](#) () const
- void [setPaintAttribute](#) ([PaintAttribute](#), bool on=true)
- bool [testPaintAttribute](#) ([PaintAttribute](#)) const
- void [setRawData](#) (const double *x, const double *y, int size)
- void [setData](#) (const double *xDATA, const double *yDATA, int size)
- void [setData](#) (const [QwtArray](#)< double > &xDATA, const [QwtArray](#)< double > &yDATA)
- void [setData](#) (const [QPolygonF](#) &data)
- void [setData](#) (const [QwtData](#) &data)
- int [closestPoint](#) (const [QPoint](#) &pos, double *dist=NULL) const
- [QwtData](#) & [data](#) ()
- const [QwtData](#) & [data](#) () const
- int [dataSize](#) () const
- double [x](#) (int i) const
- double [y](#) (int i) const
- virtual [QwtDoubleRect](#) [boundingRect](#) () const
- double [minXValue](#) () const
- double [maxXValue](#) () const
- double [minYValue](#) () const
- double [maxYValue](#) () const

- void `setCurveAttribute` (`CurveAttribute`, bool on=true)
- bool `testCurveAttribute` (`CurveAttribute`) const
- void `setPen` (const `QPen` &)
- const `QPen` & `pen` () const
- void `setBrush` (const `QBrush` &)
- const `QBrush` & `brush` () const
- void `setBaseline` (double ref)
- double `baseline` () const
- void `setStyle` (`CurveStyle` style)
- `CurveStyle` `style` () const
- void `setSymbol` (const `QwtSymbol` &s)
- const `QwtSymbol` & `symbol` () const
- void `setCurveFitter` (`QwtCurveFitter` *)
- `QwtCurveFitter` * `curveFitter` () const
- virtual void `draw` (`QPainter` *p, const `QwtScaleMap` &xMap, const `QwtScaleMap` &yMap, const `QRect` &) const
- virtual void `draw` (`QPainter` *p, const `QwtScaleMap` &xMap, const `QwtScaleMap` &yMap, int from, int to) const
- void `draw` (int from, int to) const
- virtual void `updateLegend` (`QwtLegend` *) const

Protected Member Functions

- void `init` ()
- virtual void `drawCurve` (`QPainter` *p, int style, const `QwtScaleMap` &xMap, const `QwtScaleMap` &yMap, int from, int to) const
- virtual void `drawSymbols` (`QPainter` *p, const `QwtSymbol` &, const `QwtScaleMap` &xMap, const `QwtScaleMap` &yMap, int from, int to) const
- void `drawLines` (`QPainter` *p, const `QwtScaleMap` &xMap, const `QwtScaleMap` &yMap, int from, int to) const
- void `drawSticks` (`QPainter` *p, const `QwtScaleMap` &xMap, const `QwtScaleMap` &yMap, int from, int to) const
- void `drawDots` (`QPainter` *p, const `QwtScaleMap` &xMap, const `QwtScaleMap` &yMap, int from, int to) const
- void `drawSteps` (`QPainter` *p, const `QwtScaleMap` &xMap, const `QwtScaleMap` &yMap, int from, int to) const
- void `fillCurve` (`QPainter` *, const `QwtScaleMap` &, const `QwtScaleMap` &, `QwtPolygon` &) const
- void `closePolyline` (const `QwtScaleMap` &, const `QwtScaleMap` &, `QwtPolygon` &) const

6.51.1 Detailed Description

A plot item, that represents a series of points.

A curve is the representation of a series of points in the x-y plane. It supports different display styles, interpolation (f.e. spline) and symbols.

Usage

- Assign curve properties** When a curve is created, it is configured to draw black solid lines with in Lines style and no symbols. You can change this by calling `setPen()`, `setStyle()` and `setSymbol()`.

b) **Connect/Assign data.** `QwtPlotCurve` gets its points using a `QwtData` object offering a bridge to the real storage of the points (like `QAbstractItemModel`). There are several convenience classes derived from `QwtData`, that also store the points inside (like `QStandardItemModel`). `QwtPlotCurve` also offers a couple of variations of `setData()`, that build `QwtData` objects from arrays internally.

c) **Attach the curve to a plot** See `QwtPlotItem::attach()`

Example:

see examples/bode

See also:

[QwtPlot](#), [QwtData](#), [QwtSymbol](#), [QwtScaleMap](#)

6.51.2 Member Enumeration Documentation

6.51.2.1 enum `QwtPlotCurve::CurveType`

Curve type.

- `Yfx`
Draws y as a function of x (the default). The baseline is interpreted as a horizontal line with y = [baseline\(\)](#).
- `Xfy`
Draws x as a function of y. The baseline is interpreted as a vertical line with x = [baseline\(\)](#).

The baseline is used for aligning the sticks, or filling the curve with a brush.

See also:

[setCurveType\(\)](#), [curveType\(\)](#), [baseline\(\)](#) [brush\(\)](#)

6.51.2.2 enum `QwtPlotCurve::CurveStyle`

Curve styles.

- `NoCurve`
Don't draw a curve. Note: This doesn't affect the symbols.
- `Lines`
Connect the points with straight lines. The lines might be interpolated depending on the 'Fitted' attribute. Curve fitting can be configured using [setCurveFitter\(\)](#).
- `Sticks`
Draw vertical(`Yfx`) or horizontal(`Xfy`) sticks from a baseline which is defined by [setBaseline\(\)](#).
- `Steps`
Connect the points with a step function. The step function is drawn from the left to the right or vice versa, depending on the 'Inverted' attribute.

- Dots
Draw dots at the locations of the data points. Note: This is different from a dotted line (see [setPen\(\)](#)), and faster as a curve in NoStyle style and a symbol painting a point.
- UserCurve
Styles \geq UserCurve are reserved for derived classes of [QwtPlotCurve](#) that overload [drawCurve\(\)](#) with additional application specific curve types.

See also:

[setStyle\(\)](#), [style\(\)](#)

6.51.2.3 enum [QwtPlotCurve::CurveAttribute](#)

Attribute for drawing the curve

- Fitted (in combination with the Lines [QwtPlotCurve::CurveStyle](#) only)
A [QwtCurveFitter](#) tries to interpolate/smooth the curve, before it is painted. Note that curve fitting requires temporary memory for calculating coefficients and additional points. If painting in Fitted mode is slow it might be better to fit the points, before they are passed to [QwtPlotCurve](#).
- Inverted
For Steps only. Draws a step function from the right to the left.

See also:

[setCurveAttribute\(\)](#), [testCurveAttribute\(\)](#), [curveFitter\(\)](#)

6.51.2.4 enum [QwtPlotCurve::PaintAttribute](#)

Attributes to modify the drawing algorithm.

- PaintFiltered
Tries to reduce the data that has to be painted, by sorting out duplicates, or paintings outside the visible area. Might have a notable impact on curves with many close points. Only a couple of very basic filtering algos are implemented.
- ClipPolygons
Clip polygons before painting them. In situations, where points are far outside the visible area (f.e when zooming deep) this might be a substantial improvement for the painting performance (especially on Windows).

The default is, that no paint attributes are enabled.

See also:

[setPaintAttribute\(\)](#), [testPaintAttribute\(\)](#)

6.51.3 Constructor & Destructor Documentation

6.51.3.1 [QwtPlotCurve::QwtPlotCurve \(\)](#) [explicit]

Constructor.

6.51.3.2 `QwtPlotCurve::QwtPlotCurve (const QwtText & title)` [explicit]

Constructor

Parameters:

title Title of the curve

6.51.3.3 `QwtPlotCurve::QwtPlotCurve (const QString & title)` [explicit]

Constructor

Parameters:

title Title of the curve

6.51.3.4 `QwtPlotCurve::~QwtPlotCurve ()` [virtual]

Destructor.

6.51.4 Member Function Documentation**6.51.4.1** `int QwtPlotCurve::rtti () const` [virtual]**Returns:**

`QwtPlotItem::Rtti_PlotCurve`

Reimplemented from [QwtPlotItem](#).

6.51.4.2 `void QwtPlotCurve::setCurveType (CurveType curveType)`

Assign the curve type

Parameters:

curveType Yfx or Xfy

See also:

[CurveType](#), [curveType\(\)](#)

6.51.4.3 `QwtPlotCurve::CurveType QwtPlotCurve::curveType () const`

Return the curve type

See also:

[CurveType](#), [setCurveType\(\)](#)

6.51.4.4 void QwtPlotCurve::setPaintAttribute (PaintAttribute attribute, bool on = true)

Specify an attribute how to draw the curve

Parameters:

attribute Paint attribute

on On/Off /sa PaintAttribute, [testPaintAttribute\(\)](#)

6.51.4.5 bool QwtPlotCurve::testPaintAttribute (PaintAttribute attribute) const

Return the current paint attributes.

See also:

[PaintAttribute](#), [setPaintAttribute\(\)](#)

6.51.4.6 void QwtPlotCurve::setRawData (const double * xData, const double * yData, int size)

Initialize the data by pointing to memory blocks which are not managed by [QwtPlotCurve](#).

`setRawData` is provided for efficiency. It is important to keep the pointers during the lifetime of the underlying [QwtCPointerData](#) class.

Parameters:

xData pointer to x data

yData pointer to y data

size size of x and y

Note:

Internally the data is stored in a [QwtCPointerData](#) object

6.51.4.7 void QwtPlotCurve::setData (const double * xData, const double * yData, int size)

Set data by copying x- and y-values from specified memory blocks. Contrary to `setCurveRawData()`, this function makes a 'deep copy' of the data.

Parameters:

xData Pointer to x values

yData Pointer to y values

size Size of xData and yData

Note:

Internally the data is stored in a [QwtArrayData](#) object

6.51.4.8 void QwtPlotCurve::setData (const QwtArray< double > & *xData*, const QwtArray< double > & *yData*)

Initialize data with x- and y-arrays (explicitly shared) (Builds an [QwtArrayData](#) object internally)

Parameters:

xData x data

yData y data

Note:

Internally the data is stored in a [QwtArrayData](#) object

6.51.4.9 void QwtPlotCurve::setData (const QPolygonF & *data*)

Initialize data with an array of points (explicitly shared).

Parameters:

data Data

Note:

Internally the data is stored in a [QwtPolygonFData](#) object

6.51.4.10 void QwtPlotCurve::setData (const QwtData & *data*)

Initialize data with a pointer to [QwtData](#).

Parameters:

data Data

See also:

[QwtData::copy\(\)](#)

6.51.4.11 int QwtPlotCurve::closestPoint (const QPoint & *pos*, double * *dist* = NULL) const

Find the closest curve point for a specific position

Parameters:

pos Position, where to look for the closest curve point

dist If *dist* != NULL, [closestPoint\(\)](#) returns the distance between the position and the closest curve point

Returns:

Index of the closest curve point, or -1 if none can be found (f.e when the curve has no points)

Note:

[closestPoint\(\)](#) implements a dumb algorithm, that iterates over all points

6.51.4.12 [QwtData](#) & `QwtPlotCurve::data ()` `[inline]`**Returns:**

the the curve data

6.51.4.13 `const` [QwtData](#) & `QwtPlotCurve::data () const` `[inline]`**Returns:**

the the curve data

6.51.4.14 `int` `QwtPlotCurve::dataSize () const`

Return the size of the data arrays

See also:

[setData\(\)](#)

6.51.4.15 `double` `QwtPlotCurve::x (int i) const` `[inline]`**Parameters:**

i index

Returns:

x-value at position *i*

6.51.4.16 `double` `QwtPlotCurve::y (int i) const` `[inline]`**Parameters:**

i index

Returns:

y-value at position *i*

6.51.4.17 [QwtDoubleRect](#) `QwtPlotCurve::boundingRect () const` `[virtual]`

Returns the bounding rectangle of the curve data. If there is no bounding rect, like for empty data the rectangle is invalid.

See also:

[QwtData::boundingRect\(\)](#), [QwtDoubleRect::isValid\(\)](#)

Reimplemented from [QwtPlotItem](#).

6.51.4.18 `double QwtPlotCurve::minXValue () const` [inline]
[boundingRect\(\).left\(\)](#)

6.51.4.19 `double QwtPlotCurve::maxXValue () const` [inline]
[boundingRect\(\).right\(\)](#)

6.51.4.20 `double QwtPlotCurve::minYValue () const` [inline]
[boundingRect\(\).top\(\)](#)

6.51.4.21 `double QwtPlotCurve::maxYValue () const` [inline]
[boundingRect\(\).bottom\(\)](#)

6.51.4.22 `void QwtPlotCurve::setCurveAttribute (CurveAttribute attribute, bool on = true)`

Specify an attribute for drawing the curve

Parameters:

attribute Curve attribute

on On/Off

/sa [CurveAttribute](#), [testCurveAttribute\(\)](#), [setCurveFitter\(\)](#)

6.51.4.23 `bool QwtPlotCurve::testCurveAttribute (CurveAttribute attribute) const`

Returns:

true, if attribute is enabled

See also:

[CurveAttribute](#), [setCurveAttribute\(\)](#)

6.51.4.24 `void QwtPlotCurve::setPen (const QPen & pen)`

Assign a pen

The width of non cosmetic pens is scaled according to the resolution of the paint device.

Parameters:

pen New pen

See also:

[pen\(\)](#), [brush\(\)](#), [QwtPainter::scaledPen\(\)](#)

6.51.4.25 const QPen & QwtPlotCurve::pen () const

Return the pen used to draw the lines.

See also:

[setPen\(\)](#), [brush\(\)](#)

6.51.4.26 void QwtPlotCurve::setBrush (const QBrush & brush)

Assign a brush.

In case of `brush.style() != QBrush::NoBrush` and `style() != QwtPlotCurve::Sticks` the area between the curve and the baseline will be filled.

In case `!brush.color().isValid()` the area will be filled by `pen.color()`. The fill algorithm simply connects the first and the last curve point to the baseline. So the curve data has to be sorted (ascending or descending).

Parameters:

brush New brush

See also:

[brush\(\)](#), [setBaseline\(\)](#), [baseline\(\)](#)

6.51.4.27 const QBrush & QwtPlotCurve::brush () const

Return the brush used to fill the area between lines and the baseline.

See also:

[setBrush\(\)](#), [setBaseline\(\)](#), [baseline\(\)](#)

6.51.4.28 void QwtPlotCurve::setBaseline (double reference)

Set the value of the baseline.

The baseline is needed for filling the curve with a brush or the Sticks drawing style. The default value is 0.0. The interpretation of the baseline depends on the CurveType. With `QwtPlotCurve::Yfx`, the baseline is interpreted as a horizontal line at `y = baseline()`, with `QwtPlotCurve::Yfy`, it is interpreted as a vertical line at `x = baseline()`.

Parameters:

reference baseline

See also:

[baseline\(\)](#), [setBrush\(\)](#), [setStyle\(\)](#), [setCurveType\(\)](#)

6.51.4.29 double QwtPlotCurve::baseline () const

Return the value of the baseline

See also:

[setBaseline\(\)](#)

6.51.4.30 void QwtPlotCurve::setStyle (CurveStyle style)

Set the curve's drawing style

Parameters:

style Curve style

See also:

[CurveStyle](#), [style\(\)](#)

6.51.4.31 QwtPlotCurve::CurveStyle QwtPlotCurve::style () const

Return the current style

See also:

[CurveStyle](#), [setStyle\(\)](#)

6.51.4.32 void QwtPlotCurve::setSymbol (const QwtSymbol & symbol)

Assign a symbol.

Parameters:

symbol Symbol

See also:

[symbol\(\)](#)

6.51.4.33 const QwtSymbol & QwtPlotCurve::symbol () const

Return the current symbol.

See also:

[setSymbol\(\)](#)

6.51.4.34 void QwtPlotCurve::setCurveFitter (QwtCurveFitter * curveFitter)

Assign a curve fitter setCurveFitter(NULL) disables curve fitting.

Parameters:

curveFitter Curve fitter

6.51.4.35 QwtCurveFitter * QwtPlotCurve::curveFitter () const

Get the curve fitter. If curve fitting is disabled NULL is returned.

Returns:

Curve fitter

6.51.4.36 void QwtPlotCurve::draw (QPainter * *painter*, const QwtScaleMap & *xMap*, const QwtScaleMap & *yMap*, const QRect &) const [virtual]

Draw the complete curve.

Parameters:

painter Painter

xMap Maps x-values into pixel coordinates.

yMap Maps y-values into pixel coordinates.

See also:

[drawCurve\(\)](#), [drawSymbols\(\)](#)

Implements [QwtPlotItem](#).

6.51.4.37 void QwtPlotCurve::draw (QPainter * *painter*, const QwtScaleMap & *xMap*, const QwtScaleMap & *yMap*, int *from*, int *to*) const [virtual]

Draw an interval of the curve.

Parameters:

painter Painter

xMap maps x-values into pixel coordinates.

yMap maps y-values into pixel coordinates.

from index of the first point to be painted

to index of the last point to be painted. If $to < 0$ the curve will be painted to its last point.

See also:

[drawCurve\(\)](#), [drawSymbols\(\)](#),

6.51.4.38 void QwtPlotCurve::draw (int *from*, int *to*) const

Draw a set of points of a curve.

When observing an measurement while it is running, new points have to be added to an existing curve. drawCurve can be used to display them avoiding a complete redraw of the canvas.

Setting `plot()->canvas()->setAttribute(Qt::WA_PaintOutsidePaintEvent, true)`; will result in faster painting, if the paint engine of the canvas widget supports this feature.

Parameters:

from Index of the first point to be painted

to Index of the last point to be painted. If $to < 0$ the curve will be painted to its last point.

See also:

[drawCurve\(\)](#), [drawSymbols\(\)](#)

6.51.4.39 void QwtPlotCurve::updateLegend (QwtLegend *) const [virtual]

Update the widget that represents the curve on the legend.

Reimplemented from [QwtPlotItem](#).

6.51.4.40 void QwtPlotCurve::init () [protected]

Initialize data members.

6.51.4.41 void QwtPlotCurve::drawCurve (QPainter * painter, int style, const QwtScaleMap & xMap, const QwtScaleMap & yMap, int from, int to) const [protected, virtual]

Draw the line part (without symbols) of a curve interval.

Parameters:

painter Painter

style curve style, see [QwtPlotCurve::CurveStyle](#)

xMap x map

yMap y map

from index of the first point to be painted

to index of the last point to be painted

See also:

[draw\(\)](#), [drawDots\(\)](#), [drawLines\(\)](#), [drawSteps\(\)](#), [drawSticks\(\)](#)

6.51.4.42 void QwtPlotCurve::drawSymbols (QPainter * painter, const QwtSymbol & symbol, const QwtScaleMap & xMap, const QwtScaleMap & yMap, int from, int to) const [protected, virtual]

Draw symbols.

Parameters:

painter Painter

symbol Curve symbol

xMap x map

yMap y map

from index of the first point to be painted

to index of the last point to be painted

See also:

[setSymbol\(\)](#), [draw\(\)](#), [drawCurve\(\)](#)

6.51.4.43 void QwtPlotCurve::drawLines (QPainter * *painter*, const QwtScaleMap & *xMap*, const QwtScaleMap & *yMap*, int *from*, int *to*) const [protected]

Draw lines.

If the CurveAttribute Fitted is enabled a QwtCurveFitter tries to interpolate/smooth the curve, before it is painted.

Parameters:

painter Painter
xMap x map
yMap y map
from index of the first point to be painted
to index of the last point to be painted

See also:

[setCurveAttribute\(\)](#), [setCurveFitter\(\)](#), [draw\(\)](#), [drawLines\(\)](#), [drawDots\(\)](#), [drawSteps\(\)](#), [drawSticks\(\)](#)

6.51.4.44 void QwtPlotCurve::drawSticks (QPainter * *painter*, const QwtScaleMap & *xMap*, const QwtScaleMap & *yMap*, int *from*, int *to*) const [protected]

Draw sticks

Parameters:

painter Painter
xMap x map
yMap y map
from index of the first point to be painted
to index of the last point to be painted

See also:

[draw\(\)](#), [drawCurve\(\)](#), [drawDots\(\)](#), [drawLines\(\)](#), [drawSteps\(\)](#)

6.51.4.45 void QwtPlotCurve::drawDots (QPainter * *painter*, const QwtScaleMap & *xMap*, const QwtScaleMap & *yMap*, int *from*, int *to*) const [protected]

Draw dots

Parameters:

painter Painter
xMap x map
yMap y map
from index of the first point to be painted
to index of the last point to be painted

See also:

[draw\(\)](#), [drawCurve\(\)](#), [drawSticks\(\)](#), [drawLines\(\)](#), [drawSteps\(\)](#)

6.51.4.46 void QwtPlotCurve::drawSteps (QPainter * *painter*, const QwtScaleMap & *xMap*, const QwtScaleMap & *yMap*, int *from*, int *to*) const [protected]

Draw step function

The direction of the steps depends on Inverted attribute.

Parameters:

painter Painter

xMap x map

yMap y map

from index of the first point to be painted

to index of the last point to be painted

See also:

[CurveAttribute](#), [setCurveAttribute\(\)](#), [draw\(\)](#), [drawCurve\(\)](#), [drawDots\(\)](#), [drawLines\(\)](#), [drawSticks\(\)](#)

6.51.4.47 void QwtPlotCurve::fillCurve (QPainter * *painter*, const QwtScaleMap & *xMap*, const QwtScaleMap & *yMap*, QwtPolygon & *pa*) const [protected]

Fill the area between the curve and the baseline with the curve brush

Parameters:

painter Painter

xMap x map

yMap y map

pa Polygon

See also:

[setBrush\(\)](#), [setBaseline\(\)](#), [setCurveType\(\)](#)

6.51.4.48 void QwtPlotCurve::closePolyline (const QwtScaleMap & *xMap*, const QwtScaleMap & *yMap*, QwtPolygon & *pa*) const [protected]

Complete a polygon to be a closed polygon including the area between the original polygon and the baseline.

Parameters:

xMap X map

yMap Y map

pa Polygon to be completed

6.52 QwtPlotDict Class Reference

A dictionary for plot items.

```
#include <qwt_plot_dict.h>
```

Inheritance diagram for QwtPlotDict:



Public Member Functions

- [QwtPlotDict \(\)](#)
- [~QwtPlotDict \(\)](#)
- void [setAutoDelete](#) (bool)
- bool [autoDelete](#) () const
- const [QwtPlotItemList](#) & [itemList](#) () const
- void [detachItems](#) (int rtti=QwtPlotItem::Rtti_PlotItem, bool autoDelete=true)

Friends

- class [QwtPlotItem](#)

6.52.1 Detailed Description

A dictionary for plot items.

[QwtPlotDict](#) organizes plot items in increasing z-order. If [autoDelete\(\)](#) is enabled, all attached items will be deleted in the destructor of the dictionary.

See also:

[QwtPlotItem::attach\(\)](#), [QwtPlotItem::detach\(\)](#), [QwtPlotItem::z\(\)](#)

6.52.2 Constructor & Destructor Documentation

6.52.2.1 [QwtPlotDict::QwtPlotDict \(\)](#) [explicit]

Constructor

Auto deletion is enabled.

See also:

[setAutoDelete\(\)](#), [attachItem\(\)](#)

6.52.2.2 [QwtPlotDict::~~QwtPlotDict \(\)](#)

Destructor

If autoDelete is on, all attached items will be deleted

See also:

[setAutoDelete\(\)](#), [autoDelete\(\)](#), [attachItem\(\)](#)

6.52.3 Member Function Documentation

6.52.3.1 void QwtPlotDict::setAutoDelete (bool *autoDelete*)

En/Disable Auto deletion

If Auto deletion is on all attached plot items will be deleted in the destructor of [QwtPlotDict](#). The default value is on.

See also:

[autoDelete\(\)](#), [attachItem\(\)](#)

6.52.3.2 bool QwtPlotDict::autoDelete () const

Returns:

true if auto deletion is enabled

See also:

[setAutoDelete\(\)](#), [attachItem\(\)](#)

6.52.3.3 const QwtPlotItemList & QwtPlotDict::itemList () const

A QwtPlotItemList of all attached plot items.

Use caution when iterating these lists, as removing/detaching an item will invalidate the iterator. Instead you can place pointers to objects to be removed in a removal list, and traverse that list later.

Returns:

List of all attached plot items.

6.52.3.4 void QwtPlotDict::detachItems (int *rtti* = QwtPlotItem::Rtti_PlotItem, bool *autoDelete* = true)

Detach items from the dictionary

Parameters:

rtti In case of QwtPlotItem::Rtti_PlotItem detach all items otherwise only those items of the type *rtti*.


autoDelete If true, delete all detached items

6.53 QwtPlotGrid Class Reference

A class which draws a coordinate grid.

```
#include <qwt_plot_grid.h>
```

Inheritance diagram for QwtPlotGrid:



Public Member Functions

- [QwtPlotGrid \(\)](#)
- virtual [~QwtPlotGrid \(\)](#)
- virtual int [rtti \(\)](#) const
- void [enableX \(bool tf\)](#)
- bool [xEnabled \(\)](#) const
- void [enableY \(bool tf\)](#)
- bool [yEnabled \(\)](#) const
- void [enableXMin \(bool tf\)](#)
- bool [xMinEnabled \(\)](#) const
- void [enableYMin \(bool tf\)](#)
- bool [yMinEnabled \(\)](#) const
- void [setXDiv \(const QwtScaleDiv &sx\)](#)
- const [QwtScaleDiv & xScaleDiv \(\)](#) const
- void [setYDiv \(const QwtScaleDiv &sy\)](#)
- const [QwtScaleDiv & yScaleDiv \(\)](#) const
- void [setPen \(const QPen &p\)](#)
- void [setMajPen \(const QPen &p\)](#)
- const QPen & [majPen \(\)](#) const
- void [setMinPen \(const QPen &p\)](#)
- const QPen & [minPen \(\)](#) const
- virtual void [draw \(QPainter *p, const QwtScaleMap &xMap, const QwtScaleMap &yMap, const QRect &rect\)](#) const
- virtual void [updateScaleDiv \(const QwtScaleDiv &xMap, const QwtScaleDiv &yMap\)](#)

6.53.1 Detailed Description

A class which draws a coordinate grid.

The [QwtPlotGrid](#) class can be used to draw a coordinate grid. A coordinate grid consists of major and minor vertical and horizontal gridlines. The locations of the gridlines are determined by the X and Y scale divisions which can be assigned with [setXDiv\(\)](#) and [setYDiv\(\)](#). The [draw\(\)](#) member draws the grid within a bounding rectangle.

6.53.2 Constructor & Destructor Documentation

6.53.2.1 QwtPlotGrid::QwtPlotGrid () [explicit]

Enables major grid, disables minor grid.

6.53.2.2 QwtPlotGrid::~~QwtPlotGrid () [virtual]

Destructor.

6.53.3 Member Function Documentation

6.53.3.1 `int QwtPlotGrid::rtti () const` [virtual]

Returns:

QwtPlotItem::Rtti_PlotGrid

Reimplemented from [QwtPlotItem](#).

6.53.3.2 `void QwtPlotGrid::enableX (bool tf)`

Enable or disable vertical gridlines.

Parameters:

tf Enable (true) or disable

See also:

Minor gridlines can be enabled or disabled with [enableXMin\(\)](#)

6.53.3.3 `bool QwtPlotGrid::xEnabled () const`

Returns:

true if vertical gridlines are enabled

See also:

[enableX\(\)](#)

6.53.3.4 `void QwtPlotGrid::enableY (bool tf)`

Enable or disable horizontal gridlines.

Parameters:

tf Enable (true) or disable

See also:

Minor gridlines can be enabled or disabled with [enableYMin\(\)](#)

6.53.3.5 `bool QwtPlotGrid::yEnabled () const`

Returns:

true if horizontal gridlines are enabled

See also:

[enableY\(\)](#)

6.53.3.6 void QwtPlotGrid::enableXMin (bool *tf*)

Enable or disable minor vertical gridlines.

Parameters:

tf Enable (true) or disable

See also:

[enableX\(\)](#)

6.53.3.7 bool QwtPlotGrid::xMinEnabled () const**Returns:**

true if minor vertical gridlines are enabled

See also:

[enableXMin\(\)](#)

6.53.3.8 void QwtPlotGrid::enableYMin (bool *tf*)

Enable or disable minor horizontal gridlines.

Parameters:

tf Enable (true) or disable

See also:

[enableY\(\)](#)

6.53.3.9 bool QwtPlotGrid::yMinEnabled () const**Returns:**

true if minor horizontal gridlines are enabled

See also:

[enableYMin\(\)](#)

6.53.3.10 void QwtPlotGrid::setXDiv (const [QwtScaleDiv](#) & *scaleDiv*)

Assign an x axis scale division

Parameters:

scaleDiv Scale division

6.53.3.11 `const QwtScaleDiv & QwtPlotGrid::xScaleDiv () const`**Returns:**

the scale division of the x axis

6.53.3.12 `void QwtPlotGrid::setYDiv (const QwtScaleDiv & scaleDiv)`

Assign a y axis division

Parameters:

scaleDiv Scale division

6.53.3.13 `const QwtScaleDiv & QwtPlotGrid::yScaleDiv () const`**Returns:**

the scale division of the y axis

6.53.3.14 `void QwtPlotGrid::setPen (const QPen & pen)`

Assign a pen for both major and minor gridlines

The width of non cosmetic pens is scaled according to the resolution of the paint device.

Parameters:

pen Pen

See also:

[setMajPen\(\)](#), [setMinPen\(\)](#), [QwtPainter::scaledPen\(\)](#)

6.53.3.15 `void QwtPlotGrid::setMajPen (const QPen & pen)`

Assign a pen for the major gridlines

The width of non cosmetic pens is scaled according to the resolution of the paint device.

Parameters:

pen Pen

See also:

[majPen\(\)](#), [setMinPen\(\)](#), [setPen\(\)](#), [QwtPainter::scaledPen\(\)](#)

6.53.3.16 `const QPen & QwtPlotGrid::majPen () const`**Returns:**

the pen for the major gridlines

See also:

[setMajPen\(\)](#), [setMinPen\(\)](#), [setPen\(\)](#)

6.53.3.17 void QwtPlotGrid::setMinPen (const QPen & *pen*)

Assign a pen for the minor gridlines

The width of non cosmetic pens is scaled according to the resolution of the paint device.

Parameters:

pen Pen

See also:

[minPen\(\)](#), [setMajPen\(\)](#), [setPen\(\)](#), [QwtPainter::scaledPen\(\)](#)

6.53.3.18 const QPen & QwtPlotGrid::minPen () const**Returns:**

the pen for the minor gridlines

See also:

[setMinPen\(\)](#), [setMajPen\(\)](#), [setPen\(\)](#)

6.53.3.19 void QwtPlotGrid::draw (QPainter * *painter*, const QwtScaleMap & *xMap*, const QwtScaleMap & *yMap*, const QRect & *canvasRect*) const [virtual]

Draw the grid.

The grid is drawn into the bounding rectangle such that gridlines begin and end at the rectangle's borders. The X and Y maps are used to map the scale divisions into the drawing region screen.

Parameters:

painter Painter

xMap X axis map

yMap Y axis

canvasRect Contents rect of the plot canvas

Implements [QwtPlotItem](#).

6.53.3.20 void QwtPlotGrid::updateScaleDiv (const QwtScaleDiv & *xScaleDiv*, const QwtScaleDiv & *yScaleDiv*) [virtual]

Update the grid to changes of the axes scale division

Parameters:

xScaleDiv Scale division of the x-axis

yScaleDiv Scale division of the y-axis

See also:

[QwtPlot::updateAxes\(\)](#)


Reimplemented from [QwtPlotItem](#).

6.54 QwtPlotItem Class Reference

Base class for items on the plot canvas.

```
#include <qwt_plot_item.h>
```

Inheritance diagram for QwtPlotItem:



Public Types

- enum [RttiValues](#) {
Rtti_PlotItem = 0,
Rtti_PlotGrid,
Rtti_PlotScale,
Rtti_PlotMarker,
Rtti_PlotCurve,
Rtti_PlotHistogram,
Rtti_PlotSpectrogram,
Rtti_PlotSVG,
Rtti_PlotUserItem = 1000 }
- enum [ItemAttribute](#) {
Legend = 1,
AutoScale = 2 }
- enum [RenderHint](#) { **RenderAntialiased** = 1 }

Public Member Functions

- [QwtPlotItem](#) (const [QwtText](#) &title=[QwtText](#)())
- virtual [~QwtPlotItem](#) ()
- void [attach](#) ([QwtPlot](#) *plot)
- void [detach](#) ()
- [QwtPlot](#) * [plot](#) () const
- void [setTitle](#) (const [QString](#) &title)
- void [setTitle](#) (const [QwtText](#) &title)
- const [QwtText](#) & [title](#) () const
- virtual int [rtti](#) () const
- void [setItemAttribute](#) ([ItemAttribute](#), bool on=true)
- bool [testItemAttribute](#) ([ItemAttribute](#)) const
- void [setRenderHint](#) ([RenderHint](#), bool on=true)

- bool [testRenderHint](#) ([RenderHint](#)) const
- double [z](#) () const
- void [setZ](#) (double z)
- void [show](#) ()
- void [hide](#) ()
- virtual void [setVisible](#) (bool)
- bool [isVisible](#) () const
- void [setAxis](#) (int xAxis, int yAxis)
- void [setXAxis](#) (int axis)
- int [xAxis](#) () const
- void [setYAxis](#) (int axis)
- int [yAxis](#) () const
- virtual void [itemChanged](#) ()
- virtual void [draw](#) (QPainter *painter, const [QwtScaleMap](#) &xMap, const [QwtScaleMap](#) &yMap, const QRect &canvasRect) const=0
- virtual [QwtDoubleRect](#) [boundingRect](#) () const
- virtual void [updateLegend](#) ([QwtLegend](#) *) const
- virtual void [updateScaleDiv](#) (const [QwtScaleDiv](#) &, const [QwtScaleDiv](#) &)
- virtual QWidget * [legendItem](#) () const
- [QwtDoubleRect](#) [scaleRect](#) (const [QwtScaleMap](#) &, const [QwtScaleMap](#) &) const
- QRect [paintRect](#) (const [QwtScaleMap](#) &, const [QwtScaleMap](#) &) const
- QRect [transform](#) (const [QwtScaleMap](#) &, const [QwtScaleMap](#) &, const [QwtDoubleRect](#) &) const
- [QwtDoubleRect](#) [invTransform](#) (const [QwtScaleMap](#) &, const [QwtScaleMap](#) &, const QRect &) const

6.54.1 Detailed Description

Base class for items on the plot canvas.

A plot item is "something", that can be painted on the plot canvas, or only affects the scales of the plot widget. They can be categorized as:

- Representator

A "Representator" is an item that represents some sort of data on the plot canvas. The different representator classes are organized according to the characteristics of the data:

- [QwtPlotMarker](#) Represents a point or a horizontal/vertical coordinate
- [QwtPlotCurve](#) Represents a series of points
- [QwtPlotSpectrogram](#) ([QwtPlotRasterItem](#)) Represents raster data
- ...

- Decorators

A "Decorator" is an item, that displays additional information, that is not related to any data:

- [QwtPlotGrid](#)
- [QwtPlotScaleItem](#)
- [QwtPlotSvgItem](#)
- ...

Depending on the [QwtPlotItem::ItemAttribute](#) flags, an item is included into autoscaling or has an entry on the legend.

Before misusing the existing item classes it might be better to implement a new type of plot item (don't implement a watermark as spectrogram). Deriving a new type of [QwtPlotItem](#) primarily means to implement the `YourPlotItem::draw()` method.

See also:

The `cpuplot` example shows the implementation of additional [plot](#) items.

6.54.2 Member Enumeration Documentation

6.54.2.1 enum [QwtPlotItem::RttiValues](#)

Runtime type information.

`RttiValues` is used to cast plot items, without having to enable runtime type information of the compiler.

6.54.2.2 enum [QwtPlotItem::ItemAttribute](#)

Plot Item Attributes

- Legend
The item is represented on the legend.
- AutoScale
The [boundingRect\(\)](#) of the item is included in the autoscaling calculation.

See also:

[setItemAttribute\(\)](#), [testItemAttribute\(\)](#)

6.54.2.3 enum [QwtPlotItem::RenderHint](#)

Render hints.

6.54.3 Constructor & Destructor Documentation

6.54.3.1 [QwtPlotItem::QwtPlotItem \(const \[QwtText\]\(#\) & *title* = \[QwtText\]\(#\) \(\)\)](#) [explicit]

Constructor

Parameters:

title Title of the item

6.54.3.2 [QwtPlotItem::~~QwtPlotItem \(\)](#) [virtual]

Destroy the [QwtPlotItem](#).

6.54.4 Member Function Documentation

6.54.4.1 void QwtPlotItem::attach (QwtPlot * *plot*)

Attach the item to a plot.

This method will attach a [QwtPlotItem](#) to the [QwtPlot](#) argument. It will first detach the [QwtPlotItem](#) from any plot from a previous call to attach (if necessary). If a NULL argument is passed, it will detach from any [QwtPlot](#) it was attached to.

Parameters:

plot Plot widget

See also:

[QwtPlotItem::detach\(\)](#)

6.54.4.2 void QwtPlotItem::detach () [inline]

This method detaches a [QwtPlotItem](#) from any [QwtPlot](#) it has been associated with.

[detach\(\)](#) is equivalent to calling `attach(NULL)`

See also:

[attach\(QwtPlot* plot \)](#)

6.54.4.3 QwtPlot * QwtPlotItem::plot () const

Return attached plot.

6.54.4.4 void QwtPlotItem::setTitle (const QString & *title*)

Set a new title

Parameters:

title Title

See also:

[title\(\)](#)

6.54.4.5 void QwtPlotItem::setTitle (const QwtText & *title*)

Set a new title

Parameters:

title Title

See also:

[title\(\)](#)

6.54.4.6 `const QwtText & QwtPlotItem::title () const`

Returns:

Title of the item

See also:

[setTitle\(\)](#)

6.54.4.7 `int QwtPlotItem::rtti () const` [virtual]

Return rtti for the specific class represented. [QwtPlotItem](#) is simply a virtual interface class, and base classes will implement this method with specific rtti values so a user can differentiate them.

The rtti value is useful for environments, where the runtime type information is disabled and it is not possible to do a `dynamic_cast<...>`.

Returns:

rtti value

See also:

[RttiValues](#)

Reimplemented in [QwtPlotCurve](#), [QwtPlotGrid](#), [QwtPlotMarker](#), [QwtPlotScaleItem](#), [QwtPlotSpectrogram](#), and [QwtPlotSvgItem](#).

6.54.4.8 `void QwtPlotItem::setItemAttribute (ItemAttribute attribute, bool on = true)`

Toggle an item attribute

Parameters:

attribute Attribute type

on true/false

See also:

[testItemAttribute\(\)](#), [ItemAttribute](#)

6.54.4.9 `bool QwtPlotItem::testItemAttribute (ItemAttribute attribute) const`

Test an item attribute

Parameters:

attribute Attribute type

Returns:

true/false

See also:

[setItemAttribute\(\)](#), [ItemAttribute](#)

6.54.4.10 void QwtPlotItem::setRenderHint (RenderHint hint, bool on = true)

Toggle an render hint

Parameters:

hint Render hint

on true/false

See also:

[testRenderHint\(\)](#), [RenderHint](#)

6.54.4.11 bool QwtPlotItem::testRenderHint (RenderHint hint) const

Test a render hint

Parameters:

hint Render hint

Returns:

true/false

See also:

[setRenderHint\(\)](#), [RenderHint](#)

6.54.4.12 double QwtPlotItem::z () const

Plot items are painted in increasing z-order.

Returns:

[setZ\(\)](#), [QwtPlotDict::itemList\(\)](#)

6.54.4.13 void QwtPlotItem::setZ (double z)

Set the z value.

Plot items are painted in increasing z-order.

Parameters:

z Z-value

See also:

[z\(\)](#), [QwtPlotDict::itemList\(\)](#)

6.54.4.14 void QwtPlotItem::show ()

Show the item.

6.54.4.15 void QwtPlotItem::hide ()

Hide the item.

6.54.4.16 void QwtPlotItem::setVisible (bool *on*) [virtual]

Show/Hide the item

Parameters:

on Show if true, otherwise hide

See also:

[isVisible\(\)](#), [show\(\)](#), [hide\(\)](#)

6.54.4.17 bool QwtPlotItem::isVisible () const**Returns:**

true if visible

See also:

[setVisible\(\)](#), [show\(\)](#), [hide\(\)](#)

6.54.4.18 void QwtPlotItem::setAxis (int *xAxis*, int *yAxis*)

Set X and Y axis

The item will painted according to the coordinates its Axes.

Parameters:

xAxis X Axis

yAxis Y Axis

See also:

[setXAxis\(\)](#), [setYAxis\(\)](#), [xAxis\(\)](#), [yAxis\(\)](#)

6.54.4.19 void QwtPlotItem::setXAxis (int *axis*)

Set the X axis

The item will painted according to the coordinates its Axes.

Parameters:

axis X Axis

See also:

[setAxis\(\)](#), [setYAxis\(\)](#), [xAxis\(\)](#)

6.54.4.20 `int QwtPlotItem::xAxis () const`

Return xAxis.

6.54.4.21 `void QwtPlotItem::setYAxis (int axis)`

Set the Y axis

The item will painted according to the coordinates its Axes.

Parameters:

axis Y Axis

See also:

[setAxis\(\)](#), [setXAxis\(\)](#), [yAxis\(\)](#)

6.54.4.22 `int QwtPlotItem::yAxis () const`

Return yAxis.

6.54.4.23 `void QwtPlotItem::itemChanged () [virtual]`

Update the legend and call [QwtPlot::autoRefresh](#) for the parent plot.

See also:

[updateLegend\(\)](#)

6.54.4.24 `virtual void QwtPlotItem::draw (QPainter * painter, const QwtScaleMap & xMap, const QwtScaleMap & yMap, const QRect & canvasRect) const [pure virtual]`

Draw the item.

Parameters:

painter Painter

xMap Maps x-values into pixel coordinates.

yMap Maps y-values into pixel coordinates.

canvasRect Contents rect of the canvas in painter coordinates

Implemented in [QwtPlotCurve](#), [QwtPlotGrid](#), [QwtPlotMarker](#), [QwtPlotRasterItem](#), [QwtPlotScaleItem](#), [QwtPlotSpectrogram](#), and [QwtPlotSvgItem](#).

6.54.4.25 `QwtDoubleRect QwtPlotItem::boundingRect () const [virtual]`**Returns:**

An invalid bounding rect: `QwtDoubleRect(1.0, 1.0, -2.0, -2.0)`

Reimplemented in [QwtPlotCurve](#), [QwtPlotMarker](#), [QwtPlotSpectrogram](#), and [QwtPlotSvgItem](#).

6.54.4.26 void QwtPlotItem::updateLegend (QwtLegend * legend) const [virtual]

Update the widget that represents the item on the legend.

[updateLegend\(\)](#) is called from [itemChanged\(\)](#) to adopt the widget representing the item on the legend to its new configuration.

The default implementation is made for [QwtPlotCurve](#) and updates a [QwtLegendItem\(\)](#), but an item could be represented by any type of widget, by overloading [legendItem\(\)](#) and [updateLegend\(\)](#).

Parameters:

legend Legend

See also:

[legendItem\(\)](#), [itemChanged\(\)](#), [QwtLegend\(\)](#)

Implements [QwtLegendItemManager](#).

Reimplemented in [QwtPlotCurve](#).

6.54.4.27 void QwtPlotItem::updateScaleDiv (const QwtScaleDiv &, const QwtScaleDiv &) [virtual]

Update the item to changes of the axes scale division.

Update the item, when the axes of plot have changed. The default implementation does nothing, but items that depend on the scale division (like [QwtPlotGrid\(\)](#)) have to reimplement [updateScaleDiv\(\)](#)

Parameters:

xScaleDiv Scale division of the x-axis

yScaleDiv Scale division of the y-axis

See also:

[QwtPlot::updateAxes\(\)](#)

Reimplemented in [QwtPlotGrid](#), and [QwtPlotScaleItem](#).

6.54.4.28 QWidget * QwtPlotItem::legendItem () const [virtual]

Allocate the widget that represents the item on the legend.

The default implementation is made for [QwtPlotCurve](#) and returns a [QwtLegendItem\(\)](#), but an item could be represented by any type of widget, by overloading [legendItem\(\)](#) and [updateLegend\(\)](#).

Returns:

[QwtLegendItem\(\)](#)

See also:

[updateLegend\(\)](#) [QwtLegend\(\)](#)

Implements [QwtLegendItemManager](#).

6.54.4.29 [QwtDoubleRect](#) `QwtPlotItem::scaleRect (const QwtScaleMap & xMap, const QwtScaleMap & yMap) const`

Calculate the bounding scale rect of 2 maps.

Parameters:

xMap X map

yMap X map

Returns:

Bounding rect of the scale maps

6.54.4.30 `QRect` `QwtPlotItem::paintRect (const QwtScaleMap & xMap, const QwtScaleMap & yMap) const`

Calculate the bounding paint rect of 2 maps.

Parameters:

xMap X map

yMap X map

Returns:

Bounding rect of the scale maps

6.54.4.31 `QRect` `QwtPlotItem::transform (const QwtScaleMap & xMap, const QwtScaleMap & yMap, const QwtDoubleRect & rect) const`

Transform a rectangle

Parameters:

xMap X map

yMap Y map

rect Rectangle in scale coordinates

Returns:

Rectangle in paint coordinates

See also:

[invTransform\(\)](#)

6.54.4.32 [QwtDoubleRect](#) `QwtPlotItem::invTransform (const QwtScaleMap & xMap, const QwtScaleMap & yMap, const QRect & rect) const`

Transform a rectangle from paint to scale coordinates

Parameters:

xMap X map

yMap Y map

rect Rectangle in paint coordinates

Returns:

Rectangle in scale coordinates

See also:

[transform\(\)](#)

6.55 QwtPlotLayout Class Reference

Layout engine for [QwtPlot](#).

```
#include <qwt_plot_layout.h>
```

Public Types

- enum [Options](#) {
 - AlignScales** = 1,
 - IgnoreScrollbars** = 2,
 - IgnoreFrames** = 4,
 - IgnoreMargin** = 8,
 - IgnoreLegend** = 16,
 - PrintMargin** = 1,
 - PrintTitle** = 2,
 - PrintLegend** = 4,
 - PrintGrid** = 8,
 - PrintBackground** = 16,
 - PrintFrameWithScales** = 32,
 - PrintAll** = ~PrintFrameWithScales }

Public Member Functions

- [QwtPlotLayout](#) ()
- virtual [~QwtPlotLayout](#) ()
- void [setMargin](#) (int)
- int [margin](#) () const
- void [setCanvasMargin](#) (int margin, int axis=-1)
- int [canvasMargin](#) (int axis) const
- void [setAlignCanvasToScales](#) (bool)
- bool [alignCanvasToScales](#) () const
- void [setSpacing](#) (int)
- int [spacing](#) () const
- void [setLegendPosition](#) ([QwtPlot::LegendPosition](#) pos, double ratio)
- void [setLegendPosition](#) ([QwtPlot::LegendPosition](#) pos)
- [QwtPlot::LegendPosition legendPosition](#) () const

- void [setLegendRatio](#) (double ratio)
- double [legendRatio](#) () const
- virtual QSize [minimumSizeHint](#) (const [QwtPlot](#) *) const
- virtual void [activate](#) (const [QwtPlot](#) *, const [QRect](#) &rect, int options=0)
- virtual void [invalidate](#) ()
- const [QRect](#) & [titleRect](#) () const
- const [QRect](#) & [legendRect](#) () const
- const [QRect](#) & [scaleRect](#) (int axis) const
- const [QRect](#) & [canvasRect](#) () const

Protected Member Functions

- [QRect](#) [layoutLegend](#) (int options, const [QRect](#) &) const
- [QRect](#) [alignLegend](#) (const [QRect](#) &canvasRect, const [QRect](#) &legendRect) const
- void [expandLineBreaks](#) (int options, const [QRect](#) &rect, int &dimTitle, int dimAxes[[QwtPlot::axisCnt](#)]) const
- void [alignScales](#) (int options, [QRect](#) &canvasRect, [QRect](#) scaleRect[[QwtPlot::axisCnt](#)]) const

6.55.1 Detailed Description

Layout engine for [QwtPlot](#).

It is used by the [QwtPlot](#) widget to organize its internal widgets or by [QwtPlot::print\(\)](#) to render its content to a [QPaintDevice](#) like a [QPrinter](#), [QPixmap/QImage](#) or [QSvgRenderer](#).

6.55.2 Member Enumeration Documentation

6.55.2.1 enum [QwtPlotLayout::Options](#)

Options to configure the plot layout engine

- [AlignScales](#)
Unused
- [IgnoreScrollbars](#)
Ignore the dimension of the scrollbars. There are no scrollbars, when the plot is rendered to a paint device ([QwtPlot::print\(\)](#)).
- [IgnoreFrames](#)
Ignore all frames. [QwtPlot::print\(\)](#) doesn't paint them.
- [IgnoreMargin](#)
Ignore the [margin\(\)](#).
- [IgnoreLegend](#)
Ignore the legend.

See also:

[activate\(\)](#)

6.55.3 Constructor & Destructor Documentation

6.55.3.1 QwtPlotLayout::QwtPlotLayout () [explicit]

Constructor.

6.55.3.2 QwtPlotLayout::~~QwtPlotLayout () [virtual]

Destructor.

6.55.4 Member Function Documentation

6.55.4.1 void QwtPlotLayout::setMargin (int *margin*)

Change the margin of the plot. The margin is the space around all components.

Parameters:

margin new margin

See also:

[margin\(\)](#), [setSpacing\(\)](#), [QwtPlot::setMargin\(\)](#)

6.55.4.2 int QwtPlotLayout::margin () const

Returns:

margin

See also:

[setMargin\(\)](#), [spacing\(\)](#), [QwtPlot::margin\(\)](#)

6.55.4.3 void QwtPlotLayout::setCanvasMargin (int *margin*, int *axis* = -1)

Change a margin of the canvas. The margin is the space above/below the scale ticks. A negative margin will be set to -1, excluding the borders of the scales.

Parameters:

margin New margin

axis One of [QwtPlot::Axis](#). Specifies where the position of the margin. -1 means margin at all borders.

See also:

[canvasMargin\(\)](#)

Warning:

The margin will have no effect when `alignCanvasToScales` is true

6.55.4.4 int QwtPlotLayout::canvasMargin (int *axis*) const

Returns:

Margin around the scale tick borders

See also:

[setCanvasMargin\(\)](#)

6.55.4.5 void QwtPlotLayout::setAlignCanvasToScales (bool *alignCanvasToScales*)

Change the align-canvas-to-axis-scales setting. The canvas may:

- extend beyond the axis scale ends to maximize its size,
- align with the axis scale ends to control its size.

Parameters:

alignCanvasToScales New align-canvas-to-axis-scales setting

See also:

[setCanvasMargin\(\)](#)

Note:

In this context the term 'scale' means the backbone of a scale.

Warning:

In case of `alignCanvasToScales == true` `canvasMargin` will have no effect

6.55.4.6 bool QwtPlotLayout::alignCanvasToScales () const

Return the align-canvas-to-axis-scales setting. The canvas may:

- extend beyond the axis scale ends to maximize its size
- align with the axis scale ends to control its size.

Returns:

align-canvas-to-axis-scales setting

See also:

[setAlignCanvasToScales](#), [setCanvasMargin\(\)](#)

Note:

In this context the term 'scale' means the backbone of a scale.

6.55.4.7 void QwtPlotLayout::setSpacing (int *spacing*)

Change the spacing of the plot. The spacing is the distance between the plot components.

Parameters:

spacing new spacing

See also:

[setMargin\(\)](#), [spacing\(\)](#)

6.55.4.8 int QwtPlotLayout::spacing () const

Returns:

spacing

See also:

[margin\(\)](#), [setSpacing\(\)](#)

6.55.4.9 void QwtPlotLayout::setLegendPosition (QwtPlot::LegendPosition *pos*, double *ratio*)

Specify the position of the legend.

Parameters:

pos The legend's position.

ratio Ratio between legend and the bounding rect of title, canvas and axes. The legend will be shrunk if it would need more space than the given ratio. The ratio is limited to]0.0 .. 1.0]. In case of <= 0.0 it will be reset to the default ratio. The default vertical/horizontal ratio is 0.33/0.5.

See also:

[QwtPlot::setLegendPosition\(\)](#)

6.55.4.10 void QwtPlotLayout::setLegendPosition (QwtPlot::LegendPosition *pos*)

Specify the position of the legend.

Parameters:

pos The legend's position. Valid values are [QwtPlot::LeftLegend](#), [QwtPlot::RightLegend](#), [QwtPlot::TopLegend](#), [QwtPlot::BottomLegend](#).

See also:

[QwtPlot::setLegendPosition\(\)](#)

6.55.4.11 [QwtPlot::LegendPosition](#) `QwtPlotLayout::legendPosition () const`**Returns:**

Position of the legend

See also:

[setLegendPosition\(\)](#), [QwtPlot::setLegendPosition\(\)](#), [QwtPlot::legendPosition\(\)](#)

6.55.4.12 `void QwtPlotLayout::setLegendRatio (double ratio)`

Specify the relative size of the legend in the plot

Parameters:

ratio Ratio between legend and the bounding rect of title, canvas and axes. The legend will be shrinked if it would need more space than the given ratio. The ratio is limited to]0.0 .. 1.0]. In case of <= 0.0 it will be reset to the default ratio. The default vertical/horizontal ratio is 0.33/0.5.

6.55.4.13 `double QwtPlotLayout::legendRatio () const`**Returns:**

The relative size of the legend in the plot.

See also:

[setLegendPosition\(\)](#)

6.55.4.14 `QSize QwtPlotLayout::minimumSizeHint (const QwtPlot * plot) const` [virtual]

Return a minimum size hint.

See also:

[QwtPlot::minimumSizeHint\(\)](#)

6.55.4.15 `void QwtPlotLayout::activate (const QwtPlot * plot, const QRect & plotRect, int options = 0)` [virtual]

Recalculate the geometry of all components.

Parameters:

plot Plot to be layout

plotRect Rect where to place the components

options Options

See also:

[invalidate\(\)](#), [Options](#), [titleRect\(\)](#), [legendRect\(\)](#), [scaleRect\(\)](#), [canvasRect\(\)](#)

6.55.4.16 void QwtPlotLayout::invalidate () [virtual]

Invalidate the geometry of all components.

See also:

[activate\(\)](#)

6.55.4.17 const QRect & QwtPlotLayout::titleRect () const

Returns:

Geometry for the title

See also:

[activate\(\)](#), [invalidate\(\)](#)

6.55.4.18 const QRect & QwtPlotLayout::legendRect () const

Returns:

Geometry for the legend

See also:

[activate\(\)](#), [invalidate\(\)](#)

6.55.4.19 const QRect & QwtPlotLayout::scaleRect (int *axis*) const

Parameters:

axis Axis index

Returns:

Geometry for the scale

See also:

[activate\(\)](#), [invalidate\(\)](#)

6.55.4.20 const QRect & QwtPlotLayout::canvasRect () const

Returns:

Geometry for the canvas

See also:

[activate\(\)](#), [invalidate\(\)](#)

6.55.4.21 `QRect QwtPlotLayout::layoutLegend (int options, const QRect & rect) const` [protected]

Find the geometry for the legend

Parameters:

options Options how to layout the legend
rect Rectangle where to place the legend

Returns:

Geometry for the legend

See also:

[Options](#)

6.55.4.22 `QRect QwtPlotLayout::alignLegend (const QRect & canvasRect, const QRect & legendRect) const` [protected]

Align the legend to the canvas

Parameters:

canvasRect Geometry of the canvas
legendRect Maximum geometry for the legend

Returns:

Geometry for the aligned legend

6.55.4.23 `void QwtPlotLayout::expandLineBreaks (int options, const QRect & rect, int & dimTitle, int dimAxis[QwtPlot::axisCnt]) const` [protected]

Expand all line breaks in text labels, and calculate the height of their widgets in orientation of the text.

Parameters:

options Options how to layout the legend
rect Bounding rect for title, axes and canvas.
dimTitle Expanded height of the title widget
dimAxis Expanded heights of the axis in axis orientation.

See also:

[Options](#)

6.55.4.24 `void QwtPlotLayout::alignScales (int options, QRect & canvasRect, QRect scaleRect[QwtPlot::axisCnt]) const` [protected]

Align the ticks of the axis to the canvas borders using the empty corners.

See also:


[Options](#)

6.56 QwtPlotMagnifier Class Reference

[QwtPlotMagnifier](#) provides zooming, by magnifying in steps.

```
#include <qwt_plot_magnifier.h>
```

Inheritance diagram for QwtPlotMagnifier:



Public Member Functions

- [QwtPlotMagnifier](#) ([QwtPlotCanvas](#) *)
- virtual [~QwtPlotMagnifier](#) ()
- void [setAxisEnabled](#) (int axis, bool on)
- bool [isAxisEnabled](#) (int axis) const
- [QwtPlotCanvas](#) * [canvas](#) ()
- const [QwtPlotCanvas](#) * [canvas](#) () const
- [QwtPlot](#) * [plot](#) ()
- const [QwtPlot](#) * [plot](#) () const

Protected Member Functions

- virtual void [rescale](#) (double factor)

6.56.1 Detailed Description

[QwtPlotMagnifier](#) provides zooming, by magnifying in steps.

Using [QwtPlotMagnifier](#) a plot can be zoomed in/out in steps using keys, the mouse wheel or moving a mouse button in vertical direction.

Together with [QwtPlotZoomer](#) and [QwtPlotPanner](#) it is possible to implement individual and powerful navigation of the plot canvas.

See also:

[QwtPlotZoomer](#), [QwtPlotPanner](#), [QwtPlot](#)

6.56.2 Constructor & Destructor Documentation

6.56.2.1 [QwtPlotMagnifier::QwtPlotMagnifier](#) ([QwtPlotCanvas](#) * *canvas*) [explicit]

Constructor

Parameters:

canvas Plot canvas to be magnified

6.56.2.2 QwtPlotMagnifier::~~QwtPlotMagnifier () [virtual]

Destructor.

6.56.3 Member Function Documentation

6.56.3.1 void QwtPlotMagnifier::setAxisEnabled (int *axis*, bool *on*)

En/Disable an axis.

Axes that are enabled will be synchronized to the result of panning. All other axes will remain unchanged.

Parameters:

axis Axis, see [QwtPlot::Axis](#)

on On/Off

See also:

[isAxisEnabled\(\)](#)

6.56.3.2 bool QwtPlotMagnifier::isAxisEnabled (int *axis*) const

Test if an axis is enabled

Parameters:

axis Axis, see [QwtPlot::Axis](#)

Returns:

True, if the axis is enabled

See also:

[setAxisEnabled\(\)](#)

6.56.3.3 QwtPlotCanvas * QwtPlotMagnifier::canvas ()

Return observed plot canvas.

6.56.3.4 const QwtPlotCanvas * QwtPlotMagnifier::canvas () const

Return Observed plot canvas.

6.56.3.5 QwtPlot * QwtPlotMagnifier::plot ()

Return plot widget, containing the observed plot canvas.

6.56.3.6 const QwtPlot * QwtPlotMagnifier::plot () const

Return plot widget, containing the observed plot canvas.

6.56.3.7 void QwtPlotMagnifier::rescale (double *factor*) [protected, virtual]

Zoom in/out the axes scales

Parameters:

factor A value < 1.0 zooms in, a value > 1.0 zooms out.


Implements [QwtMagnifier](#).

6.57 QwtPlotMarker Class Reference

A class for drawing markers.

```
#include <qwt_plot_marker.h>
```

Inheritance diagram for QwtPlotMarker:

**Public Types**

- enum [LineStyle](#) {
NoLine,
HLine,
VLine,
Cross }

Public Member Functions

- [QwtPlotMarker](#) ()
- virtual [~QwtPlotMarker](#) ()
- virtual int [rtti](#) () const
- double [xValue](#) () const
- double [yValue](#) () const
- [QwtDoublePoint value](#) () const
- void [setXValue](#) (double)
- void [setYValue](#) (double)
- void [setValue](#) (double, double)
- void [setValue](#) (const [QwtDoublePoint](#) &)
- void [setLineStyle](#) ([LineStyle](#) st)
- [LineStyle lineStyle](#) () const
- void [setLinePen](#) (const [QPen](#) &p)
- const [QPen](#) & [linePen](#) () const
- void [setSymbol](#) (const [QwtSymbol](#) &s)
- const [QwtSymbol](#) & [symbol](#) () const

- void [setLabel](#) (const [QwtText](#) &)
- [QwtText](#) [label](#) () const
- void [setLabelAlignment](#) (Qt::Alignment)
- Qt::Alignment [labelAlignment](#) () const
- void [setLabelOrientation](#) (Qt::Orientation)
- Qt::Orientation [labelOrientation](#) () const
- void [setSpacing](#) (int)
- int [spacing](#) () const
- virtual void [draw](#) (QPainter *p, const [QwtScaleMap](#) &xMap, const [QwtScaleMap](#) &yMap, const [QRect](#) &) const
- virtual [QwtDoubleRect](#) [boundingRect](#) () const

Protected Member Functions

- void [drawAt](#) (QPainter *, const [QRect](#) &, const [QPoint](#) &) const

6.57.1 Detailed Description

A class for drawing markers.

A marker can be a horizontal line, a vertical line, a symbol, a label or any combination of them, which can be drawn around a center point inside a bounding rectangle.

The [QwtPlotMarker::setSymbol\(\)](#) member assigns a symbol to the marker. The symbol is drawn at the specified point.

With [QwtPlotMarker::setLabel\(\)](#), a label can be assigned to the marker. The [QwtPlotMarker::setLabelAlignment\(\)](#) member specifies where the label is drawn. All the `Align*`-constants in `Qt::AlignmentFlags` (see Qt documentation) are valid. The interpretation of the alignment depends on the marker's line style. The alignment refers to the center point of the marker, which means, for example, that the label would be printed left above the center point if the alignment was set to `AlignLeft|AlignTop`.

6.57.2 Member Enumeration Documentation

6.57.2.1 enum [QwtPlotMarker::LineStyle](#)

Line styles.

See also:

[setLineStyle\(\)](#), [lineStyle\(\)](#)

6.57.3 Constructor & Destructor Documentation

6.57.3.1 [QwtPlotMarker::QwtPlotMarker](#) () [explicit]

Sets alignment to `Qt::AlignCenter`, and style to `NoLine`.

6.57.3.2 [QwtPlotMarker::~QwtPlotMarker](#) () [virtual]

Destructor.

6.57.4 Member Function Documentation

6.57.4.1 `int QwtPlotMarker::rtti () const` [virtual]

Returns:

QwtPlotItem::Rtti_PlotMarker

Reimplemented from [QwtPlotItem](#).

6.57.4.2 `double QwtPlotMarker::xValue () const`

Return x Value.

6.57.4.3 `double QwtPlotMarker::yValue () const`

Return y Value.

6.57.4.4 `QwtDoublePoint QwtPlotMarker::value () const`

Return Value.

6.57.4.5 `void QwtPlotMarker::setXValue (double)`

Set X Value.

6.57.4.6 `void QwtPlotMarker::setYValue (double)`

Set Y Value.

6.57.4.7 `void QwtPlotMarker::setValue (double, double)`

Set Value.

6.57.4.8 `void QwtPlotMarker::setValue (const QwtDoublePoint &)`

Set Value.

6.57.4.9 `void QwtPlotMarker::setLineStyle (QwtPlotMarker::LineStyle st)`

Set the line style.

Parameters:

st Line style. Can be one of QwtPlotMarker::NoLine, HLine, VLine or Cross

See also:

[lineStyle\(\)](#)

6.57.4.10 [QwtPlotMarker::LineStyle](#) QwtPlotMarker::lineStyle () const**Returns:**

the line style

See also:

For a description of line styles, see [QwtPlotMarker::setLineStyle\(\)](#)

6.57.4.11 void QwtPlotMarker::setLinePen (const QPen & *pen*)

Specify a pen for the line.

The width of non cosmetic pens is scaled according to the resolution of the paint device.

Parameters:

pen New pen

See also:

[linePen\(\)](#), [QwtPainter::scaledPen\(\)](#)

6.57.4.12 const QPen & QwtPlotMarker::linePen () const**Returns:**

the line pen

See also:

[setLinePen\(\)](#)

6.57.4.13 void QwtPlotMarker::setSymbol (const QwtSymbol & *s*)

Assign a symbol.

Parameters:

s New symbol

See also:

[symbol\(\)](#)

6.57.4.14 const QwtSymbol & QwtPlotMarker::symbol () const**Returns:**

the symbol

See also:

[setSymbol\(\)](#), [QwtSymbol](#)

6.57.4.15 void QwtPlotMarker::setLabel (const QwtText & label)

Set the label.

Parameters:

label label text

See also:

[label\(\)](#)

6.57.4.16 QwtText QwtPlotMarker::label () const**Returns:**

the label

See also:

[setLabel\(\)](#)

6.57.4.17 void QwtPlotMarker::setLabelAlignment (Qt::Alignment align)

Set the alignment of the label.

In case of QwtPlotMarker::HLine the alignment is relative to the y position of the marker, but the horizontal flags correspond to the canvas rectangle. In case of QwtPlotMarker::VLine the alignment is relative to the x position of the marker, but the vertical flags correspond to the canvas rectangle.

In all other styles the alignment is relative to the marker's position.

Parameters:

align Alignment. A combination of AlignTop, AlignBottom, AlignLeft, AlignRight, AlignCenter, AlgnHCenter, AlignVCenter.

See also:

[labelAlignment\(\)](#), [labelOrientation\(\)](#)

6.57.4.18 Qt::Alignment QwtPlotMarker::labelAlignment () const**Returns:**

the label alignment

See also:

[setLabelAlignment\(\)](#), [setLabelOrientation\(\)](#)

6.57.4.19 void QwtPlotMarker::setLabelOrientation (Qt::Orientation *orientation*)

Set the orientation of the label.

When orientation is Qt::Vertical the label is rotated by 90.0 degrees (from bottom to top).

Parameters:

orientation Orientation of the label

See also:

[labelOrientation\(\)](#), [setLabelAlignment\(\)](#)

6.57.4.20 Qt::Orientation QwtPlotMarker::labelOrientation () const**Returns:**

the label orientation

See also:

[setLabelOrientation\(\)](#), [labelAlignment\(\)](#)

6.57.4.21 void QwtPlotMarker::setSpacing (int *spacing*)

Set the spacing.

When the label is not centered on the marker position, the spacing is the distance between the position and the label.

Parameters:

spacing Spacing

See also:

[spacing\(\)](#), [setLabelAlignment\(\)](#)

6.57.4.22 int QwtPlotMarker::spacing () const**Returns:**

the spacing

See also:

[setSpacing\(\)](#)

6.57.4.23 void QwtPlotMarker::draw (QPainter * *painter*, const QwtScaleMap & *xMap*, const QwtScaleMap & *yMap*, const QRect & *canvasRect*) const [virtual]

Draw the marker

Parameters:

painter Painter
xMap x Scale Map
yMap y Scale Map
canvasRect Contents rect of the canvas in painter coordinates

Implements [QwtPlotItem](#).

6.57.4.24 QwtDoubleRect QwtPlotMarker::boundingRect () const [virtual]**Returns:**

An invalid bounding rect: QwtDoubleRect(1.0, 1.0, -2.0, -2.0)

Reimplemented from [QwtPlotItem](#).

6.57.4.25 void QwtPlotMarker::drawAt (QPainter * painter, const QRect & canvasRect, const QPoint & pos) const [protected]

Draw the marker at a specific position

Parameters:


painter Painter
canvasRect Contents rect of the canvas in painter coordinates
pos Position of the marker in painter coordinates

6.58 QwtPlotPanner Class Reference

[QwtPlotPanner](#) provides panning of a plot canvas.

```
#include <qwt_plot_panner.h>
```

Inheritance diagram for [QwtPlotPanner](#):

**Public Member Functions**

- [QwtPlotPanner](#) ([QwtPlotCanvas](#) *)
- virtual [~QwtPlotPanner](#) ()
- [QwtPlotCanvas](#) * [canvas](#) ()
- const [QwtPlotCanvas](#) * [canvas](#) () const
- [QwtPlot](#) * [plot](#) ()
- const [QwtPlot](#) * [plot](#) () const
- void [setAxisEnabled](#) (int axis, bool on)
- bool [isAxisEnabled](#) (int axis) const

Protected Slots

- virtual void [moveCanvas](#) (int dx, int dy)

6.58.1 Detailed Description

[QwtPlotPanner](#) provides panning of a plot canvas.

[QwtPlotPanner](#) is a panner for a [QwtPlotCanvas](#), that adjusts the scales of the axes after dropping the canvas on its new position.

Together with [QwtPlotZoomer](#) and [QwtPlotMagnifier](#) powerful ways of navigating on a [QwtPlot](#) widget can be implemented easily.

Note:

The axes are not updated, while dragging the canvas

See also:

[QwtPlotZoomer](#), [QwtPlotMagnifier](#)

6.58.2 Constructor & Destructor Documentation

6.58.2.1 [QwtPlotPanner::QwtPlotPanner \(QwtPlotCanvas * canvas\)](#) [explicit]

Create a plot panner.

The panner is enabled for all axes

Parameters:

canvas Plot canvas to pan, also the parent object

See also:

[setAxisEnabled\(\)](#)

6.58.2.2 [QwtPlotPanner::~~QwtPlotPanner \(\)](#) [virtual]

Destructor.

6.58.3 Member Function Documentation

6.58.3.1 [QwtPlotCanvas * QwtPlotPanner::canvas \(\)](#)

Return observed plot canvas.

6.58.3.2 [const QwtPlotCanvas * QwtPlotPanner::canvas \(\) const](#)

Return Observed plot canvas.

6.58.3.3 [QwtPlot * QwtPlotPanner::plot \(\)](#)

Return plot widget, containing the observed plot canvas.

6.58.3.4 `const QwtPlot * QwtPlotPanner::plot () const`

Return plot widget, containing the observed plot canvas.

6.58.3.5 `void QwtPlotPanner::setAxisEnabled (int axis, bool on)`

En/Disable an axis.

Axes that are enabled will be synchronized to the result of panning. All other axes will remain unchanged.

Parameters:

axis Axis, see [QwtPlot::Axis](#)

on On/Off

See also:

[isAxisEnabled\(\)](#), [moveCanvas\(\)](#)

6.58.3.6 `bool QwtPlotPanner::isAxisEnabled (int axis) const`

Test if an axis is enabled

Parameters:

axis Axis, see [QwtPlot::Axis](#)

Returns:

True, if the axis is enabled

See also:

[setAxisEnabled\(\)](#), [moveCanvas\(\)](#)

6.58.3.7 `void QwtPlotPanner::moveCanvas (int dx, int dy) [protected, virtual, slot]`

Adjust the enabled axes according to dx/dy

Parameters:

dx Pixel offset in x direction

dy Pixel offset in y direction

See also:


[QwtPanner::panned\(\)](#)

6.59 QwtPlotPicker Class Reference

[QwtPlotPicker](#) provides selections on a plot canvas.

```
#include <qwt_plot_picker.h>
```

Inheritance diagram for QwtPlotPicker:



Signals

- void [selected](#) (const [QwtDoublePoint](#) &pos)
- void [selected](#) (const [QwtDoubleRect](#) &rect)
- void [selected](#) (const [QwtArray](#)< [QwtDoublePoint](#) > &pa)
- void [appended](#) (const [QwtDoublePoint](#) &pos)
- void [moved](#) (const [QwtDoublePoint](#) &pos)

Public Member Functions

- [QwtPlotPicker](#) ([QwtPlotCanvas](#) *)
- virtual [~QwtPlotPicker](#) ()
- [QwtPlotPicker](#) (int xAxis, int yAxis, [QwtPlotCanvas](#) *)
- [QwtPlotPicker](#) (int xAxis, int yAxis, int selectionFlags, [RubberBand](#) rubberBand, [DisplayMode](#) trackerMode, [QwtPlotCanvas](#) *)
- virtual void [setAxis](#) (int xAxis, int yAxis)
- int [xAxis](#) () const
- int [yAxis](#) () const
- [QwtPlot](#) * [plot](#) ()
- const [QwtPlot](#) * [plot](#) () const
- [QwtPlotCanvas](#) * [canvas](#) ()
- const [QwtPlotCanvas](#) * [canvas](#) () const

Protected Member Functions

- [QwtDoubleRect](#) [scaleRect](#) () const
- [QwtDoubleRect](#) [invTransform](#) (const [QRect](#) &) const
- [QRect](#) [transform](#) (const [QwtDoubleRect](#) &) const
- [QwtDoublePoint](#) [invTransform](#) (const [QPoint](#) &) const
- [QPoint](#) [transform](#) (const [QwtDoublePoint](#) &) const
- virtual [QwtText](#) [trackerText](#) (const [QPoint](#) &) const
- virtual [QwtText](#) [trackerText](#) (const [QwtDoublePoint](#) &) const
- virtual void [move](#) (const [QPoint](#) &)
- virtual void [append](#) (const [QPoint](#) &)
- virtual bool [end](#) (bool ok=true)

6.59.1 Detailed Description

[QwtPlotPicker](#) provides selections on a plot canvas.

[QwtPlotPicker](#) is a [QwtPicker](#) tailored for selections on a plot canvas. It is set to a x-Axis and y-Axis and translates all pixel coordinates into this coordinate system.

6.59.2 Constructor & Destructor Documentation

6.59.2.1 QwtPlotPicker::QwtPlotPicker ([QwtPlotCanvas](#) * *canvas*) [explicit]

Create a plot picker.

The picker is set to those x- and y-axis of the plot that are enabled. If both or no x-axis are enabled, the picker is set to `QwtPlot::xBottom`. If both or no y-axis are enabled, it is set to `QwtPlot::yLeft`.

Parameters:

canvas Plot canvas to observe, also the parent object

See also:

[QwtPlot::autoReplot\(\)](#), [QwtPlot::replot\(\)](#), [QwtPlotPicker::scaleRect\(\)](#)

6.59.2.2 QwtPlotPicker::~~QwtPlotPicker () [virtual]

Destructor.

6.59.2.3 QwtPlotPicker::QwtPlotPicker (int *xAxis*, int *yAxis*, [QwtPlotCanvas](#) * *canvas*) [explicit]

Create a plot picker

Parameters:

xAxis Set the x axis of the picker

yAxis Set the y axis of the picker

canvas Plot canvas to observe, also the parent object

See also:

[QwtPlot::autoReplot\(\)](#), [QwtPlot::replot\(\)](#), [QwtPlotPicker::scaleRect\(\)](#)

6.59.2.4 QwtPlotPicker::QwtPlotPicker (int *xAxis*, int *yAxis*, int *selectionFlags*, [RubberBand](#) *rubberBand*, [DisplayMode](#) *trackerMode*, [QwtPlotCanvas](#) * *canvas*) [explicit]

Create a plot picker

Parameters:

xAxis X axis of the picker

yAxis Y axis of the picker

selectionFlags Or'd value of `SelectionType`, `RectSelectionType` and `SelectionMode`

rubberBand Rubberband style
trackerMode Tracker mode
canvas Plot canvas to observe, also the parent object

See also:

[QwtPicker](#), [QwtPicker::setSelectionFlags\(\)](#), [QwtPicker::setRubberBand\(\)](#), [QwtPicker::setTrackerMode](#)
[QwtPlot::autoReplot\(\)](#), [QwtPlot::replot\(\)](#), [QwtPlotPicker::scaleRect\(\)](#)

6.59.3 Member Function Documentation

6.59.3.1 void QwtPlotPicker::setAxis (int xAxis, int yAxis) [virtual]

Set the x and y axes of the picker

Parameters:

xAxis X axis
yAxis Y axis

Reimplemented in [QwtPlotZoomer](#).

6.59.3.2 int QwtPlotPicker::xAxis () const

Return x axis.

6.59.3.3 int QwtPlotPicker::yAxis () const

Return y axis.

6.59.3.4 QwtPlot * QwtPlotPicker::plot ()

Return plot widget, containing the observed plot canvas.

6.59.3.5 const QwtPlot * QwtPlotPicker::plot () const

Return plot widget, containing the observed plot canvas.

6.59.3.6 QwtPlotCanvas * QwtPlotPicker::canvas ()

Return observed plot canvas.

6.59.3.7 const QwtPlotCanvas * QwtPlotPicker::canvas () const

Return Observed plot canvas.

6.59.3.8 void QwtPlotPicker::selected (const QwtDoublePoint & pos) [signal]

A signal emitted in case of [selectionFlags\(\)](#) & PointSelection.

Parameters:

pos Selected point

6.59.3.9 void QwtPlotPicker::selected (const QwtDoubleRect & *rect*) [signal]

A signal emitted in case of [selectionFlags\(\)](#) & RectSelection.

Parameters:

rect Selected rectangle

6.59.3.10 void QwtPlotPicker::selected (const QwtArray< QwtDoublePoint > & *pa*) [signal]

A signal emitting the selected points, at the end of a selection.

Parameters:

pa Selected points

6.59.3.11 void QwtPlotPicker::appended (const QwtDoublePoint & *pos*) [signal]

A signal emitted when a point has been appended to the selection

Parameters:

pos Position of the appended point.

See also:

[append\(\). moved\(\)](#)

6.59.3.12 void QwtPlotPicker::moved (const QwtDoublePoint & *pos*) [signal]

A signal emitted whenever the last appended point of the selection has been moved.

Parameters:

pos Position of the moved last point of the selection.

See also:

[move\(\)](#), [appended\(\)](#)

6.59.3.13 QwtDoubleRect QwtPlotPicker::scaleRect () const [protected]

Return normalized bounding rect of the axes

See also:

[QwtPlot::autoReplot\(\)](#), [QwtPlot::replot\(\)](#).

6.59.3.14 [QwtDoubleRect](#) `QwtPlotPicker::invTransform (const QRect & rect) const` [protected]

Translate a rectangle from pixel into plot coordinates

Returns:

Rectangle in plot coordinates

See also:

[QwtPlotPicker::transform\(\)](#)

6.59.3.15 `QRect QwtPlotPicker::transform (const QwtDoubleRect & rect) const` [protected]

Translate a rectangle from plot into pixel coordinates

Returns:

Rectangle in pixel coordinates

See also:

[QwtPlotPicker::invTransform\(\)](#)

6.59.3.16 [QwtDoublePoint](#) `QwtPlotPicker::invTransform (const QPoint & pos) const` [protected]

Translate a point from pixel into plot coordinates

Returns:

Point in plot coordinates

See also:

[QwtPlotPicker::transform\(\)](#)

6.59.3.17 `QPoint QwtPlotPicker::transform (const QwtDoublePoint & pos) const` [protected]

Translate a point from plot into pixel coordinates

Returns:

Point in pixel coordinates

See also:

[QwtPlotPicker::invTransform\(\)](#)

6.59.3.18 [QwtText](#) `QwtPlotPicker::trackerText (const QPoint & pos) const` [protected, virtual]

Translate a pixel position into a position string

Parameters:

pos Position in pixel coordinates

Returns:

Position string

Reimplemented from [QwtPicker](#).

6.59.3.19 [QwtText](#) `QwtPlotPicker::trackerText (const QwtDoublePoint & pos) const` [protected, virtual]

Translate a position into a position string.

In case of [HLineRubberBand](#) the label is the value of the y position, in case of [VLineRubberBand](#) the value of the x position. Otherwise the label contains x and y position separated by a ','.

The format for the double to string conversion is "%.4f".

Parameters:

pos Position

Returns:

Position string

6.59.3.20 `void QwtPlotPicker::move (const QPoint & pos)` [protected, virtual]

Move the last point of the selection

Parameters:

pos New position

See also:

[isActive](#), [begin\(\)](#), [end\(\)](#), [append\(\)](#)

Note:

The [moved\(const QPoint &\)](#), [moved\(const QDoublePoint &\)](#) signals are emitted.

Reimplemented from [QwtPicker](#).

6.59.3.21 `void QwtPlotPicker::append (const QPoint & pos)` [protected, virtual]

Append a point to the selection and update rubberband and tracker.

Parameters:

pos Additional point

See also:

[isActive](#), [begin\(\)](#), [end\(\)](#), [move\(\)](#), [appended\(\)](#)

Note:

The [appended\(const QPoint &\)](#), [appended\(const QDoublePoint &\)](#) signals are emitted.

Reimplemented from [QwtPicker](#).

6.59.3.22 bool QwtPlotPicker::end (bool *ok* = true) [protected, virtual]

Close a selection setting the state to inactive.

Parameters:

ok If true, complete the selection and emit selected signals otherwise discard the selection.

Returns:

true if the selection is accepted, false otherwise

Reimplemented from [QwtPicker](#).

Reimplemented in [QwtPlotZoomer](#).

6.60 QwtPlotPrintFilter Class Reference

A base class for plot print filters.

```
#include <qwt_plot_printfilter.h>
```

Public Types

- enum [Options](#) {
 AlignScales = 1,
 IgnoreScrollbars = 2,
 IgnoreFrames = 4,
 IgnoreMargin = 8,
 IgnoreLegend = 16,
 PrintMargin = 1,
 PrintTitle = 2,
 PrintLegend = 4,
 PrintGrid = 8,
 PrintBackground = 16,
 PrintFrameWithScales = 32,
 PrintAll = ~PrintFrameWithScales }

- enum `Item` {
 Title,
 Legend,
 Curve,
 CurveSymbol,
 Marker,
 MarkerSymbol,
 MajorGrid,
 MinorGrid,
 CanvasBackground,
 AxisScale,
 AxisTitle,
 WidgetBackground }

Public Member Functions

- `QwtPlotPrintFilter` ()
- virtual `~QwtPlotPrintFilter` ()
- virtual `QColor color` (const `QColor` &, `Item` item) const
- virtual `QFont font` (const `QFont` &, `Item` item) const
- void `setOptions` (int options)
- int `options` () const
- virtual void `apply` (`QwtPlot` *) const
- virtual void `reset` (`QwtPlot` *) const
- virtual void `apply` (`QwtPlotItem` *) const
- virtual void `reset` (`QwtPlotItem` *) const

6.60.1 Detailed Description

A base class for plot print filters.

A print filter can be used to customize `QwtPlot::print()`.

Deprecated

In Qwt 5.0 the design of `QwtPlot` allows/recommends writing individual `QwtPlotItems`, that are not known to `QwtPlotPrintFilter`. So this concept is outdated and `QwtPlotPrintFilter` will be removed/replaced in Qwt 6.x.

6.60.2 Member Enumeration Documentation

6.60.2.1 enum `QwtPlotPrintFilter::Options`

Print options.

6.60.2.2 enum `QwtPlotPrintFilter::Item`

Print items.

6.60.3 Constructor & Destructor Documentation

6.60.3.1 QwtPlotPrintFilter::QwtPlotPrintFilter () [explicit]

Sets filter options to PrintAll

6.60.3.2 QwtPlotPrintFilter::~~QwtPlotPrintFilter () [virtual]

Destructor.

6.60.4 Member Function Documentation

6.60.4.1 QColor QwtPlotPrintFilter::color (const QColor & *c*, **Item** *item*) const [virtual]

Modifies a color for printing.

Parameters:

c Color to be modified

item Type of item where the color belongs

Returns:

Modified color.

In case of `!(QwtPlotPrintFilter::options() & PrintBackground)` MajorGrid is modified to `Qt::darkGray`, MinorGrid to `Qt::gray`. All other colors are returned unmodified.

6.60.4.2 QFont QwtPlotPrintFilter::font (const QFont & *f*, **Item** *item*) const [virtual]

Modifies a font for printing.

Parameters:

f Font to be modified

item Type of item where the font belongs

All fonts are returned unmodified

6.60.4.3 void QwtPlotPrintFilter::setOptions (int *options*)

Set plot print options.

Parameters:

options Or'd `QwtPlotPrintFilter::Options` values

See also:

[options\(\)](#)

6.60.4.4 `int QwtPlotPrintFilter::options () const`

Get plot print options.

See also:

[setOptions\(\)](#)

6.60.4.5 `void QwtPlotPrintFilter::apply (QwtPlot *plot) const` [virtual]

Change color and fonts of a plot

See also:

[apply\(\)](#)

6.60.4.6 `void QwtPlotPrintFilter::reset (QwtPlot *plot) const` [virtual]

Reset color and fonts of a plot

See also:


[apply\(\)](#)

6.61 QwtPlotRasterItem Class Reference

A class, which displays raster data.

```
#include <qwt_plot_rasteritem.h>
```

Inheritance diagram for QwtPlotRasterItem:

**Public Types**

- enum [CachePolicy](#) {
NoCache,
PaintCache,
ScreenCache }

Public Member Functions

- [QwtPlotRasterItem](#) (const QString &title=QString::null)
- [QwtPlotRasterItem](#) (const [QwtText](#) &title)
- virtual [~QwtPlotRasterItem](#) ()
- void [setAlpha](#) (int alpha)
- int [alpha](#) () const
- void [setCachePolicy](#) ([CachePolicy](#))
- [CachePolicy](#) [cachePolicy](#) () const
- void [invalidateCache](#) ()
- virtual void [draw](#) (QPainter *p, const [QwtScaleMap](#) &xMap, const [QwtScaleMap](#) &yMap, const QRect &rect) const
- virtual QSize [rasterHint](#) (const [QwtDoubleRect](#) &) const

Protected Member Functions

- virtual QImage [renderImage](#) (const [QwtScaleMap](#) &xMap, const [QwtScaleMap](#) &yMap, const [QwtDoubleRect](#) &area) const=0

6.61.1 Detailed Description

A class, which displays raster data.

Raster data is a grid of pixel values, that can be represented as a QImage. It is used for many types of information like spectrograms, cartograms, geographical maps ...

Often a plot has several types of raster data organized in layers. (f.e a geographical map, with weather statistics). Using [setAlpha\(\)](#) raster items can be stacked easily.

[QwtPlotRasterItem](#) is only implemented for images of the following formats: QImage::Format_Indexed8, QImage::Format_ARGB32.

See also:

[QwtPlotSpectrogram](#)

6.61.2 Member Enumeration Documentation

6.61.2.1 enum [QwtPlotRasterItem::CachePolicy](#)

- NoCache
[renderImage\(\)](#) is called, whenever the item has to be repainted
- PaintCache
[renderImage\(\)](#) is called, whenever the image cache is not valid, or the scales, or the size of the canvas has changed. This type of cache is only useful for improving the performance of hide/show operations. All other situations are already handled by the plot canvas cache.
- ScreenCache
The screen cache is an image in size of the screen. As long as the scales don't change the target image is scaled from the cache. This might improve the performance when resizing the plot widget, but suffers from scaling effects.

The default policy is NoCache

6.61.3 Constructor & Destructor Documentation

6.61.3.1 QwtPlotRasterItem::QwtPlotRasterItem (const QString & title = QString::null) [explicit]

Constructor.

6.61.3.2 QwtPlotRasterItem::QwtPlotRasterItem (const QwtText & title) [explicit]

Constructor.

6.61.3.3 QwtPlotRasterItem::~~QwtPlotRasterItem () [virtual]

Destructor.

6.61.4 Member Function Documentation

6.61.4.1 void QwtPlotRasterItem::setAlpha (int alpha)

Set an alpha value for the raster data.

Often a plot has several types of raster data organized in layers. (f.e a geographical map, with weather statistics). Using [setAlpha\(\)](#) raster items can be stacked easily.

The alpha value is a value [0, 255] to control the transparency of the image. 0 represents a fully transparent color, while 255 represents a fully opaque color.

Parameters:

alpha Alpha value

- alpha \geq 0
All alpha values of the pixels returned by [renderImage\(\)](#) will be set to alpha, beside those with an alpha value of 0 (invalid pixels).
- alpha $<$ 0 The alpha values returned by [renderImage\(\)](#) are not changed.

The default alpha value is -1.

See also:

[alpha\(\)](#)

6.61.4.2 int QwtPlotRasterItem::alpha () const

Returns:

Alpha value of the raster item

See also:

[setAlpha\(\)](#)

6.61.4.3 void QwtPlotRasterItem::setCachePolicy (QwtPlotRasterItem::CachePolicy *policy*)

Change the cache policy

The default policy is NoCache

Parameters:

policy Cache policy

See also:

[CachePolicy](#), [cachePolicy\(\)](#)

6.61.4.4 QwtPlotRasterItem::CachePolicy QwtPlotRasterItem::cachePolicy () const**Returns:**

Cache policy

See also:

[CachePolicy](#), [setCachePolicy\(\)](#)

6.61.4.5 void QwtPlotRasterItem::invalidateCache ()

Invalidate the paint cache

See also:

[setCachePolicy\(\)](#)

6.61.4.6 void QwtPlotRasterItem::draw (QPainter * *painter*, const QwtScaleMap & *xMap*, const QwtScaleMap & *yMap*, const QRect & *canvasRect*) const [virtual]

Draw the raster data.

Parameters:

painter Painter

xMap X-Scale Map

yMap Y-Scale Map

canvasRect Contents rect of the plot canvas

Implements [QwtPlotItem](#).

Reimplemented in [QwtPlotSpectrogram](#).

6.61.4.7 QSize QwtPlotRasterItem::rasterHint (const QwtDoubleRect &) const [virtual]

Returns the recommended raster for a given rect.

E.g. the raster hint can be used to limit the resolution of the image that is rendered.

The default implementation returns an invalid size (QSize()), what means: no hint.

Reimplemented in [QwtPlotSpectrogram](#).

6.61.4.8 virtual QImage QwtPlotRasterItem::renderImage (const QwtScaleMap & *xMap*, const QwtScaleMap & *yMap*, const QwtDoubleRect & *area*) const [protected, pure virtual]

Renders an image for an area

The format of the image must be QImage::Format_Indexed8, QImage::Format_RGB32 or QImage::Format_ARGB32

Parameters:

- xMap* Maps x-values into pixel coordinates.
- yMap* Maps y-values into pixel coordinates.
- area* Requested area for the image in scale coordinates

Implemented in [QwtPlotSpectrogram](#).

6.62 QwtPlotRescaler Class Reference

[QwtPlotRescaler](#) takes care of fixed aspect ratios for plot scales.

```
#include <qwt_plot_rescaler.h>
```

Public Types

- enum [RescalePolicy](#) {
Fixed,
Expanding,
Fitting }
- enum [ExpandingDirection](#) {
ExpandUp,
ExpandDown,
ExpandBoth }

Public Member Functions

- [QwtPlotRescaler](#) ([QwtPlotCanvas](#) *, int referenceAxis=[QwtPlot::xBottom](#), [RescalePolicy](#)=[Expanding](#))
- virtual [~QwtPlotRescaler](#) ()
- void [setEnabled](#) (bool)
- bool [isEnabled](#) () const
- void [setRescalePolicy](#) ([RescalePolicy](#))
- [RescalePolicy](#) [rescalePolicy](#) () const
- void [setExpandingDirection](#) ([ExpandingDirection](#))
- void [setExpandingDirection](#) (int axis, [ExpandingDirection](#))
- [ExpandingDirection](#) [expandingDirection](#) (int axis) const
- void [setReferenceAxis](#) (int axis)
- int [referenceAxis](#) () const
- void [setAspectRatio](#) (double ratio)
- void [setAspectRatio](#) (int axis, double ratio)
- double [aspectRatio](#) (int axis) const

- void **setIntervalHint** (int axis, const [QwtDoubleInterval](#) &)
- [QwtDoubleInterval](#) **intervalHint** (int axis) const
- [QwtPlotCanvas](#) * **canvas** ()
- const [QwtPlotCanvas](#) * **canvas** () const
- [QwtPlot](#) * **plot** ()
- const [QwtPlot](#) * **plot** () const
- virtual bool **eventFilter** (QObject *, QEvent *)
- void **rescale** () const

Protected Member Functions

- virtual void **canvasResizeEvent** (QResizeEvent *)
- virtual void **rescale** (const QSize &oldSize, const QSize &newSize) const
- virtual [QwtDoubleInterval](#) **expandScale** (int axis, const QSize &oldSize, const QSize &newSize) const
- virtual [QwtDoubleInterval](#) **syncScale** (int axis, const [QwtDoubleInterval](#) &reference, const QSize &size) const
- virtual void **updateScales** ([QwtDoubleInterval](#) intervals[[QwtPlot::axisCnt](#)]) const
- Qt::Orientation **orientation** (int axis) const
- [QwtDoubleInterval](#) **interval** (int axis) const
- [QwtDoubleInterval](#) **expandInterval** (const [QwtDoubleInterval](#) &, double width, Expanding-Direction) const

6.62.1 Detailed Description

[QwtPlotRescaler](#) takes care of fixed aspect ratios for plot scales.

[QwtPlotRescaler](#) autoadjusts the axes of a [QwtPlot](#) according to fixed aspect ratios.

6.62.2 Member Enumeration Documentation

6.62.2.1 enum [QwtPlotRescaler::RescalePolicy](#)

Rescale Policy.

The rescale policy defines how to rescale the reference axis and their depending axes.

- Fixed

The interval of the reference axis remains unchanged, when the geometry of the canvas changes. All other axes will be adjusted according to their aspect ratio.

- Expanding

The interval of the reference axis will be shrunk/expanded, when the geometry of the canvas changes. All other axes will be adjusted according to their aspect ratio.

The interval, that is represented by one pixel is fixed.

- Fitting

The intervals of the axes are calculated, so that all axes include their minimal interval.

6.62.3 Constructor & Destructor Documentation

6.62.3.1 `QwtPlotRescaler::QwtPlotRescaler (QwtPlotCanvas * canvas, int referenceAxis = QwtPlot::xBottom, RescalePolicy policy = Expanding) [explicit]`

Constructor

Parameters:

canvas Canvas
referenceAxis Reference axis, see RescalePolicy
policy Rescale policy

See also:

[setRescalePolicy\(\)](#), [setReferenceAxis\(\)](#)

6.62.3.2 `QwtPlotRescaler::~~QwtPlotRescaler () [virtual]`

Destructor.

6.62.4 Member Function Documentation

6.62.4.1 `void QwtPlotRescaler::setEnabled (bool on)`

En/disable the rescaler.

When enabled is true an event filter is installed for the canvas, otherwise the event filter is removed.

Parameters:

on true or false

See also:

[isEnabled\(\)](#), [eventFilter\(\)](#)

6.62.4.2 `bool QwtPlotRescaler::isEnabled () const`

Returns:

true when enabled, false otherwise

See also:

[setEnabled\(\)](#), [eventFilter\(\)](#)

6.62.4.3 `void QwtPlotRescaler::setRescalePolicy (RescalePolicy policy)`

Change the rescale policy

Parameters:

policy Rescale policy

See also:

[rescalePolicy\(\)](#)

6.62.4.4 QwtPlotRescaler::RescalePolicy QwtPlotRescaler::rescalePolicy () const**Returns:**

Rescale policy

See also:

[setRescalePolicy\(\)](#)

6.62.4.5 void QwtPlotRescaler::setExpandingDirection (ExpandingDirection *direction*)

Set the direction in which all axis should be expanded

Parameters:

direction Direction

See also:

[expandingDirection\(\)](#)

6.62.4.6 void QwtPlotRescaler::setExpandingDirection (int *axis*, ExpandingDirection *direction*)

Set the direction in which an axis should be expanded

Parameters:

axis Axis index (see QwtPlot::AxisId)

direction Direction

See also:

[expandingDirection\(\)](#)

6.62.4.7 QwtPlotRescaler::ExpandingDirection QwtPlotRescaler::expandingDirection (int *axis*) const

Return direction in which an axis should be expanded

Parameters:

axis Axis index (see QwtPlot::AxisId)

See also:

[setExpandingDirection\(\)](#)

6.62.4.8 void QwtPlotRescaler::setReferenceAxis (int *axis*)

Set the reference axis (see RescalePolicy)

Parameters:

axis Axis index ([QwtPlot::Axis](#))

See also:

[referenceAxis\(\)](#)

6.62.4.9 int QwtPlotRescaler::referenceAxis () const**Returns:**

Reference axis (see RescalePolicy)

See also:

[setReferenceAxis\(\)](#)

6.62.4.10 void QwtPlotRescaler::setAspectRatio (double *ratio*)

Set the aspect ratio between the scale of the reference axis and the other scales. The default ratio is 1.0

Parameters:

ratio Aspect ratio

See also:

[aspectRatio\(\)](#)

6.62.4.11 void QwtPlotRescaler::setAspectRatio (int *axis*, double *ratio*)

Set the aspect ratio between the scale of the reference axis and another scale. The default ratio is 1.0

Parameters:

axis Axis index (see QwtPlot::AxisId)

ratio Aspect ratio

See also:

[aspectRatio\(\)](#)

6.62.4.12 double QwtPlotRescaler::aspectRatio (int *axis*) const

Return aspect ratio between an axis and the reference axis.

Parameters:

axis Axis index (see QwtPlot::AxisId)

See also:

[setAspectRatio\(\)](#)

6.62.4.13 QwtPlotCanvas * QwtPlotRescaler::canvas ()**Returns:**

plot canvas

6.62.4.14 `const QwtPlotCanvas * QwtPlotRescaler::canvas () const`

Returns:

plot canvas

6.62.4.15 `QwtPlot * QwtPlotRescaler::plot ()`

Returns:

plot widget

6.62.4.16 `const QwtPlot * QwtPlotRescaler::plot () const`

Returns:

plot widget

6.62.4.17 `bool QwtPlotRescaler::eventFilter (QObject *, QEvent *) [virtual]`

Event filter for the plot canvas.

6.62.4.18 `void QwtPlotRescaler::rescale () const`

Adjust the plot axes scales.

6.62.4.19 `void QwtPlotRescaler::rescale (const QSize & oldSize, const QSize & newSize) const [protected, virtual]`

Adjust the plot axes scales

Parameters:

oldSize Previous size of the canvas

newSize New size of the canvas

6.62.4.20 `QwtDoubleInterval QwtPlotRescaler::expandScale (int axis, const QSize & oldSize, const QSize & newSize) const [protected, virtual]`

Calculate the new scale interval of a plot axis

Parameters:

axis Axis index (see QwtPlot::AxisId)

oldSize Previous size of the canvas

newSize New size of the canvas

Returns:

Calculated new interval for the axis

6.62.4.21 [QwtDoubleInterval](#) **QwtPlotRescaler::syncScale** (int *axis*, const [QwtDoubleInterval](#) & *reference*, const QSize & *size*) const [protected, virtual]

Synchronize an axis scale according to the scale of the reference axis

Parameters:

axis Axis index (see QwtPlot::AxisId)

reference Interval of the reference axis

size Size of the canvas

6.62.4.22 void **QwtPlotRescaler::updateScales** ([QwtDoubleInterval](#) *intervals*[QwtPlot::axisCnt]) const [protected, virtual]

Update the axes scales

Parameters:

intervals Scale intervals

6.62.4.23 Qt::Orientation **QwtPlotRescaler::orientation** (int *axis*) const [protected]

Return orientation of an axis

Parameters:

axis Axis index (see QwtPlot::AxisId)

6.62.4.24 [QwtDoubleInterval](#) **QwtPlotRescaler::interval** (int *axis*) const [protected]

Return interval of an axis

Parameters:

axis Axis index (see QwtPlot::AxisId)

6.62.4.25 [QwtDoubleInterval](#) **QwtPlotRescaler::expandInterval** (const [QwtDoubleInterval](#) & *interval*, double *width*, ExpandingDirection *direction*) const [protected]

Expand the interval

Parameters:

interval Interval to be expanded

width Distance to be added to the interval

direction Direction of the expand operation

Returns:


Expanded interval

6.63 QwtPlotScaleItem Class Reference

A class which draws a scale inside the plot canvas.

```
#include <qwt_plot_scaleitem.h>
```

Inheritance diagram for QwtPlotScaleItem:



Public Member Functions

- [QwtPlotScaleItem](#) ([QwtScaleDraw::Alignment](#)=[QwtScaleDraw::BottomScale](#), const double pos=0.0)
- virtual [~QwtPlotScaleItem](#) ()
- virtual int [rtti](#) () const
- void [setScaleDiv](#) (const [QwtScaleDiv](#) &)
- const [QwtScaleDiv](#) & [scaleDiv](#) () const
- void [setScaleDivFromAxis](#) (bool on)
- bool [isScaleDivFromAxis](#) () const
- void [setPalette](#) (const [QPalette](#) &)
- [QPalette](#) [palette](#) () const
- void [setFont](#) (const [QFont](#) &)
- [QFont](#) [font](#) () const
- void [setScaleDraw](#) ([QwtScaleDraw](#) *)
- const [QwtScaleDraw](#) * [scaleDraw](#) () const
- [QwtScaleDraw](#) * [scaleDraw](#) ()
- void [setPosition](#) (double pos)
- double [position](#) () const
- void [setBorderDistance](#) (int numPixels)
- int [borderDistance](#) () const
- void [setAlignment](#) ([QwtScaleDraw::Alignment](#))
- virtual void [draw](#) ([QPainter](#) *p, const [QwtScaleMap](#) &xMap, const [QwtScaleMap](#) &yMap, const [QRect](#) &rect) const
- virtual void [updateScaleDiv](#) (const [QwtScaleDiv](#) &, const [QwtScaleDiv](#) &)

6.63.1 Detailed Description

A class which draws a scale inside the plot canvas.

[QwtPlotScaleItem](#) can be used to draw an axis inside the plot canvas. It might be synchronized to one of the axis of the plot, but can also display its own ticks and labels.

It is allowed to synchronize the scale item with a disabled axis. In plots with vertical and horizontal scale items, it might be necessary to remove ticks at the intersections, by overloading [updateScaleDiv\(\)](#).

The scale might be at a specific position (f.e 0.0) or it might be aligned to a canvas border.

Example

The following example shows how to replace the left axis, by a scale item at the x position 0.0.

```
QwtPlotScaleItem *scaleItem =
    new QwtPlotScaleItem(QwtScaleDraw::RightScale, 0.0);
scaleItem->setFont(plot->axisWidget(QwtPlot::yLeft)->font());
scaleItem->attach(plot);

plot->enableAxis(QwtPlot::yLeft, false);
```

6.63.2 Constructor & Destructor Documentation

6.63.2.1 `QwtPlotScaleItem::QwtPlotScaleItem (QwtScaleDraw::Alignment alignment = QwtScaleDraw::BottomScale, const double pos = 0.0) [explicit]`

Constructor for scale item at the position *pos*.

Parameters:

alignment In case of `QwtScaleDraw::BottomScale/QwtScaleDrawTopScale` the scale item is corresponding to the `xAxis()`, otherwise it corresponds to the `yAxis()`.

pos x or y position, depending on the corresponding axis.

See also:

[setPosition\(\)](#), [setAlignment\(\)](#)

6.63.2.2 `QwtPlotScaleItem::~~QwtPlotScaleItem () [virtual]`

Destructor.

6.63.3 Member Function Documentation

6.63.3.1 `int QwtPlotScaleItem::rtti () const [virtual]`

Returns:

`QwtPlotItem::Rtti_PlotScale`

Reimplemented from [QwtPlotItem](#).

6.63.3.2 `void QwtPlotScaleItem::setScaleDiv (const QwtScaleDiv & scaleDiv)`

Assign a scale division.

When assigning a `scaleDiv` the scale division won't be synchronized with the corresponding axis anymore.

Parameters:

scaleDiv Scale division

See also:

[scaleDiv\(\)](#), [setScaleDivFromAxis\(\)](#), [isScaleDivFromAxis\(\)](#)

6.63.3.3 `const QwtScaleDiv & QwtPlotScaleItem::scaleDiv () const`**Returns:**

Scale division

6.63.3.4 `void QwtPlotScaleItem::setScaleDivFromAxis (bool on)`

Enable/Disable the synchronization of the scale division with the corresponding axis.

Parameters:

on true/false

See also:

[isScaleDivFromAxis\(\)](#)

6.63.3.5 `bool QwtPlotScaleItem::isScaleDivFromAxis () const`**Returns:**

True, if the synchronization of the scale division with the corresponding axis is enabled.

See also:

[setScaleDiv\(\)](#), [setScaleDivFromAxis\(\)](#)

6.63.3.6 `void QwtPlotScaleItem::setPalette (const QPalette & palette)`

Set the palette

See also:

[QwtAbstractScaleDraw::draw\(\)](#), [palette\(\)](#)

6.63.3.7 `QPalette QwtPlotScaleItem::palette () const`**Returns:**

palette

See also:

[setPalette\(\)](#)

6.63.3.8 `void QwtPlotScaleItem::setFont (const QFont & font)`

Change the tick label font

See also:

[font\(\)](#)

6.63.3.9 QFont QwtPlotScaleItem::font () const

Returns:

tick label font

See also:

[setFont\(\)](#)

6.63.3.10 void QwtPlotScaleItem::setScaleDraw (QwtScaleDraw * scaleDraw)

Set a scale draw.

Parameters:

scaleDraw object responsible for drawing scales.

The main use case for replacing the default [QwtScaleDraw](#) is to overload [QwtAbstractScaleDraw::label](#), to replace or swallow tick labels.

See also:

[scaleDraw\(\)](#)

6.63.3.11 const QwtScaleDraw * QwtPlotScaleItem::scaleDraw () const

Returns:

Scale draw

See also:

[setScaleDraw\(\)](#)

6.63.3.12 QwtScaleDraw * QwtPlotScaleItem::scaleDraw ()

Returns:

Scale draw

See also:

[setScaleDraw\(\)](#)

6.63.3.13 void QwtPlotScaleItem::setPosition (double pos)

Change the position of the scale

The position is interpreted as y value for horizontal axes and as x value for vertical axes.

The border distance is set to -1.

Parameters:

pos New position

See also:

[position\(\)](#), [setAlignment\(\)](#)

6.63.3.14 double QwtPlotScaleItem::position () const

Returns:

Position of the scale

See also:

[setPosition\(\)](#), [setAlignment\(\)](#)

6.63.3.15 void QwtPlotScaleItem::setBorderDistance (int *distance*)

Align the scale to the canvas.

If *distance* is ≥ 0 the scale will be aligned to a border of the contents rect of the canvas. If [alignment\(\)](#) is [QwtScaleDraw::LeftScale](#), the scale will be aligned to the right border, if it is [QwtScaleDraw::TopScale](#) it will be aligned to the bottom (and vice versa),

If *distance* is < 0 the scale will be at the [position\(\)](#).

Parameters:

distance Number of pixels between the canvas border and the backbone of the scale.

See also:

[setPosition\(\)](#), [borderDistance\(\)](#)

6.63.3.16 int QwtPlotScaleItem::borderDistance () const

Returns:

Distance from a canvas border

See also:

[setBorderDistance\(\)](#), [setPosition\(\)](#)

6.63.3.17 void QwtPlotScaleItem::setAlignment (QwtScaleDraw::Alignment *alignment*)

Change the alignment of the scale

The alignment sets the orientation of the scale and the position of the ticks:

- [QwtScaleDraw::BottomScale](#): horizontal, ticks below
- [QwtScaleDraw::TopScale](#): horizontal, ticks above
- [QwtScaleDraw::LeftScale](#): vertical, ticks left
- [QwtScaleDraw::RightScale](#): vertical, ticks right

For horizontal scales the position corresponds to [QwtPlotItem::yAxis\(\)](#), otherwise to [QwtPlotItem::xAxis\(\)](#).

See also:

[scaleDraw\(\)](#), [QwtScaleDraw::alignment\(\)](#), [setPosition\(\)](#)

6.63.3.18 void QwtPlotScaleItem::draw (QPainter * *p*, const QwtScaleMap & *xMap*, const QwtScaleMap & *yMap*, const QRect & *rect*) const [virtual]

Draw the scale.

Implements [QwtPlotItem](#).

6.63.3.19 void QwtPlotScaleItem::updateScaleDiv (const QwtScaleDiv & *xScaleDiv*, const QwtScaleDiv & *yScaleDiv*) [virtual]

Update the item to changes of the axes scale division.

In case of [isScaleDivFromAxis\(\)](#), the scale draw is synchronized to the correspond axis.

Parameters:

xScaleDiv Scale division of the x-axis

yScaleDiv Scale division of the y-axis

See also:

[QwtPlot::updateAxes\(\)](#)


Reimplemented from [QwtPlotItem](#).

6.64 QwtPlotSpectrogram Class Reference

A plot item, which displays a spectrogram.

```
#include <qwt_plot_spectrogram.h>
```

Inheritance diagram for QwtPlotSpectrogram:



Public Types

- enum [DisplayMode](#) {
 - AlwaysOff**,
 - AlwaysOn**,
 - ActiveOnly**,
 - ImageMode = 1**,
 - ContourMode = 2** }

Public Member Functions

- [QwtPlotSpectrogram](#) (const QString &title=QString::null)
- virtual [~QwtPlotSpectrogram](#) ()
- void [setDisplayMode](#) (DisplayMode, bool on=true)
- bool [testDisplayMode](#) (DisplayMode) const
- void [setData](#) (const [QwtRasterData](#) &data)
- const [QwtRasterData](#) & [data](#) () const
- void [setColorMap](#) (const [QwtColorMap](#) &)
- const [QwtColorMap](#) & [colorMap](#) () const
- virtual [QwtDoubleRect](#) [boundingRect](#) () const
- virtual QSize [rasterHint](#) (const [QwtDoubleRect](#) &) const
- void [setDefaultContourPen](#) (const QPen &)
- QPen [defaultContourPen](#) () const
- virtual QPen [contourPen](#) (double level) const
- void [setConrecAttribute](#) ([QwtRasterData::ConrecAttribute](#), bool on)
- bool [testConrecAttribute](#) ([QwtRasterData::ConrecAttribute](#)) const
- void [setContourLevels](#) (const QwtValueList &)
- QwtValueList [contourLevels](#) () const
- virtual int [rtti](#) () const
- virtual void [draw](#) (QPainter *p, const [QwtScaleMap](#) &xMap, const [QwtScaleMap](#) &yMap, const QRect &rect) const

Protected Member Functions

- virtual QImage [renderImage](#) (const [QwtScaleMap](#) &xMap, const [QwtScaleMap](#) &yMap, const [QwtDoubleRect](#) &rect) const
- virtual QSize [contourRasterSize](#) (const [QwtDoubleRect](#) &, const QRect &) const
- virtual [QwtRasterData::ContourLines](#) [renderContourLines](#) (const [QwtDoubleRect](#) &rect, const QSize &raster) const
- virtual void [drawContourLines](#) (QPainter *p, const [QwtScaleMap](#) &xMap, const [QwtScaleMap](#) &yMap, const [QwtRasterData::ContourLines](#) &lines) const

6.64.1 Detailed Description

A plot item, which displays a spectrogram.

A spectrogram displays threedimensional data, where the 3rd dimension (the intensity) is displayed using colors. The colors are calculated from the values using a color map.

In ContourMode contour lines are painted for the contour levels.

See also:

[QwtRasterData](#), [QwtColorMap](#)

6.64.2 Member Enumeration Documentation**6.64.2.1 enum [QwtPlotSpectrogram::DisplayMode](#)**

The display mode controls how the raster data will be represented.

- `ImageMode`
The values are mapped to colors using a color map.
- `ContourMode`
The data is displayed using contour lines

When both modes are enabled the contour lines are painted on top of the spectrogram. The default setting enables `ImageMode`.

See also:

[setDisplayMode\(\)](#), [testDisplayMode\(\)](#)

6.64.3 Constructor & Destructor Documentation

6.64.3.1 `QwtPlotSpectrogram::QwtPlotSpectrogram (const QString & title = QString::null)` [explicit]

Sets the following item attributes:

- `QwtPlotItem::AutoScale`: true
- `QwtPlotItem::Legend`: false

The z value is initialized by 8.0.

Parameters:

title Title

See also:

[QwtPlotItem::setItemAttribute\(\)](#), [QwtPlotItem::setZ\(\)](#)

6.64.3.2 `QwtPlotSpectrogram::~~QwtPlotSpectrogram ()` [virtual]

Destructor.

6.64.4 Member Function Documentation

6.64.4.1 `void QwtPlotSpectrogram::setDisplayMode (DisplayMode mode, bool on = true)`

The display mode controls how the raster data will be represented.

Parameters:

mode Display mode

on On/Off

The default setting enables `ImageMode`.

See also:

[DisplayMode](#), [displayMode\(\)](#)

6.64.4.2 `bool QwtPlotSpectrogram::testDisplayMode (DisplayMode mode) const`

The display mode controls how the raster data will be represented.

Parameters:

mode Display mode

Returns:

true if mode is enabled

6.64.4.3 `void QwtPlotSpectrogram::setData (const QwtRasterData & data)`

Set the data to be displayed

Parameters:

data Spectrogram Data

See also:

[data\(\)](#)

6.64.4.4 `const QwtRasterData & QwtPlotSpectrogram::data () const`**Returns:**

Spectrogram data

See also:

[setData\(\)](#)

6.64.4.5 `void QwtPlotSpectrogram::setColorMap (const QwtColorMap & colorMap)`

Change the color map

Often it is useful to display the mapping between intensities and colors as an additional plot axis, showing a color bar.

Parameters:

colorMap Color Map

See also:

[colorMap\(\)](#), [QwtScaleWidget::setColorBarEnabled\(\)](#), [QwtScaleWidget::setColorMap\(\)](#)

6.64.4.6 `const QwtColorMap & QwtPlotSpectrogram::colorMap () const`**Returns:**

Color Map used for mapping the intensity values to colors

See also:

[setColorMap\(\)](#)

6.64.4.7 [QwtDoubleRect](#) `QwtPlotSpectrogram::boundingRect () const` [virtual]**Returns:**

Bounding rect of the data

See also:

[QwtRasterData::boundingRect\(\)](#)

Reimplemented from [QwtPlotItem](#).

6.64.4.8 `QSize` `QwtPlotSpectrogram::rasterHint (const QwtDoubleRect & rect) const` [virtual]

Returns the recommended raster for a given rect.

E.g. the raster hint is used to limit the resolution of the image that is rendered.

Parameters:

rect Rect for the raster hint

Returns:

[data\(\)](#).rasterHint(rect)

Reimplemented from [QwtPlotRasterItem](#).

6.64.4.9 `void` `QwtPlotSpectrogram::setDefaultContourPen (const QPen & pen)`

Set the default pen for the contour lines.

If the spectrogram has a valid default contour pen a contour line is painted using the default contour pen. Otherwise (`pen.style() == Qt::NoPen`) the pen is calculated for each contour level using [contourPen\(\)](#).

See also:

[defaultContourPen\(\)](#), [contourPen\(\)](#)

6.64.4.10 `QPen` `QwtPlotSpectrogram::defaultContourPen () const`**Returns:**

Default contour pen

See also:

[setDefaultContourPen\(\)](#)

6.64.4.11 `QPen QwtPlotSpectrogram::contourPen (double level) const` [virtual]

Calculate the pen for a contour line.

The color of the pen is the color for level calculated by the color map

Parameters:

level Contour level

Returns:

Pen for the contour line

Note:

contourPen is only used if `defaultContourPen().style() == Qt::NoPen`

See also:

[setDefaultContourPen\(\)](#), [setColorMap\(\)](#), [setContourLevels\(\)](#)

6.64.4.12 `void QwtPlotSpectrogram::setConrecAttribute (QwtRasterData::ConrecAttribute attribute, bool on)`

Modify an attribute of the CONREC algorithm, used to calculate the contour lines.

Parameters:

attribute CONREC attribute

on On/Off

See also:

[testConrecAttribute\(\)](#), [renderContourLines\(\)](#), [QwtRasterData::contourLines\(\)](#)

6.64.4.13 `bool QwtPlotSpectrogram::testConrecAttribute (QwtRasterData::ConrecAttribute attribute) const`

Test an attribute of the CONREC algorithm, used to calculate the contour lines.

Parameters:

attribute CONREC attribute

Returns:

true, is enabled

See also:

[setConrecAttribute\(\)](#), [renderContourLines\(\)](#), [QwtRasterData::contourLines\(\)](#)

6.64.4.14 void QwtPlotSpectrogram::setContourLevels (const QwtValueList & *levels*)

Set the levels of the contour lines

Parameters:

levels Values of the contour levels

See also:

[contourLevels\(\)](#), [renderContourLines\(\)](#), [QwtRasterData::contourLines\(\)](#)

Note:

[contourLevels](#) returns the same levels but sorted.

6.64.4.15 QwtValueList QwtPlotSpectrogram::contourLevels () const

Return the levels of the contour lines.

The levels are sorted in increasing order.

See also:

[contourLevels\(\)](#), [renderContourLines\(\)](#), [QwtRasterData::contourLines\(\)](#)

6.64.4.16 int QwtPlotSpectrogram::rtti () const [virtual]**Returns:**

QwtPlotItem::Rtti_PlotSpectrogram

Reimplemented from [QwtPlotItem](#).

6.64.4.17 void QwtPlotSpectrogram::draw (QPainter * *painter*, const QwtScaleMap & *xMap*, const QwtScaleMap & *yMap*, const QRect & *canvasRect*) const [virtual]

Draw the spectrogram.

Parameters:

painter Painter

xMap Maps x-values into pixel coordinates.

yMap Maps y-values into pixel coordinates.

canvasRect Contents rect of the canvas in painter coordinates

See also:

[setDisplayMode\(\)](#), [renderImage\(\)](#), [QwtPlotRasterItem::draw\(\)](#), [drawContourLines\(\)](#)

Reimplemented from [QwtPlotRasterItem](#).

6.64.4.18 QImage QwtPlotSpectrogram::renderImage (const [QwtScaleMap](#) & *xMap*, const [QwtScaleMap](#) & *yMap*, const [QwtDoubleRect](#) & *area*) const [protected, virtual]

Render an image from the data and color map.

The area is translated into a rect of the paint device. For each pixel of this rect the intensity is mapped into a color.

Parameters:

xMap X-Scale Map

yMap Y-Scale Map

area Area that should be rendered in scale coordinates.

Returns:

A QImage::Format_Indexed8 or QImage::Format_ARGB32 depending on the color map.

See also:

[QwtRasterData::intensity\(\)](#), [QwtColorMap::rgb\(\)](#), [QwtColorMap::colorIndex\(\)](#)

Implements [QwtPlotRasterItem](#).

6.64.4.19 QSize QwtPlotSpectrogram::contourRasterSize (const [QwtDoubleRect](#) & *area*, const [QRect](#) & *rect*) const [protected, virtual]

Return the raster to be used by the CONREC contour algorithm.

A larger size will improve the precision of the CONREC algorithm, but will slow down the time that is needed to calculate the lines.

The default implementation returns `rect.size() / 2` bounded to `data().rasterHint()`.

Parameters:

area Rect, where to calculate the contour lines

rect Rect in pixel coordinates, where to paint the contour lines

Returns:

Raster to be used by the CONREC contour algorithm.

Note:

The size will be bounded to `rect.size()`.

See also:

[drawContourLines\(\)](#), [QwtRasterData::contourLines\(\)](#)

6.64.4.20 QwtRasterData::ContourLines QwtPlotSpectrogram::renderContourLines (const [QwtDoubleRect](#) & *rect*, const [QSize](#) & *raster*) const [protected, virtual]

Calculate contour lines

Parameters:

rect Rectangle, where to calculate the contour lines
raster Raster, used by the CONREC algorithm

See also:

[contourLevels\(\)](#), [setConrecAttribute\(\)](#), [QwtRasterData::contourLines\(\)](#)

6.64.4.21 void `QwtPlotSpectrogram::drawContourLines` (`QPainter * painter`, const `QwtScaleMap & xMap`, const `QwtScaleMap & yMap`, const `QwtRasterData::ContourLines & contourLines`) const
 [protected, virtual]

Paint the contour lines

Parameters:

painter Painter
xMap Maps x-values into pixel coordinates.
yMap Maps y-values into pixel coordinates.
contourLines Contour lines

See also:


[renderContourLines\(\)](#), [defaultContourPen\(\)](#), [contourPen\(\)](#)

6.65 QwtPlotSvgItem Class Reference

A plot item, which displays data in Scalable Vector Graphics (SVG) format.

```
#include <qwt_plot_svgitem.h>
```

Inheritance diagram for QwtPlotSvgItem:

**Public Member Functions**

- `QwtPlotSvgItem` (const `QString &title=QString::null`)
- `QwtPlotSvgItem` (const `QwtText &title`)
- virtual `~QwtPlotSvgItem` ()
- bool `loadFile` (const `QwtDoubleRect &`, const `QString &fileName`)
- bool `loadData` (const `QwtDoubleRect &`, const `QByteArray &`)
- virtual `QwtDoubleRect boundingRect` () const
- virtual void `draw` (`QPainter *p`, const `QwtScaleMap &xMap`, const `QwtScaleMap &yMap`, const `QRect &rect`) const
- virtual int `rtti` () const

Protected Member Functions

- void `render` (QPainter *painter, const [QwtDoubleRect](#) &viewBox, const QRect &rect) const
- [QwtDoubleRect](#) `viewBox` (const [QwtDoubleRect](#) &area) const

6.65.1 Detailed Description

A plot item, which displays data in Scalable Vector Graphics (SVG) format.

SVG images are often used to display maps

6.65.2 Constructor & Destructor Documentation

6.65.2.1 `QwtPlotSvgItem::QwtPlotSvgItem (const QString & title = QString::null) [explicit]`

Constructor.

Sets the following item attributes:

- `QwtPlotItem::AutoScale`: true
- `QwtPlotItem::Legend`: false

Parameters:

title Title

6.65.2.2 `QwtPlotSvgItem::QwtPlotSvgItem (const QwtText & title) [explicit]`

Constructor.

Sets the following item attributes:

- `QwtPlotItem::AutoScale`: true
- `QwtPlotItem::Legend`: false

Parameters:

title Title

6.65.2.3 `QwtPlotSvgItem::~QwtPlotSvgItem () [virtual]`

Destructor.

6.65.3 Member Function Documentation

6.65.3.1 `bool QwtPlotSvgItem::loadFile (const QwtDoubleRect & rect, const QString & fileName)`

Load a SVG file

Parameters:

rect Bounding rectangle
fileName SVG file name

Returns:

true, if the SVG file could be loaded

6.65.3.2 `bool QwtPlotSvgItem::loadData (const QwtDoubleRect & rect, const QByteArray & data)`

Load SVG data

Parameters:

rect Bounding rectangle
data in SVG format

Returns:

true, if the SVG data could be loaded

6.65.3.3 `QwtDoubleRect QwtPlotSvgItem::boundingRect () const` [virtual]

Bounding rect of the item.

Reimplemented from [QwtPlotItem](#).

6.65.3.4 `void QwtPlotSvgItem::draw (QPainter * painter, const QwtScaleMap & xMap, const QwtScaleMap & yMap, const QRect & canvasRect) const` [virtual]

Draw the SVG item

Parameters:

painter Painter
xMap X-Scale Map
yMap Y-Scale Map
canvasRect Contents rect of the plot canvas

Implements [QwtPlotItem](#).

6.65.3.5 `int QwtPlotSvgItem::rtti () const` [virtual]**Returns:**

QwtPlotItem::Rtti_PlotSVG

Reimplemented from [QwtPlotItem](#).

6.65.3.6 `void QwtPlotSvgItem::render (QPainter * painter, const QwtDoubleRect & viewBox, const QRect & rect) const` [protected]

Render the SVG data

Parameters:

- painter* Painter
- viewBox* View Box, see QSvgRenderer::viewBox
- rect* Target rectangle on the paint device

6.65.3.7 `QwtDoubleRect QwtPlotSvgItem::viewBox (const QwtDoubleRect & rect) const` [protected]

Calculate the viewBox from an rect and boundingRect().

Parameters:

- rect* Rectangle in scale coordinates

Returns:


- viewBox View Box, see QSvgRenderer::viewBox

6.66 QwtPlotZoomer Class Reference

[QwtPlotZoomer](#) provides stacked zooming for a plot widget.

```
#include <qwt_plot_zoomer.h>
```

Inheritance diagram for QwtPlotZoomer:



Public Slots

- void [moveBy](#) (double x, double y)
- virtual void [move](#) (double x, double y)
- virtual void [zoom](#) (const QwtDoubleRect &)
- virtual void [zoom](#) (int up)

Signals

- void [zoomed](#) (const QwtDoubleRect &rect)

Public Member Functions

- [QwtPlotZoomer](#) ([QwtPlotCanvas](#) *, bool doReplot=true)
- [QwtPlotZoomer](#) (int xAxis, int yAxis, [QwtPlotCanvas](#) *, bool doReplot=true)
- [QwtPlotZoomer](#) (int xAxis, int yAxis, int selectionFlags, [DisplayMode](#) trackerMode, [QwtPlotCanvas](#) *, bool doReplot=true)
- virtual void [setZoomBase](#) (bool doReplot=true)
- virtual void [setZoomBase](#) (const [QwtDoubleRect](#) &)
- [QwtDoubleRect](#) [zoomBase](#) () const
- [QwtDoubleRect](#) [zoomRect](#) () const
- virtual void [setAxis](#) (int xAxis, int yAxis)
- void [setMaxStackDepth](#) (int)
- int [maxStackDepth](#) () const
- const [QStack](#)< [QwtDoubleRect](#) > & [zoomStack](#) () const
- void [setZoomStack](#) (const [QStack](#)< [QwtDoubleRect](#) > &, int zoomRectIndex=-1)
- uint [zoomRectIndex](#) () const
- virtual void [setSelectionFlags](#) (int)

Protected Member Functions

- virtual void [rescale](#) ()
- virtual [QwtDoubleSize](#) [minZoomSize](#) () const
- virtual void [widgetMouseEvent](#) ([QMouseEvent](#) *)
- virtual void [widgetKeyPressEvent](#) ([QKeyEvent](#) *)
- virtual void [begin](#) ()
- virtual bool [end](#) (bool ok=true)
- virtual bool [accept](#) ([QwtPolygon](#) &) const

6.66.1 Detailed Description

[QwtPlotZoomer](#) provides stacked zooming for a plot widget.

[QwtPlotZoomer](#) offers rubberband selections on the plot canvas, translating the selected rectangles into plot coordinates and adjusting the axes to them. Zooming can be repeated as often as possible, limited only by [maxStackDepth\(\)](#) or [minZoomSize\(\)](#). Each rectangle is pushed on a stack.

Zoom rectangles can be selected depending on [selectionFlags\(\)](#) using the mouse or keyboard ([QwtEventPattern](#), [QwtPickerMachine](#)). [QwtEventPattern::MouseSelect3/QwtEventPatternKeyUndo](#), or [QwtEventPattern::MouseSelect6/QwtEventPatternKeyRedo](#) walk up and down the zoom stack. [QwtEventPattern::MouseSelect2](#) or [QwtEventPattern::KeyHome](#) unzoom to the initial size.

[QwtPlotZoomer](#) is tailored for plots with one x and y axis, but it is allowed to attach a second [QwtPlotZoomer](#) for the other axes.

Note:

The realtime example includes a derived zoomer class that adds scrollbars to the plot canvas.

6.66.2 Constructor & Destructor Documentation

6.66.2.1 QwtPlotZoomer::QwtPlotZoomer (QwtPlotCanvas * canvas, bool doReplot = true) [explicit]

Create a zoomer for a plot canvas.

The zoomer is set to those x- and y-axis of the parent plot of the canvas that are enabled. If both or no x-axis are enabled, the picker is set to QwtPlot::xBottom. If both or no y-axis are enabled, it is set to QwtPlot::yLeft.

The [selectionFlags\(\)](#) are set to QwtPicker::RectSelection & QwtPicker::ClickSelection, the tracker mode to QwtPicker::ActiveOnly.

Parameters:

canvas Plot canvas to observe, also the parent object

doReplot Call replot for the attached plot before initializing the zoomer with its scales. This might be necessary, when the plot is in a state with pending scale changes.

See also:

[QwtPlot::autoReplot\(\)](#), [QwtPlot::replot\(\)](#), [setZoomBase\(\)](#)

6.66.2.2 QwtPlotZoomer::QwtPlotZoomer (int xAxis, int yAxis, QwtPlotCanvas * canvas, bool doReplot = true) [explicit]

Create a zoomer for a plot canvas.

The [selectionFlags\(\)](#) are set to QwtPicker::RectSelection & QwtPicker::ClickSelection, the tracker mode to QwtPicker::ActiveOnly.

Parameters:

xAxis X axis of the zoomer

yAxis Y axis of the zoomer

canvas Plot canvas to observe, also the parent object

doReplot Call replot for the attached plot before initializing the zoomer with its scales. This might be necessary, when the plot is in a state with pending scale changes.

See also:

[QwtPlot::autoReplot\(\)](#), [QwtPlot::replot\(\)](#), [setZoomBase\(\)](#)

6.66.2.3 QwtPlotZoomer::QwtPlotZoomer (int xAxis, int yAxis, int selectionFlags, DisplayMode trackerMode, QwtPlotCanvas * canvas, bool doReplot = true) [explicit]

Create a zoomer for a plot canvas.

Parameters:

xAxis X axis of the zoomer

yAxis Y axis of the zoomer

selectionFlags Or'd value of [QwtPicker::RectSelectionType](#) and [QwtPicker::SelectionMode](#). QwtPicker::RectSelection will be auto added.

trackerMode Tracker mode

canvas Plot canvas to observe, also the parent object

doReplot Call replot for the attached plot before initializing the zoomer with its scales. This might be necessary, when the plot is in a state with pending scale changes.

See also:

[QwtPicker](#), [QwtPicker::setSelectionFlags\(\)](#), [QwtPicker::setRubberBand\(\)](#), [QwtPicker::setTrackerMode\(\)](#)
[QwtPlot::autoReplot\(\)](#), [QwtPlot::replot\(\)](#), [setZoomBase\(\)](#)

6.66.3 Member Function Documentation

6.66.3.1 void QwtPlotZoomer::setZoomBase (bool *doReplot* = true) [virtual]

Reinitialized the zoom stack with [scaleRect\(\)](#) as base.

Parameters:

doReplot Call replot for the attached plot before initializing the zoomer with its scales. This might be necessary, when the plot is in a state with pending scale changes.

See also:

[zoomBase\(\)](#), [scaleRect\(\)](#) [QwtPlot::autoReplot\(\)](#), [QwtPlot::replot\(\)](#).

6.66.3.2 void QwtPlotZoomer::setZoomBase (const [QwtDoubleRect](#) & *base*) [virtual]

Set the initial size of the zoomer.

base is united with the current [scaleRect\(\)](#) and the zoom stack is reinitialized with it as zoom base. plot is zoomed to [scaleRect\(\)](#).

Parameters:

base Zoom base

See also:

[zoomBase\(\)](#), [scaleRect\(\)](#)

6.66.3.3 [QwtDoubleRect](#) QwtPlotZoomer::zoomBase () const

Returns:

Initial rectangle of the zoomer

See also:

[setZoomBase\(\)](#), [zoomRect\(\)](#)

6.66.3.4 [QwtDoubleRect](#) `QwtPlotZoomer::zoomRect () const`

Rectangle at the current position on the zoom stack.

See also:

[zoomRectIndex\(\)](#), [scaleRect\(\)](#).

6.66.3.5 `void QwtPlotZoomer::setAxis (int xAxis, int yAxis) [virtual]`

Reinitialize the axes, and set the zoom base to their scales.

Parameters:

xAxis X axis

yAxis Y axis

Reimplemented from [QwtPlotPicker](#).

6.66.3.6 `void QwtPlotZoomer::setMaxStackDepth (int depth)`

Limit the number of recursive zoom operations to depth.

A value of -1 set the depth to unlimited, 0 disables zooming. If the current zoom rectangle is below depth, the plot is unzoomed.

Parameters:

depth Maximum for the stack depth

See also:

[maxStackDepth\(\)](#)

Note:

depth doesn't include the zoom base, so `zoomStack().count()` might be `maxStackDepth() + 1`.

6.66.3.7 `int QwtPlotZoomer::maxStackDepth () const`

Returns:

Maximal depth of the zoom stack.

See also:

[setMaxStackDepth\(\)](#)

6.66.3.8 `const QwtZoomStack & QwtPlotZoomer::zoomStack () const`

Return the zoom stack. `zoomStack()[0]` is the zoom base, `zoomStack()[1]` the first zoomed rectangle.

See also:

[setZoomStack\(\)](#), [zoomRectIndex\(\)](#)

6.66.3.9 uint QwtPlotZoomer::zoomRectIndex () const

Returns:

Index of current position of zoom stack.

6.66.3.10 void QwtPlotZoomer::setSelectionFlags (int *flags*) [virtual]

Set the selection flags

Parameters:

flags Or'd value of [QwtPicker::RectSelectionType](#) and [QwtPicker::SelectionMode](#). The default value is [QwtPicker::RectSelection](#) & [QwtPicker::ClickSelection](#).

See also:

[selectionFlags\(\)](#), [SelectionType](#), [RectSelectionType](#), [SelectionMode](#)

Note:

[QwtPicker::RectSelection](#) will be auto added.

Reimplemented from [QwtPicker](#).

6.66.3.11 void QwtPlotZoomer::moveBy (double *dx*, double *dy*) [slot]

Move the current zoom rectangle.

Parameters:

dx X offset

dy Y offset

Note:

The changed rectangle is limited by the zoom base

6.66.3.12 void QwtPlotZoomer::move (double *x*, double *y*) [virtual, slot]

Move the the current zoom rectangle.

Parameters:

x X value

y Y value

See also:

[QwtDoubleRect::move\(\)](#)

Note:

The changed rectangle is limited by the zoom base

6.66.3.13 void QwtPlotZoomer::zoom (const QwtDoubleRect & rect) [virtual, slot]

Zoom in.

Clears all rectangles above the current position of the zoom stack and pushes the intersection of zoomRect() and the normalized rect on it.

Note:

If the maximal stack depth is reached, zoom is ignored.
The zoomed signal is emitted.

6.66.3.14 void QwtPlotZoomer::zoom (int offset) [virtual, slot]

Zoom in or out.

Activate a rectangle on the zoom stack with an offset relative to the current position. Negative values of offset will zoom out, positive zoom in. A value of 0 zooms out to the zoom base.

Parameters:

offset Offset relative to the current position of the zoom stack.

Note:

The zoomed signal is emitted.

See also:

[zoomRectIndex\(\)](#)

6.66.3.15 void QwtPlotZoomer::zoomed (const QwtDoubleRect & rect) [signal]

A signal emitting the zoomRect(), when the plot has been zoomed in or out.

Parameters:

rect Current zoom rectangle.

6.66.3.16 void QwtPlotZoomer::rescale () [protected, virtual]

Adjust the observed plot to zoomRect()

Note:

Initiates QwtPlot::replot

6.66.3.17 QwtDoubleSize QwtPlotZoomer::minZoomSize () const [protected, virtual]

Limit zooming by a minimum rectangle.

Returns:

[zoomBase\(\).width\(\)](#) / 10e4, [zoomBase\(\).height\(\)](#) / 10e4

6.66.3.18 void QwtPlotZoomer::widgetMouseReleaseEvent (QMouseEvent * *me*) [protected, virtual]

Qt::MidButton zooms out one position on the zoom stack, Qt::RightButton to the zoom base.

Changes the current position on the stack, but doesn't pop any rectangle.

Note:

The mouse events can be changed, using [QwtEventPattern::setMousePattern](#): 2, 1

Reimplemented from [QwtPicker](#).

6.66.3.19 void QwtPlotZoomer::widgetKeyPressEvent (QKeyEvent * *ke*) [protected, virtual]

Qt::Key_Plus zooms out, Qt::Key_Minus zooms in one position on the zoom stack, Qt::Key_Escape zooms out to the zoom base.

Changes the current position on the stack, but doesn't pop any rectangle.

Note:

The keys codes can be changed, using [QwtEventPattern::setKeyPattern](#): 3, 4, 5

Reimplemented from [QwtPicker](#).

6.66.3.20 void QwtPlotZoomer::begin () [protected, virtual]

Rejects selections, when the stack depth is too deep, or the zoomed rectangle is [minZoomSize\(\)](#).

See also:

[minZoomSize\(\)](#), [maxStackDepth\(\)](#)

Reimplemented from [QwtPicker](#).

6.66.3.21 bool QwtPlotZoomer::end (bool *ok* = true) [protected, virtual]

Expand the selected rectangle to [minZoomSize\(\)](#) and zoom in if accepted.

See also:

[accept\(\)](#), [minZoomSize\(\)](#)

Reimplemented from [QwtPlotPicker](#).

6.66.3.22 bool QwtPlotZoomer::accept (QwtPolygon & *pa*) const [protected, virtual]

Check and correct a selected rectangle.

Reject rectangles with a height or width < 2, otherwise expand the selected rectangle to a minimum size of 11x11 and accept it.

Returns:

true if rect is accepted, or has been changed to a accepted rectangle.


Reimplemented from [QwtPicker](#).

6.67 QwtPolygonFData Class Reference

Data class containing a single `QwtArray<QwtDoublePoint>` object.

```
#include <qwt_data.h>
```

Inheritance diagram for QwtPolygonFData:



Public Member Functions

- [QwtPolygonFData](#) (const `QPolygonF` &)
- [QwtPolygonFData](#) & `operator=` (const [QwtPolygonFData](#) &)
- virtual `QwtData * copy` () const
- virtual `size_t size` () const
- virtual `double x` (size_t i) const
- virtual `double y` (size_t i) const
- const `QPolygonF` & `data` () const

6.67.1 Detailed Description

Data class containing a single `QwtArray<QwtDoublePoint>` object.

6.67.2 Constructor & Destructor Documentation

6.67.2.1 `QwtPolygonFData::QwtPolygonFData` (const `QPolygonF` & *polygon*)

Constructor

Parameters:

polygon Polygon data

See also:

[QwtPlotCurve::setData\(\)](#)

6.67.3 Member Function Documentation

6.67.3.1 `QwtPolygonFData` & `QwtPolygonFData::operator=` (const `QwtPolygonFData` &)

Assignment.

6.67.3.2 `QwtData * QwtPolygonFData::copy` () const [virtual]

Returns:

Pointer to a copy (virtual copy constructor)

Implements [QwtData](#).

6.67.3.3 `size_t QwtPolygonFData::size () const` [virtual]**Returns:**

Size of the data set

Implements [QwtData](#).**6.67.3.4** `double QwtPolygonFData::x (size_t i) const` [virtual]

Return the x value of data point i

Parameters:*i* Index**Returns:**

x X value of data point i

Implements [QwtData](#).**6.67.3.5** `double QwtPolygonFData::y (size_t i) const` [virtual]

Return the y value of data point i

Parameters:*i* Index**Returns:**


y Y value of data point i

Implements [QwtData](#).**6.67.3.6** `const QPolygonF & QwtPolygonFData::data () const`**Returns:**

Point array

6.68 QwtRasterData Class Reference[QwtRasterData](#) defines an interface to any type of raster data.

```
#include <qwt_raster_data.h>
```

Inheritance diagram for [QwtRasterData](#):

Public Types

- enum [ConrecAttribute](#) {
IgnoreAllVerticesOnLevel = 1,
IgnoreOutOfRange = 2 }
- typedef QMap< double, QPolygonF > **ContourLines**

Public Member Functions

- [QwtRasterData](#) ()
- [QwtRasterData](#) (const [QwtDoubleRect](#) &)
- virtual [~QwtRasterData](#) ()
- virtual [QwtRasterData](#) * *copy* () const=0
- virtual void *setBoundingRect* (const [QwtDoubleRect](#) &)
- [QwtDoubleRect](#) *boundingRect* () const
- virtual QSize *rasterHint* (const [QwtDoubleRect](#) &) const
- virtual void *initRaster* (const [QwtDoubleRect](#) &, const QSize &raster)
- virtual void *discardRaster* ()
- virtual double *value* (double x, double y) const=0
- virtual [QwtDoubleInterval](#) *range* () const=0
- virtual ContourLines *contourLines* (const [QwtDoubleRect](#) &rect, const QSize &raster, const QList< double > &levels, int flags) const

6.68.1 Detailed Description

[QwtRasterData](#) defines an interface to any type of raster data.

[QwtRasterData](#) is an abstract interface, that is used by [QwtPlotRasterItem](#) to find the values at the pixels of its raster.

Often a raster item is used to display values from a matrix. Then the derived raster data class needs to implement some sort of resampling, that maps the raster of the matrix into the requested raster of the raster item (depending on resolution and scales of the canvas).

6.68.2 Member Enumeration Documentation

6.68.2.1 enum [QwtRasterData::ConrecAttribute](#)

Attribute to modify the contour algorithm.

6.68.3 Constructor & Destructor Documentation

6.68.3.1 [QwtRasterData::QwtRasterData](#) ()

Constructor.

6.68.3.2 [QwtRasterData::QwtRasterData](#) (const [QwtDoubleRect](#) & *boundingRect*)

Constructor

Parameters:

boundingRect Bounding rectangle

See also:

[setBoundingRect\(\)](#)

6.68.3.3 QwtRasterData::~~QwtRasterData () [virtual]

Destructor.

6.68.4 Member Function Documentation

6.68.4.1 virtual QwtRasterData* QwtRasterData::copy () const [pure virtual]

Clone the data.

6.68.4.2 void QwtRasterData::setBoundingRect (const QwtDoubleRect & boundingRect) [virtual]

Set the bounding rect (== area, un plot coordinates)

Parameters:

boundingRect Bounding rectangle

See also:

[boundingRect\(\)](#)

6.68.4.3 QwtDoubleRect QwtRasterData::boundingRect () const

Returns:

Bounding rectangle

See also:

[boundingRect\(\)](#)

6.68.4.4 QSize QwtRasterData::rasterHint (const QwtDoubleRect &) const [virtual]

Find the raster of the data for an area.

The resolution is the number of horizontal and vertical pixels that the data can return for an area. An invalid resolution indicates that the data can return values for any detail level.

The resolution will limit the size of the image that is rendered from the data. F.e. this might be important when printing a spectrogram to a A0 printer with 600 dpi.

The default implementation returns an invalid resolution (size)

Parameters:

rect In most implementations the resolution of the data doesn't depend on the requested rectangle.

Returns:

Resolution, as number of horizontal and vertical pixels

6.68.4.5 `void QwtRasterData::initRaster (const QwtDoubleRect &, const QSize & raster)` [virtual]

Initialize a raster.

Before the composition of an image `QwtPlotSpectrogram` calls `initRaster`, announcing the area and its resolution that will be requested.

The default implementation does nothing, but for data sets that are stored in files, it might be good idea to reimplement `initRaster`, where the data is resampled and loaded into memory.

Parameters:

rect Area of the raster

raster Number of horizontal and vertical pixels

See also:

[initRaster\(\), value\(\)](#)

6.68.4.6 `void QwtRasterData::discardRaster ()` [virtual]

Discard a raster.

After the composition of an image `QwtPlotSpectrogram` calls `discardRaster()`.

The default implementation does nothing, but if data has been loaded in `initRaster()`, it could be deleted now.

See also:

[initRaster\(\), value\(\)](#)

6.68.4.7 `virtual double QwtRasterData::value (double x, double y) const` [pure virtual]

Returns:

the value at a raster position

Parameters:

x X value in plot coordinates

y Y value in plot coordinates

6.68.4.8 `virtual QwtDoubleInterval QwtRasterData::range () const` [pure virtual]

Returns:

the range of the values

6.68.4.9 `QwtRasterData::ContourLines QwtRasterData::contourLines (const QwtDoubleRect & rect, const QSize & raster, const QList< double > & levels, int flags) const` [virtual]

Calculate contour lines


An adaptation of CONREC, a simple contouring algorithm. <http://local.wasp.uwa.edu.au/~pbourke/papers/c>

6.69 QwtRichTextEngine Class Reference

A text engine for Qt rich texts.

```
#include <qwt_text_engine.h>
```

Inheritance diagram for QwtRichTextEngine:



Public Member Functions

- [QwtRichTextEngine \(\)](#)
- virtual int [heightForWidth](#) (const QFont &font, int flags, const QString &text, int width) const
- virtual QSize [textSize](#) (const QFont &font, int flags, const QString &text) const
- virtual void [draw](#) (QPainter *painter, const QRect &rect, int flags, const QString &text) const
- virtual bool [mightRender](#) (const QString &) const
- virtual void [textMargins](#) (const QFont &, const QString &, int &left, int &right, int &top, int &bottom) const

6.69.1 Detailed Description

A text engine for Qt rich texts.

[QwtRichTextEngine](#) renders Qt rich texts using the classes of the Scribe framework of Qt.

6.69.2 Constructor & Destructor Documentation

6.69.2.1 QwtRichTextEngine::QwtRichTextEngine ()

Constructor.

6.69.3 Member Function Documentation

6.69.3.1 int QwtRichTextEngine::heightForWidth (const QFont & font, int flags, const QString & text, int width) const [virtual]

Find the height for a given width

Parameters:

font Font of the text

flags Bitwise OR of the flags used like in QPainter::drawText

text Text to be rendered

width Width

Returns:

Calculated height

Implements [QwtTextEngine](#).

6.69.3.2 `QSize QwtRichTextEngine::textSize (const QFont & font, int flags, const QString & text) const` [virtual]

Returns the size, that is needed to render text

Parameters:

font Font of the text
flags Bitwise OR of the flags used like in QPainter::drawText
text Text to be rendered

Returns:

Caluclated size

Implements [QwtTextEngine](#).

6.69.3.3 `void QwtRichTextEngine::draw (QPainter * painter, const QRect & rect, int flags, const QString & text) const` [virtual]

Draw the text in a clipping rectangle

Parameters:

painter Painter
rect Clipping rectangle
flags Bitwise OR of the flags like in for QPainter::drawText
text Text to be rendered

Implements [QwtTextEngine](#).

6.69.3.4 `bool QwtRichTextEngine::mightRender (const QString & text) const` [virtual]

Test if a string can be rendered by this text engine

Parameters:

text Text to be tested

Returns:

QStyleSheet::mightBeRichText(text);

Implements [QwtTextEngine](#).

6.69.3.5 `void QwtRichTextEngine::textMargins (const QFont &, const QString &, int & left, int & right, int & top, int & bottom) const` [virtual]

Return margins around the texts

Parameters:

left Return 0
right Return 0
top Return 0
bottom Return 0


Implements [QwtTextEngine](#).

6.70 QwtRoundScaleDraw Class Reference

A class for drawing round scales.

```
#include <qwt_round_scale_draw.h>
```

Inheritance diagram for QwtRoundScaleDraw:



Public Member Functions

- [QwtRoundScaleDraw](#) ()
- [QwtRoundScaleDraw](#) (const [QwtRoundScaleDraw](#) &)
- virtual [~QwtRoundScaleDraw](#) ()
- [QwtRoundScaleDraw](#) & [operator=](#) (const [QwtRoundScaleDraw](#) &other)
- void [setRadius](#) (int radius)
- int [radius](#) () const
- void [moveCenter](#) (int x, int y)
- void [moveCenter](#) (const [QPoint](#) &)
- [QPoint](#) [center](#) () const
- void [setAngleRange](#) (double angle1, double angle2)
- virtual int [extent](#) (const [QPen](#) &, const [QFont](#) &) const

Protected Member Functions

- virtual void [drawTick](#) ([QPainter](#) *p, double val, int len) const
- virtual void [drawBackbone](#) ([QPainter](#) *p) const
- virtual void [drawLabel](#) ([QPainter](#) *p, double val) const

6.70.1 Detailed Description

A class for drawing round scales.

[QwtRoundScaleDraw](#) can be used to draw round scales. The circle segment can be adjusted by [QwtRoundScaleDraw::setAngleRange\(\)](#). The geometry of the scale can be specified with [QwtRoundScaleDraw::moveCenter\(\)](#) and [QwtRoundScaleDraw::setRadius\(\)](#).

After a scale division has been specified as a [QwtScaleDiv](#) object using [QwtAbstractScaleDraw::setScaleDiv\(const QwtScaleDiv &s\)](#), the scale can be drawn with the [QwtAbstractScaleDraw::draw\(\)](#) member.

6.70.2 Constructor & Destructor Documentation

6.70.2.1 QwtRoundScaleDraw::QwtRoundScaleDraw ()

Constructor.

The range of the scale is initialized to [0, 100], The center is set to (50, 50) with a radius of 50. The angle range is set to [-135, 135].

6.70.2.2 `QwtRoundScaleDraw::QwtRoundScaleDraw (const QwtRoundScaleDraw &)`

Copy constructor.

6.70.2.3 `QwtRoundScaleDraw::~~QwtRoundScaleDraw ()` [virtual]

Destructor.

6.70.3 Member Function Documentation**6.70.3.1** `QwtRoundScaleDraw & QwtRoundScaleDraw::operator= (const QwtRoundScaleDraw & other)`

Assignment operator.

6.70.3.2 `void QwtRoundScaleDraw::setRadius (int radius)`

Change of radius the scale

Radius is the radius of the backbone without ticks and labels.

Parameters:

radius New Radius

See also:

[moveCenter\(\)](#)

6.70.3.3 `int QwtRoundScaleDraw::radius () const`

Get the radius

Radius is the radius of the backbone without ticks and labels.

See also:

[setRadius\(\)](#), [extent\(\)](#)

6.70.3.4 `void QwtRoundScaleDraw::moveCenter (int x, int y)` [inline]

Move the center of the scale draw, leaving the radius unchanged.

6.70.3.5 `void QwtRoundScaleDraw::moveCenter (const QPoint & center)`

Move the center of the scale draw, leaving the radius unchanged

Parameters:

center New center

See also:

[setRadius\(\)](#)

6.70.3.6 QPoint QwtRoundScaleDraw::center () const

Get the center of the scale.

6.70.3.7 void QwtRoundScaleDraw::setAngleRange (double *angle1*, double *angle2*)

Adjust the baseline circle segment for round scales.

The baseline will be drawn from $\min(\text{angle1}, \text{angle2})$ to $\max(\text{angle1}, \text{angle2})$. The default setting is [-135, 135]. An angle of 0 degrees corresponds to the 12 o'clock position, and positive angles count in a clockwise direction.

Parameters:

angle1

angle2 boundaries of the angle interval in degrees.

Warning:

- The angle range is limited to [-360, 360] degrees. Angles exceeding this range will be clipped.
- For angles more than 359 degrees above or below $\min(\text{angle1}, \text{angle2})$, scale marks will not be drawn.
- If you need a counterclockwise scale, use `QwtScaleDiv::setRange`

6.70.3.8 int QwtRoundScaleDraw::extent (const QPen & *pen*, const QFont & *font*) const [virtual]

Calculate the extent of the scale

The extent is the distance between the baseline to the outermost pixel of the scale draw. `radius() + extent()` is an upper limit for the radius of the bounding circle.

Parameters:

pen Pen that is used for painting backbone and ticks

font Font used for painting the labels

See also:

[setMinimumExtent\(\)](#), [minimumExtent\(\)](#)

Warning:

The implemented algo is not too smart and calculates only an upper limit, that might be a few pixels too large

Implements [QwtAbstractScaleDraw](#).

6.70.3.9 void QwtRoundScaleDraw::drawTick (QPainter * *painter*, double *value*, int *len*) const [protected, virtual]

Draw a tick

Parameters:

painter Painter

value Value of the tick

len Length of the tick

See also:

[drawBackbone\(\)](#), [drawLabel\(\)](#)

Implements [QwtAbstractScaleDraw](#).

6.70.3.10 `void QwtRoundScaleDraw::drawBackbone (QPainter * painter) const` [protected, virtual]

Draws the baseline of the scale

Parameters:

painter Painter

See also:

[drawTick\(\)](#), [drawLabel\(\)](#)

Implements [QwtAbstractScaleDraw](#).

6.70.3.11 `void QwtRoundScaleDraw::drawLabel (QPainter * painter, double value) const` [protected, virtual]

Draws the label for a major scale tick

Parameters:

painter Painter

value Value

See also:

[drawTick\(\)](#), [drawBackbone\(\)](#)

Implements [QwtAbstractScaleDraw](#).

6.71 QwtScaleArithmetic Class Reference

Arithmetic including a tolerance.

```
#include <qwt_scale_engine.h>
```

Static Public Member Functions

- static int [compareEps](#) (double value1, double value2, double intervalSize)
- static double [ceilEps](#) (double value, double intervalSize)
- static double [floorEps](#) (double value, double intervalSize)
- static double [divideEps](#) (double interval, double steps)
- static double [ceil125](#) (double x)
- static double [floor125](#) (double x)

6.71.1 Detailed Description

Arithmetic including a tolerance.

6.71.2 Member Function Documentation

6.71.2.1 `int QwtScaleArithmetic::compareEps (double value1, double value2, double intervalSize)` `[static]`

Compare 2 values, relative to an interval.

Values are "equal", when : $\cdot value2 - value1 \leq \text{abs}(intervalSize * 10e^{-6})$

Parameters:

value1 First value to compare
value2 Second value to compare
intervalSize interval size

Returns:

0: if equal, -1: if $value2 > value1$, 1: if $value1 > value2$

6.71.2.2 `double QwtScaleArithmetic::ceilEps (double value, double intervalSize)` `[static]`

Ceil a value, relative to an interval

Parameters:

value Value to ceil
intervalSize Interval size

See also:

[floorEps\(\)](#)

6.71.2.3 `double QwtScaleArithmetic::floorEps (double value, double intervalSize)` `[static]`

Floor a value, relative to an interval

Parameters:

value Value to floor
intervalSize Interval size

See also:

[floorEps\(\)](#)

6.71.2.4 `double QwtScaleArithmetic::divideEps (double intervalSize, double numSteps)`
[static]

Divide an interval into steps.

$$stepSize = (intervalSize - intervalSize * 10e^{-6}) / numSteps$$

Parameters:

intervalSize Interval size
numSteps Number of steps

Returns:

Step size

6.71.2.5 `double QwtScaleArithmetic::ceil125 (double x)` [static]

Find the smallest value out of $\{1,2,5\} * 10^n$ with an integer number n which is greater than or equal to x

Parameters:

x Input value

6.71.2.6 `double QwtScaleArithmetic::floor125 (double x)` [static]

Find the largest value out of $\{1,2,5\} * 10^n$ with an integer number n which is smaller than or equal to x .

Parameters:

x Input value

6.72 QwtScaleDiv Class Reference

A class representing a scale division.

```
#include <qwt_scale_div.h>
```

Public Types

- enum `TickType` {
 NoTick = -1,
 MinorTick,
 MediumTick,
 MajorTick,
 NTickTypes }

Public Member Functions

- [QwtScaleDiv](#) ()
- [QwtScaleDiv](#) (const [QwtDoubleInterval](#) &, [QwtValueList](#)[NTickTypes])
- [QwtScaleDiv](#) (double lowerBound, double upperBound, [QwtValueList](#)[NTickTypes])
- int [operator==](#) (const [QwtScaleDiv](#) &s) const
- int [operator!=](#) (const [QwtScaleDiv](#) &s) const
- void [setInterval](#) (double lowerBound, double upperBound)
- void [setInterval](#) (const [QwtDoubleInterval](#) &)
- [QwtDoubleInterval](#) [interval](#) () const
- double [lowerBound](#) () const
- double [upperBound](#) () const
- double [range](#) () const
- bool [contains](#) (double v) const
- void [setTicks](#) (int type, const [QwtValueList](#) &)
- const [QwtValueList](#) & [ticks](#) (int type) const
- void [invalidate](#) ()
- bool [isValid](#) () const
- void [invert](#) ()

6.72.1 Detailed Description

A class representing a scale division.

A scale division consists of its limits and 3 list of tick values qualified as major, medium and minor ticks.

In most cases scale divisions are calculated by a [QwtScaleEngine](#).

See also:

[subDivideInto\(\)](#), [subDivide\(\)](#)

6.72.2 Member Enumeration Documentation**6.72.2.1 enum [QwtScaleDiv::TickType](#)**

Scale tick types.

6.72.3 Constructor & Destructor Documentation**6.72.3.1 [QwtScaleDiv::QwtScaleDiv](#) ()** [explicit]

Construct an invalid [QwtScaleDiv](#) instance.

6.72.3.2 [QwtScaleDiv::QwtScaleDiv](#) (const [QwtDoubleInterval](#) & *interval*, [QwtValueList](#) *ticks*[NTickTypes]) [explicit]

Construct [QwtScaleDiv](#) instance.

Parameters:

interval Interval

ticks List of major, medium and minor ticks

6.72.3.3 QwtScaleDiv::QwtScaleDiv (double *lowerBound*, double *upperBound*, QwtValueList *ticks*[NTickTypes]) [explicit]

Construct [QwtScaleDiv](#) instance.

Parameters:

lowerBound First interval limit
upperBound Second interval limit
ticks List of major, medium and minor ticks

6.72.4 Member Function Documentation

6.72.4.1 int QwtScaleDiv::operator==(const [QwtScaleDiv](#) & *other*) const

Equality operator.

Returns:

true if this instance is equal to other

6.72.4.2 int QwtScaleDiv::operator!=(const [QwtScaleDiv](#) & *s*) const

Inequality.

Returns:

true if this instance is not equal to *s*

6.72.4.3 void QwtScaleDiv::setInterval (double *lowerBound*, double *upperBound*) [inline]

Change the interval

Parameters:

lowerBound lower bound
upperBound upper bound

6.72.4.4 void QwtScaleDiv::setInterval (const [QwtDoubleInterval](#) & *interval*)

Change the interval

Parameters:

interval Interval

6.72.4.5 [QwtDoubleInterval](#) QwtScaleDiv::interval () const [inline]

Returns:

lowerBound -> upperBound

6.72.4.6 `double QwtScaleDiv::lowerBound () const` `[inline]`**Returns:**

lower bound

See also:

[upperBound\(\)](#)

6.72.4.7 `double QwtScaleDiv::upperBound () const` `[inline]`**Returns:**

upper bound

See also:

[lowerBound\(\)](#)

6.72.4.8 `double QwtScaleDiv::range () const` `[inline]`**Returns:**

[upperBound\(\)](#) - [lowerBound\(\)](#)

6.72.4.9 `bool QwtScaleDiv::contains (double value) const`

Return if a value is between [lowerBound\(\)](#) and [upperBound\(\)](#)

Parameters:

value Value

Returns:

true/false

6.72.4.10 `void QwtScaleDiv::setTicks (int type, const QwtValueList & ticks)`

Assign ticks

Parameters:

type MinorTick, MediumTick or MajorTick

ticks Values of the tick positions

6.72.4.11 `const QwtValueList & QwtScaleDiv::ticks (int type) const`

Return a list of ticks

Parameters:

type MinorTick, MediumTick or MajorTick

6.72.4.12 void QwtScaleDiv::invalidate ()

Invalidate the scale division.

6.72.4.13 bool QwtScaleDiv::isValid () const

Check if the scale division is valid.

6.72.4.14 void QwtScaleDiv::invert ()


Invert the scale division.

6.73 QwtScaleDraw Class Reference

A class for drawing scales.

```
#include <qwt_scale_draw.h>
```

Inheritance diagram for QwtScaleDraw:

**Public Types**

- enum [Alignment](#) {
BottomScale,
TopScale,
LeftScale,
RightScale }

Public Member Functions

- [QwtScaleDraw](#) ()
- [QwtScaleDraw](#) (const [QwtScaleDraw](#) &)
- virtual [~QwtScaleDraw](#) ()
- [QwtScaleDraw](#) & [operator=](#) (const [QwtScaleDraw](#) &other)
- void [getBorderDistHint](#) (const QFont &, int &start, int &end) const
- int [minLabelDist](#) (const QFont &) const
- int [minLength](#) (const QPen &, const QFont &) const
- virtual int [extent](#) (const QPen &, const QFont &) const
- void [move](#) (int x, int y)
- void [move](#) (const QPoint &)
- void [setLength](#) (int length)
- [Alignment](#) [alignment](#) () const
- void [setAlignment](#) ([Alignment](#))
- Qt::Orientation [orientation](#) () const
- QPoint [pos](#) () const

- int [length](#) () const
- void [setLabelAlignment](#) (Qt::Alignment)
- Qt::Alignment [labelAlignment](#) () const
- void [setLabelRotation](#) (double rotation)
- double [labelRotation](#) () const
- int [maxLabelHeight](#) (const QFont &) const
- int [maxLabelWidth](#) (const QFont &) const
- QPoint [labelPosition](#) (double val) const
- QRect [labelRect](#) (const QFont &, double val) const
- QSize [labelSize](#) (const QFont &, double val) const
- QRect [boundingLabelRect](#) (const QFont &, double val) const

Protected Member Functions

- QMatrix [labelMatrix](#) (const QPoint &, const QSize &) const
- virtual void [drawTick](#) (QPainter *p, double val, int len) const
- virtual void [drawBackbone](#) (QPainter *p) const
- virtual void [drawLabel](#) (QPainter *p, double val) const

6.73.1 Detailed Description

A class for drawing scales.

[QwtScaleDraw](#) can be used to draw linear or logarithmic scales. A scale has a position, an alignment and a length, which can be specified . The labels can be rotated and aligned to the ticks using [setLabelRotation\(\)](#) and [setLabelAlignment\(\)](#).

After a scale division has been specified as a [QwtScaleDiv](#) object using [QwtAbstractScaleDraw::setScaleDiv\(const QwtScaleDiv &s\)](#), the scale can be drawn with the [QwtAbstractScaleDraw::draw\(\)](#) member.

6.73.2 Member Enumeration Documentation

6.73.2.1 enum [QwtScaleDraw::Alignment](#)

Alignment of the scale draw

See also:

[setAlignment\(\)](#), [alignment\(\)](#)

6.73.3 Constructor & Destructor Documentation

6.73.3.1 [QwtScaleDraw::QwtScaleDraw \(\)](#)

Constructor.

The range of the scale is initialized to [0, 100], The position is at (0, 0) with a length of 100. The orientation is [QwtAbstractScaleDraw::Bottom](#).

6.73.3.2 [QwtScaleDraw::QwtScaleDraw \(const \[QwtScaleDraw\]\(#\) &\)](#)

Copy constructor.

6.73.3.3 QwtScaleDraw::~~QwtScaleDraw () [virtual]

Destructor.

6.73.4 Member Function Documentation

6.73.4.1 QwtScaleDraw & QwtScaleDraw::operator= (const QwtScaleDraw & other)

Assignment operator.

6.73.4.2 void QwtScaleDraw::getBorderDistHint (const QFont & font, int & start, int & end) const

Determine the minimum border distance.

This member function returns the minimum space needed to draw the mark labels at the scale's endpoints.

Parameters:

font Font
start Start border distance
end End border distance

6.73.4.3 int QwtScaleDraw::minLabelDist (const QFont & font) const

Determine the minimum distance between two labels, that is necessary that the texts don't overlap.

Parameters:

font Font

Returns:

The maximum width of a label

See also:

[getBorderDistHint\(\)](#)

6.73.4.4 int QwtScaleDraw::minLength (const QPen & pen, const QFont & font) const

Calculate the minimum length that is needed to draw the scale

Parameters:

pen Pen that is used for painting backbone and ticks
font Font used for painting the labels

See also:

[extent\(\)](#)

6.73.4.5 `int QwtScaleDraw::extent (const QPen & pen, const QFont & font) const` [virtual]

Calculate the width/height that is needed for a vertical/horizontal scale.

The extent is calculated from the pen width of the backbone, the major tick length, the spacing and the maximum width/height of the labels.

Parameters:

pen Pen that is used for painting backbone and ticks

font Font used for painting the labels

See also:

[minLength\(\)](#)

Implements [QwtAbstractScaleDraw](#).

6.73.4.6 `void QwtScaleDraw::move (int x, int y)` [inline]

Move the position of the scale

See also:

[move\(const QPoint &\)](#)

6.73.4.7 `void QwtScaleDraw::move (const QPoint & pos)`

Move the position of the scale.

The meaning of the parameter *pos* depends on the alignment:

QwtScaleDraw::LeftScale The origin is the topmost point of the backbone. The backbone is a vertical line. Scale marks and labels are drawn at the left of the backbone.

QwtScaleDraw::RightScale The origin is the topmost point of the backbone. The backbone is a vertical line. Scale marks and labels are drawn at the right of the backbone.

QwtScaleDraw::TopScale The origin is the leftmost point of the backbone. The backbone is a horizontal line. Scale marks and labels are drawn above the backbone.

QwtScaleDraw::BottomScale The origin is the leftmost point of the backbone. The backbone is a horizontal line. Scale marks and labels are drawn below the backbone.

Parameters:

pos Origin of the scale

See also:

[pos\(\)](#), [setLength\(\)](#)

6.73.4.8 void QwtScaleDraw::setLength (int *length*)

Set the length of the backbone.

The length doesn't include the space needed for overlapping labels.

See also:

[move\(\)](#), [minLabelDist\(\)](#)

6.73.4.9 QwtScaleDraw::Alignment QwtScaleDraw::alignment () const

Return alignment of the scale

See also:

[setAlignment\(\)](#)

6.73.4.10 void QwtScaleDraw::setAlignment (Alignment *align*)

Set the alignment of the scale

The default alignment is QwtScaleDraw::BottomScale

See also:

[alignment\(\)](#)

6.73.4.11 Qt::Orientation QwtScaleDraw::orientation () const

Return the orientation

TopScale, BottomScale are horizontal (Qt::Horizontal) scales, LeftScale, RightScale are vertical (Qt::Vertical) scales.

See also:

[alignment\(\)](#)

6.73.4.12 QPoint QwtScaleDraw::pos () const

Returns:

Origin of the scale

See also:

[move\(\)](#), [length\(\)](#)

6.73.4.13 int QwtScaleDraw::length () const

Returns:

the length of the backbone

See also:

[setLength\(\)](#), [pos\(\)](#)

6.73.4.14 void QwtScaleDraw::setLabelAlignment (Qt::Alignment alignment)

Change the label flags.

Labels are aligned to the point ticklength + spacing away from the backbone.

The alignment is relative to the orientation of the label text. In case of an flags of 0 the label will be aligned depending on the orientation of the scale:

QwtScaleDraw::TopScale: Qt::AlignHCenter | Qt::AlignTop

QwtScaleDraw::BottomScale: Qt::AlignHCenter | Qt::AlignBottom

QwtScaleDraw::LeftScale: Qt::AlignLeft | Qt::AlignVCenter

QwtScaleDraw::RightScale: Qt::AlignRight | Qt::AlignVCenter

Changing the alignment is often necessary for rotated labels.

Parameters:

alignment Or'd Qt::AlignmentFlags <see qnamespace.h>

See also:

[setLabelRotation\(\)](#), [labelRotation\(\)](#), [labelAlignment\(\)](#)

Warning:

The various alignments might be confusing. The alignment of the label is not the alignment of the scale and is not the alignment of the flags (QwtText::flags()) returned from [QwtAbstractScaleDraw::label\(\)](#).

6.73.4.15 Qt::Alignment QwtScaleDraw::labelAlignment () const**Returns:**

the label flags

See also:

[setLabelAlignment\(\)](#), [labelRotation\(\)](#)

6.73.4.16 void QwtScaleDraw::setLabelRotation (double rotation)

Rotate all labels.

When changing the rotation, it might be necessary to adjust the label flags too. Finding a useful combination is often the result of try and error.

Parameters:

rotation Angle in degrees. When changing the label rotation, the label flags often needs to be adjusted too.

See also:

[setLabelAlignment\(\)](#), [labelRotation\(\)](#), [labelAlignment\(\)](#).

6.73.4.17 double QwtScaleDraw::labelRotation () const**Returns:**

the label rotation

See also:

[setLabelRotation\(\)](#), [labelAlignment\(\)](#)

6.73.4.18 int QwtScaleDraw::maxLabelHeight (const QFont & font) const**Parameters:**

font Font

Returns:

the maximum height of a label

6.73.4.19 int QwtScaleDraw::maxLabelWidth (const QFont & font) const**Parameters:**

font Font

Returns:

the maximum width of a label

6.73.4.20 QPoint QwtScaleDraw::labelPosition (double value) const

Find the position, where to paint a label

The position has a distance of [majTickLength\(\)](#) + [spacing\(\)](#) + 1 from the backbone. The direction depends on the [alignment\(\)](#)

Parameters:

value Value

6.73.4.21 QRect QwtScaleDraw::labelRect (const QFont & font, double value) const

Find the bounding rect for the label. The coordinates of the rect are relative to spacing + ticklength from the backbone in direction of the tick.

Parameters:

font Font used for painting

value Value

6.73.4.22 QSize QwtScaleDraw::labelSize (const QFont & *font*, double *value*) const

Calculate the size that is needed to draw a label

Parameters:

font Label font

value Value

6.73.4.23 QRect QwtScaleDraw::boundingLabelRect (const QFont & *font*, double *value*) const

Find the bounding rect for the label. The coordinates of the rect are absolute coordinates (calculated from [pos\(\)](#)). in direction of the tick.

Parameters:

font Font used for painting

value Value

See also:

[labelRect\(\)](#)

6.73.4.24 QMatrix QwtScaleDraw::labelMatrix (const QPoint & *pos*, const QSize & *size*) const
[protected]

Calculate the matrix that is needed to paint a label depending on its alignment and rotation.

Parameters:

pos Position where to paint the label

size Size of the label

See also:

[setLabelAlignment\(\)](#), [setLabelRotation\(\)](#)

6.73.4.25 void QwtScaleDraw::drawTick (QPainter * *painter*, double *value*, int *len*) const
[protected, virtual]

Draw a tick

Parameters:

painter Painter

value Value of the tick

len Length of the tick

See also:

[drawBackbone\(\)](#), [drawLabel\(\)](#)

Implements [QwtAbstractScaleDraw](#).

6.73.4.26 void QwtScaleDraw::drawBackbone (QPainter * *painter*) const [protected, virtual]

Draws the baseline of the scale

Parameters:

painter Painter

See also:

[drawTick\(\)](#), [drawLabel\(\)](#)

Implements [QwtAbstractScaleDraw](#).

6.73.4.27 void QwtScaleDraw::drawLabel (QPainter * *painter*, double *value*) const [protected, virtual]

Draws the label for a major scale tick

Parameters:

painter Painter

value Value

See also:

[drawTick\(\)](#), [drawBackbone\(\)](#), [boundingLabelRect\(\)](#)


Implements [QwtAbstractScaleDraw](#).

6.74 QwtScaleEngine Class Reference

Base class for scale engines.

```
#include <qwt_scale_engine.h>
```

Inheritance diagram for QwtScaleEngine:



Public Types

- enum [Attribute](#) {
 - NoAttribute** = 0,
 - IncludeReference** = 1,
 - Symmetric** = 2,
 - Floating** = 4,
 - Inverted** = 8 }

Public Member Functions

- [QwtScaleEngine](#) ()
- virtual [~QwtScaleEngine](#) ()
- void [setAttribute](#) ([Attribute](#), bool on=true)
- bool [testAttribute](#) ([Attribute](#)) const
- void [setAttributes](#) (int)
- int [attributes](#) () const
- void [setReference](#) (double reference)
- double [reference](#) () const
- void [setMargins](#) (double lower, double upper)
- double [lowerMargin](#) () const
- double [upperMargin](#) () const
- virtual void [autoScale](#) (int maxNumSteps, double &x1, double &x2, double &stepSize) const =0
- virtual [QwtScaleDiv](#) [divideScale](#) (double x1, double x2, int maxMajSteps, int maxMinSteps, double stepSize=0.0) const=0
- virtual [QwtScaleTransformation](#) * [transformation](#) () const=0

Protected Member Functions

- bool [contains](#) (const [QwtDoubleInterval](#) &, double val) const
- [QwtValueList](#) [strip](#) (const [QwtValueList](#) &, const [QwtDoubleInterval](#) &) const
- double [divideInterval](#) (double interval, int numSteps) const
- [QwtDoubleInterval](#) [buildInterval](#) (double v) const

6.74.1 Detailed Description

Base class for scale engines.

A scale engine tries to find "reasonable" ranges and step sizes for scales.

The layout of the scale can be varied with [setAttribute\(\)](#).

Qwt offers implementations for logarithmic (log10) and linear scales. Contributions for other types of scale engines (date/time, log2 ...) are welcome.

6.74.2 Member Enumeration Documentation**6.74.2.1 enum [QwtScaleEngine::Attribute](#)**

- IncludeReference
Build a scale which includes the [reference\(\)](#) value.
- Symmetric
Build a scale which is symmetric to the [reference\(\)](#) value.
- Floating

The endpoints of the scale are supposed to be equal the outmost included values plus the specified margins (see [setMargins\(\)](#)). If this attribute is **not** set, the endpoints of the scale will be integer multiples of the step size.

- Inverted
Turn the scale upside down.

See also:

[setAttribute\(\)](#), [testAttribute\(\)](#), [reference\(\)](#), [lowerMargin\(\)](#), [upperMargin\(\)](#)

6.74.3 Constructor & Destructor Documentation

6.74.3.1 QwtScaleEngine::QwtScaleEngine () [explicit]

Constructor.

6.74.3.2 QwtScaleEngine::~~QwtScaleEngine () [virtual]

Destructor.

6.74.4 Member Function Documentation

6.74.4.1 void QwtScaleEngine::setAttribute (**Attribute** *attribute*, bool *on* = true)

Change a scale attribute

Parameters:

attribute Attribute to change
on On/Off

See also:

[Attribute](#), [testAttribute\(\)](#)

6.74.4.2 bool QwtScaleEngine::testAttribute (**Attribute** *attribute*) const

Check if a attribute is set.

Parameters:

attribute Attribute to be tested

See also:

[Attribute](#), [setAttribute\(\)](#)

6.74.4.3 void QwtScaleEngine::setAttributes (int *attributes*)

Change the scale attribute

Parameters:

attributes Set scale attributes

See also:

[Attribute](#), [attributes\(\)](#)

6.74.4.4 int QwtScaleEngine::attributes () const

Return the scale attributes

See also:

[Attribute](#), [setAttributes\(\)](#), [testAttribute\(\)](#)

6.74.4.5 void QwtScaleEngine::setReference (double *r*)

Specify a reference point.

Parameters:

r new reference value

The reference point is needed if options IncludeReference or Symmetric are active. Its default value is 0.0.

See also:

[Attribute](#)

6.74.4.6 double QwtScaleEngine::reference () const

Returns:

the reference value

See also:

[setReference\(\)](#), [setAttribute\(\)](#)

6.74.4.7 void QwtScaleEngine::setMargins (double *lower*, double *upper*)

Specify margins at the scale's endpoints.

Parameters:

lower minimum distance between the scale's lower boundary and the smallest enclosed value

upper minimum distance between the scale's upper boundary and the greatest enclosed value

Margins can be used to leave a minimum amount of space between the enclosed intervals and the boundaries of the scale.

Warning:

- [QwtLog10ScaleEngine](#) measures the margins in decades.

See also:

[upperMargin\(\)](#), [lowerMargin\(\)](#)

6.74.4.8 double QwtScaleEngine::lowerMargin () const**Returns:**

the margin at the lower end of the scale The default margin is 0.

See also:

[setMargins\(\)](#)

6.74.4.9 double QwtScaleEngine::upperMargin () const**Returns:**

the margin at the upper end of the scale The default margin is 0.

See also:

[setMargins\(\)](#)

6.74.4.10 virtual void QwtScaleEngine::autoScale (int *maxNumSteps*, double & *x1*, double & *x2*, double & *stepSize*) const [pure virtual]

Align and divide an interval

Parameters:

maxNumSteps Max. number of steps
x1 First limit of the interval (In/Out)
x2 Second limit of the interval (In/Out)
stepSize Step size (Return value)

Implemented in [QwtLinearScaleEngine](#), and [QwtLog10ScaleEngine](#).

6.74.4.11 virtual [QwtScaleDiv](#) QwtScaleEngine::divideScale (double *x1*, double *x2*, int *maxMajSteps*, int *maxMinSteps*, double *stepSize* = 0.0) const [pure virtual]

Calculate a scale division.

Parameters:

x1 First interval limit
x2 Second interval limit
maxMajSteps Maximum for the number of major steps
maxMinSteps Maximum number of minor steps
stepSize Step size. If *stepSize* == 0.0, the *scaleEngine* calculates one.

Implemented in [QwtLinearScaleEngine](#), and [QwtLog10ScaleEngine](#).

6.74.4.12 virtual [QwtScaleTransformation*](#) QwtScaleEngine::transformation () const [pure virtual]

Returns:

a transformation

Implemented in [QwtLinearScaleEngine](#), and [QwtLog10ScaleEngine](#).

6.74.4.13 bool QwtScaleEngine::contains (const [QwtDoubleInterval](#) & *interval*, double *value*) const [protected]

Check if an interval "contains" a value

Parameters:

interval Interval

value Value

See also:

[QwtScaleArithmetic::compareEps\(\)](#)

6.74.4.14 [QwtValueList](#) QwtScaleEngine::strip (const [QwtValueList](#) & *ticks*, const [QwtDoubleInterval](#) & *interval*) const [protected]

Remove ticks from a list, that are not inside an interval

Parameters:

ticks Tick list

interval Interval

Returns:

Stripped tick list

6.74.4.15 double QwtScaleEngine::divideInterval (double *intervalSize*, int *numSteps*) const [protected]

Calculate a step size for an interval size

Parameters:

intervalSize Interval size

numSteps Number of steps

Returns:

Step size

6.74.4.16 [QwtDoubleInterval](#) QwtScaleEngine::buildInterval (double *v*) const [protected]

Build an interval for a value.

In case of $v == 0.0$ the interval is $[-0.5, 0.5]$, otherwise it is $[0.5 * v, 1.5 * v]$

6.75 QwtScaleMap Class Reference

A scale map.

```
#include <qwt_scale_map.h>
```

Public Member Functions

- [QwtScaleMap \(\)](#)
- [QwtScaleMap \(const QwtScaleMap &\)](#)
- [~QwtScaleMap \(\)](#)
- [QwtScaleMap & operator= \(const QwtScaleMap &\)](#)
- void [setTransformation \(QwtScaleTransformation *\)](#)
- const [QwtScaleTransformation * transformation \(\)](#) const
- void [setPaintInterval \(int p1, int p2\)](#)
- void [setPaintXInterval \(double p1, double p2\)](#)
- void [setScaleInterval \(double s1, double s2\)](#)
- int [transform \(double x\)](#) const
- double [invTransform \(double i\)](#) const
- double [xTransform \(double x\)](#) const
- double [p1 \(\)](#) const
- double [p2 \(\)](#) const
- double [s1 \(\)](#) const
- double [s2 \(\)](#) const
- double [pDist \(\)](#) const
- double [sDist \(\)](#) const

Public Attributes

- QT_STATIC_CONST double **LogMin**
- QT_STATIC_CONST double **LogMax**

6.75.1 Detailed Description

A scale map.

[QwtScaleMap](#) offers transformations from a scale into a paint interval and vice versa.

6.75.2 Constructor & Destructor Documentation

6.75.2.1 QwtScaleMap::QwtScaleMap ()

Constructor.

The scale and paint device intervals are both set to [0,1].

6.75.2.2 QwtScaleMap::QwtScaleMap (const QwtScaleMap &)

Copy constructor.

6.75.2.3 QwtScaleMap::~~QwtScaleMap ()

Destructor

6.75.3 Member Function Documentation

6.75.3.1 QwtScaleMap & QwtScaleMap::operator= (const QwtScaleMap &)

Assignment operator.

6.75.3.2 void QwtScaleMap::setTransformation (QwtScaleTransformation * transformation)

Initialize the map with a transformation

6.75.3.3 const QwtScaleTransformation * QwtScaleMap::transformation () const

Get the transformation.

6.75.3.4 void QwtScaleMap::setPaintInterval (int p1, int p2)

Specify the borders of the paint device interval.

Parameters:

p1 first border

p2 second border

6.75.3.5 void QwtScaleMap::setPaintXInterval (double p1, double p2)

Specify the borders of the paint device interval.

Parameters:

p1 first border

p2 second border

6.75.3.6 void QwtScaleMap::setScaleInterval (double s1, double s2)

Specify the borders of the scale interval.

Parameters:

s1 first border

s2 second border

Warning:

logarithmic scales might be aligned to [LogMin, LogMax]

6.75.3.7 int QwtScaleMap::transform (double *s*) const [inline]

Transform a point related to the scale interval into a point related to the interval of the paint device and round it to an integer. (In Qt <= 3.x paint devices are integer based.)

Parameters:

s Value relative to the coordinates of the scale

See also:

[xTransform\(\)](#)

6.75.3.8 double QwtScaleMap::invTransform (double *p*) const [inline]

Transform an paint device value into a value in the interval of the scale.

Parameters:

p Value relative to the coordinates of the paint device

See also:

[transform\(\)](#)

6.75.3.9 double QwtScaleMap::xTransform (double *s*) const [inline]

Transform a point related to the scale interval into an point related to the interval of the paint device

Parameters:

s Value relative to the coordinates of the scale

6.75.3.10 double QwtScaleMap::p1 () const [inline]**Returns:**

First border of the paint interval

6.75.3.11 double QwtScaleMap::p2 () const [inline]**Returns:**

Second border of the paint interval

6.75.3.12 double QwtScaleMap::s1 () const [inline]**Returns:**

First border of the scale interval

6.75.3.13 `double QwtScaleMap::s2 () const` [inline]

Returns:

Second border of the scale interval

6.75.3.14 `double QwtScaleMap::pDist () const` [inline]

Returns:

`qwtAbs(p2) - p1()`

6.75.3.15 `double QwtScaleMap::sDist () const` [inline]

Returns:

`qwtAbs(s2) - s1()`

6.76 QwtScaleTransformation Class Reference

Operations for linear or logarithmic (base 10) transformations.

```
#include <qwt_scale_map.h>
```

Public Types

- enum `Type` {
 RubberBand,
 Text,
 Linear,
 Log10,
 Other }

Public Member Functions

- `QwtScaleTransformation` (Type type)
- virtual `~QwtScaleTransformation` ()
- virtual double `xForm` (double x, double s1, double s2, double p1, double p2) const
- virtual double `invXForm` (double x, double s1, double s2, double p1, double p2) const
- Type `type` () const
- virtual `QwtScaleTransformation * copy` () const

6.76.1 Detailed Description

Operations for linear or logarithmic (base 10) transformations.

6.76.2 Constructor & Destructor Documentation

6.76.2.1 QwtScaleTransformation::QwtScaleTransformation (Type *type*)

Constructor for a linear transformation.

6.76.2.2 QwtScaleTransformation::~~QwtScaleTransformation () [virtual]

Destructor.

6.76.3 Member Function Documentation

6.76.3.1 double QwtScaleTransformation::xForm (double *s*, double *s1*, double *s2*, double *p1*, double *p2*) const [virtual]

Transform a value between 2 linear intervals.

Parameters:

- x* value related to the interval [*x1*, *x2*]
- x1* first border of source interval
- x2* first border of source interval
- y1* first border of target interval
- y2* first border of target interval

Returns:

- linear mapping:** $y1 + (y2 - y1) / (x2 - x1) * (x - x1)$
- log10 mapping:** $p1 + (p2 - p1) / \log(s2 / s1) * \log(x / s1)$

6.76.3.2 double QwtScaleTransformation::invXForm (double *p*, double *p1*, double *p2*, double *s1*, double *s2*) const [virtual]

Transform a value from a linear to a logarithmic interval.

Parameters:

- x* value related to the linear interval [*p1*, *p2*]
- p1* first border of linear interval
- p2* first border of linear interval
- s1* first border of logarithmic interval
- s2* first border of logarithmic interval

Returns:

- $\exp((x - p1) / (p2 - p1) * \log(s2 / s1)) * s1;$

6.76.3.3 Type QwtScaleTransformation::type () const [inline]

Returns:

Transformation type

6.76.3.4 QwtScaleTransformation * QwtScaleTransformation::copy () const [virtual]

Create a clone of the transformation.

6.77 QwtScaleWidget Class Reference

A Widget which contains a scale.

```
#include <qwt_scale_widget.h>
```

Signals

- void [scaleDivChanged \(\)](#)

Public Member Functions

- [QwtScaleWidget](#) (QWidget *parent=NULL)
- [QwtScaleWidget](#) (QwtScaleDraw::Alignment, QWidget *parent=NULL)
- virtual [~QwtScaleWidget \(\)](#)
- void [setTitle](#) (const QString &title)
- void [setTitle](#) (const QwtText &title)
- [QwtText](#) [title](#) () const
- void [setBorderDist](#) (int start, int end)
- int [startBorderDist](#) () const
- int [endBorderDist](#) () const
- void [getBorderDistHint](#) (int &start, int &end) const
- void [getMinBorderDist](#) (int &start, int &end) const
- void [setMinBorderDist](#) (int start, int end)
- void [setMargin](#) (int)
- int [margin](#) () const
- void [setSpacing](#) (int td)
- int [spacing](#) () const
- void [setPenWidth](#) (int)
- int [penWidth](#) () const
- void [setScaleDiv](#) (QwtScaleTransformation *, const QwtScaleDiv &sd)
- void [setScaleDraw](#) (QwtScaleDraw *)
- const [QwtScaleDraw](#) * [scaleDraw](#) () const
- [QwtScaleDraw](#) * [scaleDraw](#) ()
- void [setLabelAlignment](#) (Qt::Alignment)
- void [setLabelRotation](#) (double rotation)
- void [setColorBarEnabled](#) (bool)
- bool [isColorBarEnabled](#) () const
- void [setColorBarWidth](#) (int)
- int [colorBarWidth](#) () const
- void [setColorMap](#) (const QwtDoubleInterval &, const QwtColorMap &)
- [QwtDoubleInterval](#) [colorBarInterval](#) () const
- const [QwtColorMap](#) & [colorMap](#) () const
- virtual QSize [sizeHint](#) () const
- virtual QSize [minimumSizeHint](#) () const
- int [titleHeightForWidth](#) (int width) const

- int `dimForLength` (int length, const QFont &scaleFont) const
- void `drawColorBar` (QPainter *painter, const QRect &rect) const
- void `drawTitle` (QPainter *painter, QwtScaleDraw::Alignment, const QRect &rect) const
- void `setAlignment` (QwtScaleDraw::Alignment)
- QwtScaleDraw::Alignment `alignment` () const
- QRect `colorBarRect` (const QRect &) const

Protected Member Functions

- virtual void `paintEvent` (QPaintEvent *e)
- virtual void `resizeEvent` (QResizeEvent *e)
- void `draw` (QPainter *p) const
- void `scaleChange` ()
- void `layoutScale` (bool update=true)

6.77.1 Detailed Description

A Widget which contains a scale.

This Widget can be used to decorate composite widgets with a scale.

6.77.2 Constructor & Destructor Documentation

6.77.2.1 QwtScaleWidget::QwtScaleWidget (QWidget *parent = NULL) [explicit]

Create a scale with the position QwtScaleWidget::Left.

Parameters:

parent Parent widget

6.77.2.2 QwtScaleWidget::QwtScaleWidget (QwtScaleDraw::Alignment align, QWidget *parent = NULL) [explicit]

Constructor.

Parameters:

align Alignment.

parent Parent widget

6.77.2.3 QwtScaleWidget::~QwtScaleWidget () [virtual]

Destructor.

6.77.3 Member Function Documentation

6.77.3.1 void QwtScaleWidget::scaleDivChanged () [signal]

Signal emitted, whenever the scale division changes.

6.77.3.2 void QwtScaleWidget::setTitle (const QString & title)

Give title new text contents

Parameters:

title New title

See also:

[title\(\)](#), [setTitle\(const QwtText &\);](#)

6.77.3.3 void QwtScaleWidget::setTitle (const QwtText & title)

Give title new text contents

Parameters:

title New title

See also:

[title\(\)](#)

Warning:

The title flags are interpreted in direction of the label, AlignTop, AlignBottom can't be set as the title will always be aligned to the scale.

6.77.3.4 QwtText QwtScaleWidget::title () const**Returns:**

title

See also:

[setTitle\(\)](#)

6.77.3.5 void QwtScaleWidget::setBorderDist (int dist1, int dist2)

Specify distances of the scale's endpoints from the widget's borders. The actual borders will never be less than minimum border distance.

Parameters:

dist1 Left or top Distance

dist2 Right or bottom distance

See also:

[borderDist\(\)](#)

6.77.3.6 int QwtScaleWidget::startBorderDist () const**Returns:**

start border distance

See also:

[setBorderDist\(\)](#)

6.77.3.7 int QwtScaleWidget::endBorderDist () const**Returns:**

end border distance

See also:

[setBorderDist\(\)](#)

6.77.3.8 void QwtScaleWidget::getBorderDistHint (int & start, int & end) const

Calculate a hint for the border distances.

This member function calculates the distance of the scale's endpoints from the widget borders which is required for the mark labels to fit into the widget. The maximum of this distance and the minimum border distance is returned.

Warning:

- The minimum border distance depends on the font.

See also:

[setMinBorderDist\(\)](#), [getMinBorderDist\(\)](#), [setBorderDist\(\)](#)

6.77.3.9 void QwtScaleWidget::getMinBorderDist (int & start, int & end) const

Get the minimum value for the distances of the scale's endpoints from the widget borders.

See also:

[setMinBorderDist\(\)](#), [getBorderDistHint\(\)](#)

6.77.3.10 void QwtScaleWidget::setMinBorderDist (int start, int end)

Set a minimum value for the distances of the scale's endpoints from the widget borders. This is useful to avoid that the scales are "jumping", when the tick labels or their positions change often.

Parameters:

start Minimum for the start border

end Minimum for the end border

See also:

[getMinBorderDist\(\)](#), [getBorderDistHint\(\)](#)

6.77.3.11 void QwtScaleWidget::setMargin (int *margin*)

Specify the margin to the colorBar/base line.

Parameters:

margin Margin

See also:

[margin\(\)](#)

6.77.3.12 int QwtScaleWidget::margin () const**Returns:**

margin

See also:

[setMargin\(\)](#)

6.77.3.13 void QwtScaleWidget::setSpacing (int *spacing*)

Specify the distance between color bar, scale and title.

Parameters:

spacing Spacing

See also:

[spacing\(\)](#)

6.77.3.14 int QwtScaleWidget::spacing () const**Returns:**

distance between scale and title

See also:

[setMargin\(\)](#)

6.77.3.15 void QwtScaleWidget::setPenWidth (int *width*)

Specify the width of the scale pen.

Parameters:

width Pen width

See also:

[penWidth\(\)](#)

6.77.3.16 `int QwtScaleWidget::penWidth () const`**Returns:**

Scale pen width

See also:

[setPenWidth\(\)](#)

6.77.3.17 `void QwtScaleWidget::setScaleDiv (QwtScaleTransformation * transformation, const QwtScaleDiv & scaleDiv)`

Assign a scale division.

The scale division determines where to set the tick marks.

Parameters:

transformation Transformation, needed to translate between scale and pixel values

scaleDiv Scale Division

See also:

For more information about scale divisions, see [QwtScaleDiv](#).

6.77.3.18 `void QwtScaleWidget::setScaleDraw (QwtScaleDraw * sd)`

Set a scale draw *sd* has to be created with `new` and will be deleted in `~QwtScaleWidget()` or the next call of `setScaleDraw()`.

Parameters:

sd ScaleDraw object

See also:

[scaleDraw\(\)](#)

6.77.3.19 `const QwtScaleDraw * QwtScaleWidget::scaleDraw () const`

scaleDraw of this scale

See also:

[setScaleDraw\(\)](#), [QwtScaleDraw::setScaleDraw\(\)](#)

6.77.3.20 `QwtScaleDraw * QwtScaleWidget::scaleDraw ()`

scaleDraw of this scale

See also:

[QwtScaleDraw::setScaleDraw\(\)](#)

6.77.3.21 void QwtScaleWidget::setLabelAlignment (Qt::Alignment *alignment*)

Change the alignment for the labels.

See also:

[QwtScaleDraw::setLabelAlignment\(\)](#), [setLabelRotation\(\)](#)

6.77.3.22 void QwtScaleWidget::setLabelRotation (double *rotation*)

Change the rotation for the labels. See [QwtScaleDraw::setLabelRotation\(\)](#).

, rotation Rotation

See also:

[QwtScaleDraw::setLabelRotation\(\)](#), [setLabelFlags\(\)](#)

6.77.3.23 QSize QwtScaleWidget::sizeHint () const [virtual]

Returns:

a size hint

6.77.3.24 QSize QwtScaleWidget::minimumSizeHint () const [virtual]

Returns:

a minimum size hint

6.77.3.25 int QwtScaleWidget::titleHeightForWidth (int *width*) const

Find the height of the title for a given width.

Parameters:

width Width

Returns:

height Height

6.77.3.26 int QwtScaleWidget::dimForLength (int *length*, const QFont & *scaleFont*) const

Find the minimum dimension for a given length. *dim* is the height, *length* the width seen in direction of the title.

Parameters:

length width for horizontal, height for vertical scales

scaleFont Font of the scale

Returns:

height for horizontal, width for vertical scales

6.77.3.27 void QwtScaleWidget::drawTitle (QPainter * *painter*, QwtScaleDraw::Alignment *align*, const QRect & *rect*) const

Rotate and paint a title according to its position into a given rectangle.

Parameters:

painter Painter

align Alignment

rect Bounding rectangle

6.77.3.28 void QwtScaleWidget::setAlignment (QwtScaleDraw::Alignment *alignment*)

Change the alignment

Parameters:

alignment New alignment

See also:

[alignment\(\)](#)

6.77.3.29 QwtScaleDraw::Alignment QwtScaleWidget::alignment () const

Returns:

position

See also:

[setPosition\(\)](#)

6.77.3.30 void QwtScaleWidget::paintEvent (QPaintEvent * *e*) [protected, virtual]

paintEvent

6.77.3.31 void QwtScaleWidget::resizeEvent (QResizeEvent * *e*) [protected, virtual]

resizeEvent

6.77.3.32 void QwtScaleWidget::draw (QPainter * *p*) const [protected]

draw the scale

6.77.3.33 void QwtScaleWidget::scaleChange () [protected]

Notify a change of the scale.

This virtual function can be overloaded by derived classes. The default implementation updates the geometry and repaints the widget.

6.77.3.34 void QwtScaleWidget::layoutScale (bool *update* = true) [protected]


Recalculate the scale's geometry and layout based on.

6.78 QwtSimpleCompassRose Class Reference

A simple rose for [QwtCompass](#).

```
#include <qwt_compass_rose.h>
```

Inheritance diagram for QwtSimpleCompassRose:

**Public Member Functions**

- [QwtSimpleCompassRose](#) (int numThorns=8, int numThornLevels=-1)
- void [setWidth](#) (double w)
- double [width](#) () const
- void [setNumThorns](#) (int count)
- int [numThorns](#) () const
- void [setNumThornLevels](#) (int count)
- int [numThornLevels](#) () const
- void [setShrinkFactor](#) (double factor)
- double [shrinkFactor](#) () const
- virtual void [draw](#) (QPainter *, const QPoint ¢er, int radius, double north, QPalette::ColorGroup=QPalette::Active) const

Static Public Member Functions

- static void [drawRose](#) (QPainter *, const QPalette &, const QPoint ¢er, int radius, double origin, double width, int numThorns, int numThornLevels, double shrinkFactor)

6.78.1 Detailed Description

A simple rose for [QwtCompass](#).

6.78.2 Constructor & Destructor Documentation**6.78.2.1** QwtSimpleCompassRose::QwtSimpleCompassRose (int *numThorns* = 8, int *numThornLevels* = -1)

Constructor

Parameters:

numThorns Number of thorns

numThornLevels Number of thorn levels

6.78.3 Member Function Documentation

6.78.3.1 void QwtSimpleCompassRose::setWidth (double *width*)

Set the width of the rose heads. Lower value make thinner heads. The range is limited from 0.03 to 0.4.

Parameters:

width Width

6.78.3.2 double QwtSimpleCompassRose::width () const [inline]

See also:

[setWidth\(\)](#)

6.78.3.3 void QwtSimpleCompassRose::setNumThorns (int *numThorns*)

Set the number of thorns on one level The number is aligned to a multiple of 4, with a minimum of 4

Parameters:

numThorns Number of thorns

See also:

[numThorns\(\)](#), [setNumThornLevels\(\)](#)

6.78.3.4 int QwtSimpleCompassRose::numThorns () const

Returns:

Number of thorns

See also:

[setNumThorns\(\)](#), [setNumThornLevels\(\)](#)

6.78.3.5 void QwtSimpleCompassRose::setNumThornLevels (int *numThornLevels*)

Set the of thorns levels

Parameters:

numThornLevels Number of thorns levels

See also:

[setNumThorns\(\)](#), [numThornLevels\(\)](#)

6.78.3.6 int QwtSimpleCompassRose::numThornLevels () const

Returns:

Number of thorn levels

See also:

[setNumThorns\(\)](#), [setNumThornLevels\(\)](#)

6.78.3.7 void QwtSimpleCompassRose::draw (QPainter * *painter*, const QPoint & *center*, int *radius*, double *north*, QPalette::ColorGroup *cg* = QPalette::Active) const [virtual]

Draw the rose

Parameters:

painter Painter
center Center point
radius Radius of the rose
north Position
cg Color group

Implements [QwtCompassRose](#).

6.78.3.8 void QwtSimpleCompassRose::drawRose (QPainter * *painter*, const QPalette & *palette*, const QPoint & *center*, int *radius*, double *north*, double *width*, int *numThorns*, int *numThornLevels*, double *shrinkFactor*) [static]

Draw the rose

Parameters:


painter Painter
palette Palette
center Center of the rose
radius Radius of the rose
north Position pointing to north
width Width of the rose
numThorns Number of thorns
numThornLevels Number of thorn levels
shrinkFactor Factor to shrink the thorns with each level

6.79 QwtSlider Class Reference

The Slider Widget.

```
#include <qwt_slider.h>
```

Inheritance diagram for QwtSlider:



Public Types

- enum [ScalePos](#) {
NoScale,
LeftScale,
RightScale,
TopScale,
BottomScale,
NoScale,
LeftScale,
RightScale,
TopScale,
BottomScale }
- enum [BGSTYLE](#) {
BgTrough = 0x1,
BgSlot = 0x2,
BgBoth = BgTrough | BgSlot }

Public Member Functions

- [QwtSlider](#) (QWidget *parent, Qt::Orientation=Qt::Horizontal, [ScalePos](#)=NoScale, [BGSTYLE](#) bgStyle=BgTrough)
- virtual void [setOrientation](#) (Qt::Orientation)
- void [setBgStyle](#) ([BGSTYLE](#))
- [BGSTYLE](#) [bgStyle](#) () const
- void [setScalePosition](#) ([ScalePos](#) s)
- [ScalePos](#) [scalePosition](#) () const
- int [thumbLength](#) () const
- int [thumbWidth](#) () const
- int [borderWidth](#) () const
- void [setThumbLength](#) (int l)
- void [setThumbWidth](#) (int w)
- void [setBorderWidth](#) (int bw)
- void [setMargins](#) (int x, int y)
- virtual QSize [sizeHint](#) () const
- virtual QSize [minimumSizeHint](#) () const
- void [setScaleDraw](#) (QwtScaleDraw *)
- const [QwtScaleDraw](#) * [scaleDraw](#) () const

Protected Member Functions

- virtual double [getValue](#) (const QPoint &p)
- virtual void [getScrollMode](#) (const QPoint &p, int &scrollMode, int &direction)
- void [draw](#) (QPainter *p, const QRect &update_rect)
- virtual void [drawSlider](#) (QPainter *p, const QRect &r)
- virtual void [drawThumb](#) (QPainter *p, const QRect &, int pos)
- virtual void [resizeEvent](#) (QResizeEvent *e)
- virtual void [paintEvent](#) (QPaintEvent *e)
- virtual void [valueChange](#) ()
- virtual void [rangeChange](#) ()
- virtual void [scaleChange](#) ()
- virtual void [fontChange](#) (const QFont &oldFont)
- void [layoutSlider](#) (bool update=true)
- int [xyPosition](#) (double v) const
- [QwtScaleDraw](#) * [scaleDraw](#) ()

6.79.1 Detailed Description

The Slider Widget.

[QwtSlider](#) is a slider widget which operates on an interval of type double. [QwtSlider](#) supports different layouts as well as a scale.

See also:

[QwtAbstractSlider](#) and [QwtAbstractScale](#) for the descriptions of the inherited members.

6.79.2 Member Enumeration Documentation

6.79.2.1 enum [QwtSlider::ScalePos](#)

Scale position. [QwtSlider](#) tries to enforce valid combinations of its orientation and scale position:

- Qt::Horizontal combines with NoScale, TopScale and BottomScale
- Qt::Vertical combines with NoScale, LeftScale and RightScale

See also:

[QwtSlider\(\)](#)

6.79.2.2 enum [QwtSlider::BGSTYLE](#)

Background style.

See also:

[QwtSlider\(\)](#)

6.79.3 Constructor & Destructor Documentation

6.79.3.1 QwtSlider::QwtSlider (QWidget * *parent*, Qt::Orientation *orientation* = Qt::Horizontal, ScalePos *scalePos* = NoScale, BGSTYLE *bgStyle* = BgTrough) [explicit]

Constructor.

Parameters:

parent parent widget

orientation Orientation of the slider. Can be Qt::Horizontal or Qt::Vertical. Defaults to Qt::Horizontal.

scalePos Position of the scale. Defaults to QwtSlider::NoScale.

bgStyle Background style. QwtSlider::BgTrough draws the slider button in a trough, QwtSlider::BgSlot draws a slot underneath the button. An or-combination of both may also be used. The default is QwtSlider::BgTrough.

[QwtSlider](#) enforces valid combinations of its orientation and scale position. If the combination is invalid, the scale position will be set to NoScale. Valid combinations are:

- Qt::Horizontal with NoScale, TopScale, or BottomScale;
- Qt::Vertical with NoScale, LeftScale, or RightScale.

6.79.4 Member Function Documentation

6.79.4.1 void QwtSlider::setOrientation (Qt::Orientation *o*) [virtual]

Set the orientation.

Parameters:

o Orientation. Allowed values are Qt::Horizontal and Qt::Vertical.

If the new orientation and the old scale position are an invalid combination, the scale position will be set to QwtSlider::NoScale.

See also:

[QwtAbstractSlider::orientation\(\)](#)

Reimplemented from [QwtAbstractSlider](#).

6.79.4.2 void QwtSlider::setBgStyle (BGSTYLE *st*)

Set the background style.

6.79.4.3 QwtSlider::BGSTYLE QwtSlider::bgStyle () const

Returns:

the background style.

6.79.4.4 void QwtSlider::setScalePosition (ScalePos s)

Change the scale position (and slider orientation).

Parameters:

s Position of the scale.

A valid combination of scale position and orientation is enforced:

- if the new scale position is Left or Right, the scale orientation will become Qt::Vertical;
- if the new scale position is Bottom or Top the scale orientation will become Qt::Horizontal;
- if the new scale position is QwtSlider::NoScale, the scale orientation will not change.

6.79.4.5 QwtSlider::ScalePos QwtSlider::scalePosition () const

Return the scale position.

6.79.4.6 int QwtSlider::thumbLength () const**Returns:**

the thumb length.

6.79.4.7 int QwtSlider::thumbWidth () const**Returns:**

the thumb width.

6.79.4.8 int QwtSlider::borderWidth () const**Returns:**

the border width.

6.79.4.9 void QwtSlider::setThumbLength (int *thumbLength*)

Set the slider's thumb length.

Parameters:

thumbLength new length

6.79.4.10 void QwtSlider::setThumbWidth (int *w*)

Change the width of the thumb.

Parameters:

w new width

6.79.4.11 void QwtSlider::setBorderWidth (int *bd*)

Change the slider's border width.

Parameters:

bd border width

6.79.4.12 void QwtSlider::setMargins (int *xMargin*, int *yMargin*)

Set distances between the widget's border and internals.

Parameters:

xMargin Horizontal margin

yMargin Vertical margin

6.79.4.13 QSize QwtSlider::sizeHint () const [virtual]**Returns:**

[QwtSlider::minimumSizeHint\(\)](#)

6.79.4.14 QSize QwtSlider::minimumSizeHint () const [virtual]

Return a minimum size hint.

Warning:

The return value of [QwtSlider::minimumSizeHint\(\)](#) depends on the font and the scale.

6.79.4.15 void QwtSlider::setScaleDraw (QwtScaleDraw * *scaleDraw*)

Set a scale draw.

For changing the labels of the scales, it is necessary to derive from [QwtScaleDraw](#) and overload [QwtScaleDraw::label\(\)](#).

Parameters:

scaleDraw ScaleDraw object, that has to be created with new and will be deleted in ~QwtSlider or the next call of [setScaleDraw\(\)](#).

6.79.4.16 const QwtScaleDraw * QwtSlider::scaleDraw () const**Returns:**

the scale draw of the slider

See also:

[setScaleDraw\(\)](#)

6.79.4.17 `double QwtSlider::getValue (const QPoint & pos)` [protected, virtual]

Determine the value corresponding to a specified mouse location.

Parameters:

pos Mouse position

Implements [QwtAbstractSlider](#).

6.79.4.18 `void QwtSlider::getScrollMode (const QPoint & p, int & scrollMode, int & direction)` [protected, virtual]

Determine scrolling mode and direction.

Parameters:

p point

scrollMode Scrolling mode

direction Direction

Implements [QwtAbstractSlider](#).

6.79.4.19 `void QwtSlider::draw (QPainter * p, const QRect & update_rect)` [protected]

Draw the [QwtSlider](#).

6.79.4.20 `void QwtSlider::drawSlider (QPainter * painter, const QRect & r)` [protected, virtual]

Draw the slider into the specified rectangle.

Parameters:

painter Painter

r Rectangle

6.79.4.21 `void QwtSlider::drawThumb (QPainter * painter, const QRect & sliderRect, int pos)` [protected, virtual]

Draw the thumb at a position

Parameters:

painter Painter

sliderRect Bounding rectangle of the slider

pos Position of the slider thumb

6.79.4.22 `void QwtSlider::resizeEvent (QResizeEvent * e)` [protected, virtual]

Qt resize event.

6.79.4.23 void QwtSlider::paintEvent (QPaintEvent * *event*) [protected, virtual]

Qt paint event

Parameters:

event Paint event

6.79.4.24 void QwtSlider::valueChange () [protected, virtual]

Notify change of value.

Reimplemented from [QwtAbstractSlider](#).

6.79.4.25 void QwtSlider::rangeChange () [protected, virtual]

Notify change of range.

Reimplemented from [QwtDoubleRange](#).

6.79.4.26 void QwtSlider::scaleChange () [protected, virtual]

Notify changed scale.

Reimplemented from [QwtAbstractScale](#).

6.79.4.27 void QwtSlider::fontChange (const QFont & *oldFont*) [protected, virtual]

Notify change in font.

6.79.4.28 void QwtSlider::layoutSlider (bool *update_geometry* = true) [protected]

Recalculate the slider's geometry and layout based on the current rect and fonts.

Parameters:

update_geometry notify the layout system and call update to redraw the scale

6.79.4.29 int QwtSlider::xyPosition (double *value*) const [protected]

Find the x/y position for a given value *v*

Parameters:

value Value

6.79.4.30 [QwtScaleDraw](#) * QwtSlider::scaleDraw () [protected]

Returns:

the scale draw of the slider

See also:

[setScaleDraw\(\)](#)

6.80 QwtSpline Class Reference

A class for spline interpolation.

```
#include <qwt_spline.h>
```

Public Types

- enum [SplineType](#) {
 Natural,
 Periodic }

Public Member Functions

- [QwtSpline](#) ()
- [QwtSpline](#) (const [QwtSpline](#) &)
- [~QwtSpline](#) ()
- [QwtSpline](#) & [operator=](#) (const [QwtSpline](#) &)
- void [setSplineType](#) ([SplineType](#))
- [SplineType](#) [splineType](#) () const
- bool [setPoints](#) (const [QPolygonF](#) &points)
- [QPolygonF](#) [points](#) () const
- void [reset](#) ()
- bool [isValid](#) () const
- double [value](#) (double x) const
- const [QwtArray](#)< double > & [coefficientsA](#) () const
- const [QwtArray](#)< double > & [coefficientsB](#) () const
- const [QwtArray](#)< double > & [coefficientsC](#) () const

Protected Member Functions

- bool [buildNaturalSpline](#) (const [QPolygonF](#) &)
- bool [buildPeriodicSpline](#) (const [QPolygonF](#) &)

Protected Attributes

- [PrivateData](#) * [d_data](#)

6.80.1 Detailed Description

A class for spline interpolation.

The [QwtSpline](#) class is used for cubical spline interpolation. Two types of splines, natural and periodic, are supported.

Usage:

1. First call [setPoints\(\)](#) to determine the spline coefficients for a tabulated function $y(x)$.
2. After the coefficients have been set up, the interpolated function value for an argument x can be determined by calling [QwtSpline::value\(\)](#).

Example:

```
#include <qwt_spline.h>

QPolygonF interpolate(const QPolygonF& points, int numValues)
{
    QwtSpline spline;
    if ( !spline.setPoints(points) )
        return points;

    QPolygonF interpolatedPoints(numValues);

    const double delta =
        (points[numPoints - 1].x() - points[0].x()) / (points.size() - 1);
    for(i = 0; i < points.size(); i++) / interpolate
    {
        const double x = points[0].x() + i * delta;
        interpolatedPoints[i].setX(x);
        interpolatedPoints[i].setY(spline.value(x));
    }
    return interpolatedPoints;
}
```

6.80.2 Member Enumeration Documentation**6.80.2.1 enum [QwtSpline::SplineType](#)**

Spline type.

6.80.3 Constructor & Destructor Documentation**6.80.3.1 [QwtSpline::QwtSpline \(\)](#)**

Constructor.

6.80.3.2 [QwtSpline::QwtSpline \(const \[QwtSpline\]\(#\) & *other*\)](#)

Copy constructor

Parameters:

other Spline used for initialization

6.80.3.3 [QwtSpline::~~QwtSpline \(\)](#)

Destructor.

6.80.4 Member Function Documentation**6.80.4.1 [QwtSpline & QwtSpline::operator= \(const \[QwtSpline\]\(#\) & *other*\)](#)**

Assignment operator

Parameters:

other Spline used for initialization

6.80.4.2 void QwtSpline::setSplineType (SplineType splineType)

Select the algorithm used for calculating the spline

Parameters:

splineType Spline type

See also:

[splineType\(\)](#)

6.80.4.3 QwtSpline::SplineType QwtSpline::splineType () const**Returns:**

the spline type

See also:

[setSplineType\(\)](#)

6.80.4.4 bool QwtSpline::setPoints (const QPolygonF & points)

Calculate the spline coefficients.

Depending on the value of *periodic*, this function will determine the coefficients for a natural or a periodic spline and store them internally.

Parameters:

x

y points

size number of points

periodic if true, calculate periodic spline

Returns:

true if successful

Warning:

The sequence of *x* (but not *y*) values has to be strictly monotone increasing, which means $x[0] < x[1] < \dots < x[n-1]$. If this is not the case, the function will return false

6.80.4.5 QPolygonF QwtSpline::points () const

Return points passed by setPoints

6.80.4.6 void QwtSpline::reset ()

Free allocated memory and set size to 0.

6.80.4.7 `bool QwtSpline::isValid () const`

True if valid.

6.80.4.8 `double QwtSpline::value (double x) const`

Calculate the interpolated function value corresponding to a given argument x.

6.80.4.9 `const QwtArray< double > & QwtSpline::coefficientsA () const`

Returns:

A coefficients

6.80.4.10 `const QwtArray< double > & QwtSpline::coefficientsB () const`

Returns:

B coefficients

6.80.4.11 `const QwtArray< double > & QwtSpline::coefficientsC () const`

Returns:

C coefficients

6.80.4.12 `bool QwtSpline::buildNaturalSpline (const QPolygonF & points) [protected]`

Determines the coefficients for a natural spline.

Returns:

true if successful

6.80.4.13 `bool QwtSpline::buildPeriodicSpline (const QPolygonF & points) [protected]`

Determines the coefficients for a periodic spline.

Returns:


true if successful

6.81 **QwtSplineCurveFitter Class Reference**

A curve fitter using cubic splines.

```
#include <qwt_curve_fitter.h>
```

Inheritance diagram for QwtSplineCurveFitter:



Public Types

- enum **FitMode** {
 Auto,
 Spline,
 ParametricSpline }

Public Member Functions

- [QwtSplineCurveFitter](#) ()
- virtual [~QwtSplineCurveFitter](#) ()
- void [setFitMode](#) (FitMode)
- FitMode [fitMode](#) () const
- void [setSpline](#) (const [QwtSpline](#) &)
- const [QwtSpline](#) & [spline](#) () const
- [QwtSpline](#) & [spline](#) ()
- void [setSplineSize](#) (int size)
- int [splineSize](#) () const
- virtual [QPolygonF](#) [fitCurve](#) (const [QPolygonF](#) &) const

6.81.1 Detailed Description

A curve fitter using cubic splines.

6.81.2 Constructor & Destructor Documentation

6.81.2.1 [QwtSplineCurveFitter::QwtSplineCurveFitter](#) ()

Constructor.

6.81.2.2 [QwtSplineCurveFitter::~~QwtSplineCurveFitter](#) () [virtual]

Destructor.

6.81.3 Member Function Documentation

6.81.3.1 void [QwtSplineCurveFitter::setFitMode](#) (FitMode *mode*)

Select the algorithm used for building the spline

Parameters:

mode Mode representing a spline algorithm

See also:

[fitMode\(\)](#)

6.81.3.2 QwtSplineCurveFitter::FitMode QwtSplineCurveFitter::fitMode () const

Returns:

Mode representing a spline algorithm

See also:

[setFitMode\(\)](#)

6.81.3.3 QPolygonF QwtSplineCurveFitter::fitCurve (const QPolygonF & *points*) const [virtual]

Find a curve which has the best fit to a series of data points

Parameters:

points Series of data points

Returns:

Curve points

Implements [QwtCurveFitter](#).

6.82 QwtSymbol Class Reference

A class for drawing symbols.

```
#include <qwt_symbol.h>
```

Public Types

- enum [Style](#) {
 Arrow,
 Ray,
 TriangleStyle,
 ThinStyle,
 Style1,
 Style2,
 NoSymbol = -1,
 Ellipse,
 Rect,
 Diamond,
 Triangle,
 DTriangle,
 UTriangle,
 LTriangle,

RTriangle,
Cross,
XCross,
HLine,
VLine,
Star1,
Star2,
Hexagon,
StyleCnt }

Public Member Functions

- [QwtSymbol](#) ()
- [QwtSymbol](#) ([Style](#) st, const [QBrush](#) &bd, const [QPen](#) &pn, const [QSize](#) &s)
- virtual [~QwtSymbol](#) ()
- bool [operator!=](#) (const [QwtSymbol](#) &) const
- virtual bool [operator==](#) (const [QwtSymbol](#) &) const
- virtual [QwtSymbol](#) * [clone](#) () const
- void [setSize](#) (const [QSize](#) &s)
- void [setSize](#) (int a, int b=-1)
- void [setBrush](#) (const [QBrush](#) &b)
- void [setPen](#) (const [QPen](#) &p)
- void [setStyle](#) ([Style](#) s)
- const [QBrush](#) & [brush](#) () const
- const [QPen](#) & [pen](#) () const
- const [QSize](#) & [size](#) () const
- [Style](#) [style](#) () const
- void [draw](#) ([QPainter](#) *p, const [QPoint](#) &pt) const
- void [draw](#) ([QPainter](#) *p, int x, int y) const
- virtual void [draw](#) ([QPainter](#) *p, const [QRect](#) &r) const

6.82.1 Detailed Description

A class for drawing symbols.

6.82.2 Member Enumeration Documentation

6.82.2.1 enum [QwtSymbol::Style](#)

Style

See also:

[setStyle\(\)](#), [style\(\)](#)

6.82.3 Constructor & Destructor Documentation

6.82.3.1 QwtSymbol::QwtSymbol ()

Default Constructor

The symbol is constructed with gray interior, black outline with zero width, no size and style 'NoSymbol'.

6.82.3.2 QwtSymbol::QwtSymbol (QwtSymbol::Style *style*, const QBrush & *brush*, const QPen & *pen*, const QSize & *size*)

Constructor.

Parameters:

- style* Symbol Style
- brush* brush to fill the interior
- pen* outline pen
- size* size

6.82.3.3 QwtSymbol::~~QwtSymbol () [virtual]

Destructor.

6.82.4 Member Function Documentation

6.82.4.1 bool QwtSymbol::operator!= (const QwtSymbol &) const

!= operator

6.82.4.2 bool QwtSymbol::operator== (const QwtSymbol &) const [virtual]

== operator

6.82.4.3 QwtSymbol * QwtSymbol::clone () const [virtual]

Allocate and return a symbol with the same attributes

Returns:

Cloned symbol

6.82.4.4 void QwtSymbol::setSize (const QSize & *size*)

Set the symbol's size

Parameters:

size Size

6.82.4.5 void QwtSymbol::setSize (int *width*, int *height* = -1)

Specify the symbol's size.

If the 'h' parameter is left out or less than 0, and the 'w' parameter is greater than or equal to 0, the symbol size will be set to (w,w).

Parameters:

width Width

height Height (defaults to -1)

6.82.4.6 void QwtSymbol::setBrush (const QBrush & *brush*)

Assign a brush.

The brush is used to draw the interior of the symbol.

Parameters:

brush Brush

6.82.4.7 void QwtSymbol::setPen (const QPen & *pen*)

Assign a pen

The pen is used to draw the symbol's outline.

The width of non cosmetic pens is scaled according to the resolution of the paint device.

Parameters:

pen Pen

See also:

[pen\(\)](#), [setBrush\(\)](#), [QwtPainter::scaledPen\(\)](#)

6.82.4.8 void QwtSymbol::setStyle (QwtSymbol::Style *s*)

Specify the symbol style.

The following styles are defined:

NoSymbol No Style. The symbol cannot be drawn.

Ellipse Ellipse or circle

Rect Rectangle

Diamond Diamond

Triangle Triangle pointing upwards

DTriangle Triangle pointing downwards

UTriangle Triangle pointing upwards

LTriangle Triangle pointing left

RTriangle Triangle pointing right

Cross Cross (+)

XCross Diagonal cross (X)

HLine Horizontal line

VLine Vertical line

Star1 X combined with +

Star2 Six-pointed star

Hexagon Hexagon

Parameters:

s style

6.82.4.9 `const QBrush& QwtSymbol::brush () const` [inline]

Return Brush.

6.82.4.10 `const QPen& QwtSymbol::pen () const` [inline]

Return Pen.

6.82.4.11 `const QSize& QwtSymbol::size () const` [inline]

Return Size.

6.82.4.12 `Style QwtSymbol::style () const` [inline]

Return Style.

6.82.4.13 `void QwtSymbol::draw (QPainter * painter, const QPoint & pos) const`

Draw the symbol at a specified point.

Parameters:

painter Painter

pos Center of the symbol

6.82.4.14 `void QwtSymbol::draw (QPainter * p, int x, int y) const`

Draw the symbol at a point (x,y).

6.82.4.15 void QwtSymbol::draw (QPainter * *painter*, const QRect & *r*) const [virtual]

Draw the symbol into a bounding rectangle.

This function assumes that the painter has been initialized with brush and pen before. This allows a much more performant implementation when painting many symbols with the same brush and pen like in curves.

Parameters:

- painter* Painter
- r* Bounding rectangle

6.83 QwtText Class Reference

A class representing a text.

```
#include <qwt_text.h>
```

Public Types

- enum [TextFormat](#) {
 - AutoText** = 0,
 - PlainText**,
 - RichText**,
 - MathMLText**,
 - TeXText**,
 - OtherFormat** = 100 }
- enum [PaintAttribute](#) {
 - PaintCached** = 1,
 - PaintPacked** = 2,
 - PaintFiltered** = 1,
 - ClipPolygons** = 2,
 - PaintUsingTextFont** = 1,
 - PaintUsingTextColor** = 2,
 - PaintBackground** = 4 }
- enum [LayoutAttribute](#) { **MinimumLayout** = 1 }

Public Member Functions

- [QwtText](#) (const QString &=QString::null, [TextFormat](#) textFormat=AutoText)
- [QwtText](#) (const [QwtText](#) &)
- [~QwtText](#) ()
- [QwtText](#) & [operator=](#) (const [QwtText](#) &)
- int [operator==](#) (const [QwtText](#) &) const
- int [operator!=](#) (const [QwtText](#) &) const
- void [setText](#) (const QString &, [QwtText::TextFormat](#) textFormat=AutoText)
- QString [text](#) () const
- bool [isNull](#) () const

- bool [isEmpty](#) () const
- void [setFont](#) (const QFont &)
- QFont [font](#) () const
- QFont [usedFont](#) (const QFont &) const
- void [setRenderFlags](#) (int flags)
- int [renderFlags](#) () const
- void [setColor](#) (const QColor &)
- QColor [color](#) () const
- QColor [usedColor](#) (const QColor &) const
- void [setBackgroundPen](#) (const QPen &)
- QPen [backgroundPen](#) () const
- void [setBackgroundBrush](#) (const QBrush &)
- QBrush [backgroundBrush](#) () const
- void [setPaintAttribute](#) (PaintAttribute, bool on=true)
- bool [testPaintAttribute](#) (PaintAttribute) const
- void [setLayoutAttribute](#) (LayoutAttribute, bool on=true)
- bool [testLayoutAttribute](#) (LayoutAttribute) const
- int [heightForWidth](#) (int width, const QFont &=QFont()) const
- QSize [textSize](#) (const QFont &=QFont()) const
- void [draw](#) (QPainter *painter, const QRect &rect) const

Static Public Member Functions

- static const [QwtTextEngine](#) * [textEngine](#) (const QString &text, [QwtText::TextFormat](#)=AutoText)
- static const [QwtTextEngine](#) * [textEngine](#) ([QwtText::TextFormat](#))
- static void [setTextEngine](#) ([QwtText::TextFormat](#), [QwtTextEngine](#) *)

6.83.1 Detailed Description

A class representing a text.

A [QwtText](#) is a text including a set of attributes how to render it.

- Format

A text might include control sequences (f.e tags) describing how to render it. Each format (f.e MathML, TeX, Qt Rich Text) has its own set of control sequences, that can be handles by a [QwtTextEngine](#) for this format.
- Background

A text might have a background, defined by a QPen and QBrush to improve its visibility.
- Font

A text might have an individual font.
- Color

A text might have an individual color.
- Render Flags

Flags from Qt::AlignmentFlag and Qt::TextFlag used like in QPainter::drawText.

See also:

[QwtTextEngine](#), [QwtTextLabel](#)

6.83.2 Member Enumeration Documentation

6.83.2.1 enum [QwtText::TextFormat](#)

Text format.

The text format defines the [QwtTextEngine](#), that is used to render the text.

- [AutoText](#)

The text format is determined using [QwtTextEngine::mightRender](#) for all available text engines in increasing order > [PlainText](#). If none of the text engines can render the text is rendered like [PlainText](#).
- [PlainText](#)

Draw the text as it is, using a [QwtPlainTextEngine](#).
- [RichText](#)

Use the Scribe framework (Qt Rich Text) to render the text.
- [MathMLText](#)

Use a MathML (<http://en.wikipedia.org/wiki/MathML>) render engine to display the text. The Qwt MathML extension offers such an engine based on the MathML renderer of the Qt solutions package. Unfortunately it is only available for owners of a commercial Qt license.
- [TeXText](#)

Use a TeX (<http://en.wikipedia.org/wiki/TeX>) render engine to display the text.
- [OtherFormat](#)

The number of text formats can be extended using [setTextEngine](#). Formats >= [OtherFormat](#) are not used by Qwt.

See also:

[QwtTextEngine](#), [setTextEngine\(\)](#)

6.83.2.2 enum [QwtText::PaintAttribute](#)

Paint Attributes.

Font and color and background are optional attributes of a [QwtText](#). The paint attributes hold the information, if they are set.

- [PaintUsingTextFont](#)

The text has an individual font.
- [PaintUsingTextColor](#)

The text has an individual color.
- [PaintBackground](#)

The text has an individual background.

6.83.2.3 enum QwtText::LayoutAttribute

Layout Attributes.

The layout attributes affects some aspects of the layout of the text.

- MinimumLayout

Layout the text without its margins. This mode is useful if a text needs to be aligned accurately, like the tick labels of a scale. If [QwtTextEngine::textMargins](#) is not implemented for the format of the text, MinimumLayout has no effect.

6.83.3 Constructor & Destructor Documentation

6.83.3.1 QwtText::QwtText (const QString & *text* = QString::null, QwtText::TextFormat *textFormat* = AutoText)

Constructor

Parameters:

- text* Text content
- textFormat* Text format

6.83.3.2 QwtText::QwtText (const QwtText &)

Copy constructor.

6.83.3.3 QwtText::~~QwtText ()

Destructor.

6.83.4 Member Function Documentation

6.83.4.1 QwtText & QwtText::operator= (const QwtText &)

Assignment operator.

6.83.4.2 int QwtText::operator== (const QwtText &) const

Relational operator.

6.83.4.3 int QwtText::operator!= (const QwtText &) const

Relational operator.

6.83.4.4 void QwtText::setText (const QString & *text*, QwtText::TextFormat *textFormat* = AutoText)

Assign a new text content

Parameters:

- text* Text content

textFormat Text format

See also:

[text\(\)](#)

6.83.4.5 QString QwtText::text () const

Return the text.

See also:

[setText\(\)](#)

6.83.4.6 bool QwtText::isNull () const [inline]

Returns:

[text\(\).isNull\(\)](#)

6.83.4.7 bool QwtText::isEmpty () const [inline]

Returns:

[text\(\).isEmpty\(\)](#)

6.83.4.8 void QwtText::setFont (const QFont & font)

Set the font.

Parameters:

font Font

Note:

Setting the font might have no effect, when the text contains control sequences for setting fonts.

6.83.4.9 QFont QwtText::font () const

Return the font.

6.83.4.10 QFont QwtText::usedFont (const QFont & defaultFont) const

Return the font of the text, if it has one. Otherwise return defaultFont.

Parameters:

defaultFont Default font

See also:

[setFont\(\)](#), [font\(\)](#), [PaintAttributes](#)

6.83.4.11 void QwtText::setRenderFlags (int *renderFlags*)

Change the render flags.

The default setting is Qt::AlignCenter

Parameters:

renderFlags Bitwise OR of the flags used like in QPainter::drawText

See also:

[renderFlags\(\)](#), [QwtTextEngine::draw\(\)](#)

Note:

Some renderFlags might have no effect, depending on the text format.

6.83.4.12 int QwtText::renderFlags () const**Returns:**

Render flags

See also:

[setRenderFlags\(\)](#)

6.83.4.13 void QwtText::setColor (const QColor & *color*)

Set the pen color used for painting the text.

Parameters:

color Color

Note:

Setting the color might have no effect, when the text contains control sequences for setting colors.

6.83.4.14 QColor QwtText::color () const

Return the pen color, used for painting the text.

6.83.4.15 QColor QwtText::usedColor (const QColor & *defaultColor*) const

Return the color of the text, if it has one. Otherwise return defaultColor.

Parameters:

defaultColor Default color

See also:

[setColor\(\)](#), [color\(\)](#), PaintAttributes

6.83.4.16 void QwtText::setBackgroundPen (const QPen & *pen*)

Set the background pen

Parameters:

pen Background pen

See also:

[backgroundPen\(\)](#), [setBackgroundBrush\(\)](#)

6.83.4.17 QPen QwtText::backgroundPen () const**Returns:**

Background pen

See also:

[setBackgroundPen\(\)](#), [backgroundBrush\(\)](#)

6.83.4.18 void QwtText::setBackgroundBrush (const QBrush & *brush*)

Set the background brush

Parameters:

brush Background brush

See also:

[backgroundBrush\(\)](#), [setBackgroundPen\(\)](#)

6.83.4.19 QBrush QwtText::backgroundBrush () const**Returns:**

Background brush

See also:

[setBackgroundBrush\(\)](#), [backgroundPen\(\)](#)

6.83.4.20 void QwtText::setPaintAttribute ([PaintAttribute](#) *attribute*, bool *on* = true)

Change a paint attribute

Parameters:

attribute Paint attribute

on On/Off

Note:

Used by [setFont\(\)](#), [setColor\(\)](#), [setBackgroundPen\(\)](#) and [setBackgroundBrush\(\)](#)

See also:

[testPaintAttribute\(\)](#)

6.83.4.21 bool QwtText::testPaintAttribute (PaintAttribute attribute) const

Test a paint attribute

Parameters:

attribute Paint attribute

Returns:

true, if attribute is enabled

See also:

[setPaintAttribute\(\)](#)

6.83.4.22 void QwtText::setLayoutAttribute (LayoutAttribute attribute, bool on = true)

Change a layout attribute

Parameters:

attribute Layout attribute

on On/Off

See also:

[testLayoutAttribute\(\)](#)

6.83.4.23 bool QwtText::testLayoutAttribute (LayoutAttribute attribute) const

Test a layout attribute

Parameters:

attribute Layout attribute

Returns:

true, if attribute is enabled

See also:

[setLayoutAttribute\(\)](#)

6.83.4.24 `int QwtText::heightForWidth (int width, const QFont & defaultFont = QFont ()) const`

Find the height for a given width

Parameters:

defaultFont Font, used for the calculation if the text has no font

width Width

Returns:

Calculated height

6.83.4.25 `QSize QwtText::textSize (const QFont & defaultFont = QFont ()) const`

Returns the size, that is needed to render text

Parameters:

defaultFont Font of the text

Returns:

Caluclated size

6.83.4.26 `void QwtText::draw (QPainter * painter, const QRect & rect) const`

Draw a text into a rectangle

Parameters:

painter Painter

rect Rectangle

6.83.4.27 `const QwtTextEngine * QwtText::textEngine (const QString & text, QwtText::TextFormat format = AutoText) [static]`

Find the text engine for a text format

In case of `QwtText::AutoText` the first text engine (beside `QwtPlainTextEngine`) is returned, where `QwtTextEngine::mightRender` returns true. If there is none `QwtPlainTextEngine` is returned.

If no text engine is registered for the format `QwtPlainTextEngine` is returned.

Parameters:

text Text, needed in case of `AutoText`

format Text format

6.83.4.28 `const QwtTextEngine * QwtText::textEngine (QwtText::TextFormat format)`
[static]

Find the text engine for a text format.

textEngine can be used to find out if a text format is supported. F.e, if one wants to use MathML labels, the MathML renderer from the commercial Qt solutions package might be required, that is not available in Qt Open Source Edition environments.

Parameters:

format Text format

Returns:

The text engine, or NULL if no engine is available.

6.83.4.29 `void QwtText::setTextEngine (QwtText::TextFormat format, QwtTextEngine * engine)`
[static]

Assign/Replace a text engine for a text format

With setTextEngine it is possible to extend Qwt with other types of text formats.

Owner of a commercial Qt license can build the qwtmathml library, that is based on the MathML renderer, that is included in MML Widget component of the Qt solutions package.

For QwtText::PlainText it is not allowed to assign a engine == NULL.

Parameters:

format Text format

engine Text engine

See also:

[QwtMathMLTextEngine](#)

Warning:


Using QwtText::AutoText does nothing.

6.84 QwtTextEngine Class Reference

Abstract base class for rendering text strings.

```
#include <qwt_text_engine.h>
```

Inheritance diagram for QwtTextEngine:



Public Member Functions

- virtual [~QwtTextEngine](#) ()
- virtual int [heightForWidth](#) (const QFont &font, int flags, const QString &text, int width) const=0
- virtual QSize [textSize](#) (const QFont &font, int flags, const QString &text) const=0
- virtual bool [mightRender](#) (const QString &text) const =0
- virtual void [textMargins](#) (const QFont &font, const QString &text, int &left, int &right, int &top, int &bottom) const =0
- virtual void [draw](#) (QPainter *painter, const QRect &rect, int flags, const QString &text) const=0

Protected Member Functions

- [QwtTextEngine](#) ()

6.84.1 Detailed Description

Abstract base class for rendering text strings.

A text engine is responsible for rendering texts for a specific text format. They are used by [QwtText](#) to render a text.

[QwtPlainTextEngine](#) and [QwtRichTextEngine](#) are part of the Qwt library.

[QwtMathMLTextEngine](#) can be found in Qwt MathML extension, that needs the MathML renderer of the Qt solutions package. Unfortunately it is only available with a commercial Qt license.

See also:

[QwtText::setTextEngine\(\)](#)

6.84.2 Constructor & Destructor Documentation

6.84.2.1 [QwtTextEngine::~~QwtTextEngine](#) () [virtual]

Destructor.

6.84.2.2 [QwtTextEngine::QwtTextEngine](#) () [protected]

Constructor.

6.84.3 Member Function Documentation

6.84.3.1 [virtual int QwtTextEngine::heightForWidth](#) (const QFont & *font*, int *flags*, const QString & *text*, int *width*) const [pure virtual]

Find the height for a given width

Parameters:

font Font of the text

flags Bitwise OR of the flags used like in [QPainter::drawText](#)

text Text to be rendered

width Width

Returns:

Calculated height

Implemented in [QwtPlainTextEngine](#), [QwtRichTextEngine](#), and [QwtMathMLTextEngine](#).

6.84.3.2 virtual QSize QwtTextEngine::textSize (const QFont & font, int flags, const QString & text) const [pure virtual]

Returns the size, that is needed to render text

Parameters:

font Font of the text

flags Bitwise OR of the flags like in for QPainter::drawText

text Text to be rendered

Returns:

Calculated size

Implemented in [QwtPlainTextEngine](#), [QwtRichTextEngine](#), and [QwtMathMLTextEngine](#).

6.84.3.3 virtual bool QwtTextEngine::mightRender (const QString & text) const [pure virtual]

Test if a string can be rendered by this text engine

Parameters:

text Text to be tested

Returns:

true, if it can be rendered

Implemented in [QwtPlainTextEngine](#), [QwtRichTextEngine](#), and [QwtMathMLTextEngine](#).

6.84.3.4 virtual void QwtTextEngine::textMargins (const QFont & font, const QString & text, int & left, int & right, int & top, int & bottom) const [pure virtual]

Return margins around the texts

The textSize might include margins around the text, like QFontMetrics::descent. In situations where texts need to be aligned in detail, knowing these margins might improve the layout calculations.

Parameters:

font Font of the text

text Text to be rendered

left Return value for the left margin

right Return value for the right margin

top Return value for the top margin

bottom Return value for the bottom margin

Implemented in [QwtPlainTextEngine](#), [QwtRichTextEngine](#), and [QwtMathMLTextEngine](#).

6.84.3.5 virtual void QwtTextEngine::draw (QPainter * *painter*, const QRect & *rect*, int *flags*, const QString & *text*) const [pure virtual]

Draw the text in a clipping rectangle

Parameters:

- painter* Painter
- rect* Clipping rectangle
- flags* Bitwise OR of the flags like in for QPainter::drawText
- text* Text to be rendered


Implemented in [QwtPlainTextEngine](#), [QwtRichTextEngine](#), and [QwtMathMLTextEngine](#).

6.85 QwtTextLabel Class Reference

A Widget which displays a [QwtText](#).

```
#include <qwt_text_label.h>
```

Inheritance diagram for QwtTextLabel:



Public Slots

- void [setText](#) (const QString &, [QwtText::TextFormat](#) textFormat=QwtText::AutoText)
- virtual void [setText](#) (const [QwtText](#) &)
- void [clear](#) ()

Public Member Functions

- [QwtTextLabel](#) (QWidget *parent=NULL)
- [QwtTextLabel](#) (const [QwtText](#) &, QWidget *parent=NULL)
- virtual [~QwtTextLabel](#) ()
- const [QwtText](#) & [text](#) () const
- int [indent](#) () const
- void [setIndent](#) (int)
- int [margin](#) () const
- void [setMargin](#) (int)
- virtual QSize [sizeHint](#) () const
- virtual QSize [minimumSizeHint](#) () const
- virtual int [heightForWidth](#) (int) const
- QRect [textRect](#) () const

Protected Member Functions

- virtual void [paintEvent](#) (QPaintEvent *e)
- virtual void [drawContents](#) (QPainter *)
- virtual void [drawText](#) (QPainter *, const QRect &)

6.85.1 Detailed Description

A Widget which displays a [QwtText](#).

6.85.2 Constructor & Destructor Documentation

6.85.2.1 QwtTextLabel::QwtTextLabel (QWidget * *parent* = NULL) [explicit]

Constructs an empty label.

Parameters:

parent Parent widget

6.85.2.2 QwtTextLabel::QwtTextLabel (const [QwtText](#) & *text*, QWidget * *parent* = NULL) [explicit]

Constructs a label that displays the text, text

Parameters:

parent Parent widget

text Text

6.85.2.3 QwtTextLabel::~~QwtTextLabel () [virtual]

Destructor.

6.85.3 Member Function Documentation

6.85.3.1 void QwtTextLabel::setText (const QString & *text*, [QwtText::TextFormat](#) *textFormat* = [QwtText::AutoText](#)) [slot]

Change the label's text, keeping all other [QwtText](#) attributes

Parameters:

text New text

textFormat Format of text

See also:

[QwtText](#)

6.85.3.2 void QwtTextLabel::setText (const [QwtText](#) & *text*) [virtual, slot]

Change the label's text

Parameters:

text New text

Reimplemented in [QwtLegendItem](#).

6.85.3.3 void QwtTextLabel::clear () [slot]

Clear the text and all [QwtText](#) attributes.

6.85.3.4 const [QwtText](#) & QwtTextLabel::text () const

Return the text.

6.85.3.5 int QwtTextLabel::indent () const

Return label's text indent in pixels.

6.85.3.6 void QwtTextLabel::setIndent (int *indent*)

Set label's text indent in pixels

Parameters:

indent Indentation in pixels

6.85.3.7 int QwtTextLabel::margin () const

Return label's text indent in pixels.

6.85.3.8 void QwtTextLabel::setMargin (int *margin*)

Set label's margin in pixels

Parameters:

margin Margin in pixels

6.85.3.9 QSize QwtTextLabel::sizeHint () const [virtual]

Return label's margin in pixels.

Reimplemented in [QwtLegendItem](#).

6.85.3.10 QSize QwtTextLabel::minimumSizeHint () const [virtual]

Return a minimum size hint.

6.85.3.11 `int QwtTextLabel::heightForWidth (int width) const` [virtual]

Returns the preferred height for this widget, given the width.

Parameters:

width Width

6.85.3.12 `QRect QwtTextLabel::textRect () const`

Calculate the rect for the text in widget coordinates

Returns:

Text rect

6.85.3.13 `void QwtTextLabel::paintEvent (QPaintEvent * event)` [protected, virtual]

Qt paint event

Parameters:

event Paint event

Reimplemented in [QwtLegendItem](#).

6.85.3.14 `void QwtTextLabel::drawContents (QPainter *)` [protected, virtual]

Redraw the text and focus indicator.

6.85.3.15 `void QwtTextLabel::drawText (QPainter *, const QRect &)` [protected, virtual]

Redraw the text.


Reimplemented in [QwtLegendItem](#).

6.86 QwtThermo Class Reference

The Thermometer Widget.

```
#include <qwt_thermo.h>
```

Inheritance diagram for QwtThermo:

**Public Types**

- enum `ScalePos` {

NoScale,
LeftScale,
RightScale,
TopScale,
BottomScale,
NoScale,
LeftScale,
RightScale,
TopScale,
BottomScale }

Public Slots

- void [setValue](#) (double val)

Public Member Functions

- [QwtThermo](#) (QWidget *parent=NULL)
- virtual [~QwtThermo](#) ()
- void [setOrientation](#) (Qt::Orientation o, ScalePos s)
- void [setScalePosition](#) (ScalePos s)
- ScalePos [scalePosition](#) () const
- void [setBorderWidth](#) (int w)
- int [borderWidth](#) () const
- void [setFillBrush](#) (const QBrush &b)
- const QBrush & [fillBrush](#) () const
- void [setFillColor](#) (const QColor &c)
- const QColor & [fillColor](#) () const
- void [setAlarmBrush](#) (const QBrush &b)
- const QBrush & [alarmBrush](#) () const
- void [setAlarmColor](#) (const QColor &c)
- const QColor & [alarmColor](#) () const
- void [setAlarmLevel](#) (double v)
- double [alarmLevel](#) () const
- void [setAlarmEnabled](#) (bool tf)
- bool [alarmEnabled](#) () const
- void [setPipeWidth](#) (int w)
- int [pipeWidth](#) () const
- void [setMaxValue](#) (double v)
- double [maxValue](#) () const
- void [setMinValue](#) (double v)
- double [minValue](#) () const
- double [value](#) () const
- void [setRange](#) (double vmin, double vmax, bool lg=false)
- void [setMargin](#) (int m)
- virtual QSize [sizeHint](#) () const
- virtual QSize [minimumSizeHint](#) () const
- void [setScaleDraw](#) (QwtScaleDraw *)
- const QwtScaleDraw * [scaleDraw](#) () const

Protected Member Functions

- void [draw](#) (QPainter *p, const QRect &update_rect)
- void [drawThermo](#) (QPainter *p)
- void [layoutThermo](#) (bool update=true)
- virtual void [scaleChange](#) ()
- virtual void [fontChange](#) (const QFont &oldFont)
- virtual void [paintEvent](#) (QPaintEvent *e)
- virtual void [resizeEvent](#) (QResizeEvent *e)
- [QwtScaleDraw](#) * [scaleDraw](#) ()

6.86.1 Detailed Description

The Thermometer Widget.

[QwtThermo](#) is a widget which displays a value in an interval. It supports:

- a horizontal or vertical layout;
- a range;
- a scale;
- an alarm level.

By default, the scale and range run over the same interval of values. [QwtAbstractScale::setScale\(\)](#) changes the interval of the scale and allows easy conversion between physical units.

The example shows how to make the scale indicate in degrees Fahrenheit and to set the value in degrees Kelvin:

```
#include <qapplication.h>
#include <qwt_thermo.h>

double Kelvin2Fahrenheit(double kelvin)
{
    // see http://en.wikipedia.org/wiki/Kelvin
    return 1.8*kelvin - 459.67;
}

int main(int argc, char **argv)
{
    const double minKelvin = 0.0;
    const double maxKelvin = 500.0;

    QApplication a(argc, argv);
    QwtThermo t;
    t.setRange(minKelvin, maxKelvin);
    t.setScale(Kelvin2Fahrenheit(minKelvin), Kelvin2Fahrenheit(maxKelvin));
    // set the value in Kelvin but the scale displays in Fahrenheit
    // 273.15 Kelvin = 0 Celsius = 32 Fahrenheit
    t.setValue(273.15);
    a.setMainWidget(&t);
    t.show();
    return a.exec();
}
```

6.86.2 Constructor & Destructor Documentation

6.86.2.1 QwtThermo::QwtThermo (QWidget * *parent* = NULL) [explicit]

Constructor

Parameters:

parent Parent widget

6.86.2.2 QwtThermo::~~QwtThermo () [virtual]

Destructor.

6.86.3 Member Function Documentation

6.86.3.1 void QwtThermo::setOrientation (Qt::Orientation *o*, ScalePos *s*)

Set the thermometer orientation and the scale position.

The scale position NoScale disables the scale.

Parameters:

- o* orientation. Possible values are Qt::Horizontal and Qt::Vertical. The default value is Qt::Vertical.
- s* Position of the scale. The default value is NoScale.

A valid combination of scale position and orientation is enforced:

- a horizontal thermometer can have the scale positions TopScale, BottomScale or NoScale;
- a vertical thermometer can have the scale positions LeftScale, RightScale or NoScale;
- an invalid scale position will default to NoScale.

See also:

[setScalePosition\(\)](#)

6.86.3.2 void QwtThermo::setScalePosition (ScalePos *scalePos*)

Change the scale position (and thermometer orientation).

Parameters:

scalePos Position of the scale.

A valid combination of scale position and orientation is enforced:

- if the new scale position is LeftScale or RightScale, the scale orientation will become Qt::Vertical;
- if the new scale position is BottomScale or TopScale, the scale orientation will become Qt::Horizontal;
- if the new scale position is NoScale, the scale orientation will not change.

See also:

[setOrientation\(\)](#), [scalePosition\(\)](#)

6.86.3.3 QwtThermo::ScalePos QwtThermo::scalePosition () const

Return the scale position.

See also:

[setScalePosition\(\)](#)

6.86.3.4 void QwtThermo::setBorderWidth (int *width*)

Set the border width of the pipe.

Parameters:

width Border width

See also:

[borderWidth\(\)](#)

6.86.3.5 int QwtThermo::borderWidth () const

Return the border width of the thermometer pipe.

See also:

[setBorderWidth\(\)](#)

6.86.3.6 void QwtThermo::setFillBrush (const QBrush & *brush*)

Change the brush of the liquid.

Parameters:

brush New brush. The default brush is solid black.

See also:

[fillBrush\(\)](#)

6.86.3.7 const QBrush & QwtThermo::fillBrush () const

Return the liquid brush.

See also:

[setFillBrush\(\)](#)

6.86.3.8 void QwtThermo::setFillColor (const QColor & *c*)

Change the color of the liquid.

Parameters:

c New color. The default color is black.

See also:

[fillColor\(\)](#)

6.86.3.9 const QColor & QwtThermo::fillColor () const

Return the liquid color.

See also:

[setFillColor\(\)](#)

6.86.3.10 void QwtThermo::setAlarmBrush (const QBrush & brush)

Specify the liquid brush above the alarm threshold.

Parameters:

brush New brush. The default is solid white.

See also:

[alarmBrush\(\)](#)

6.86.3.11 const QBrush & QwtThermo::alarmBrush () const

Return the liquid brush above the alarm threshold.

See also:

[setAlarmBrush\(\)](#)

6.86.3.12 void QwtThermo::setAlarmColor (const QColor & c)

Specify the liquid color above the alarm threshold.

Parameters:

c New color. The default is white.

6.86.3.13 const QColor & QwtThermo::alarmColor () const

Return the liquid color above the alarm threshold.

6.86.3.14 void QwtThermo::setAlarmLevel (double level)

Specify the alarm threshold.

Parameters:

level Alarm threshold

See also:

[alarmLevel\(\)](#)

6.86.3.15 double QwtThermo::alarmLevel () const

Return the alarm threshold.

See also:

[setAlarmLevel\(\)](#)

6.86.3.16 void QwtThermo::setAlarmEnabled (bool *tf*)

Enable or disable the alarm threshold.

Parameters:

tf true (disabled) or false (enabled)

6.86.3.17 bool QwtThermo::alarmEnabled () const

Return if the alarm threshold is enabled or disabled.

6.86.3.18 void QwtThermo::setPipeWidth (int *width*)

Change the width of the pipe.

Parameters:

width Width of the pipe

See also:

[pipeWidth\(\)](#)

6.86.3.19 int QwtThermo::pipeWidth () const

Return the width of the pipe.

See also:

[setPipeWidth\(\)](#)

6.86.3.20 void QwtThermo::setMaxValue (double *max*)

Set the maximum value.

Parameters:

max Maximum value

See also:

[maxValue\(\)](#), [setMinValue\(\)](#)

6.86.3.21 double QwtThermo::maxValue () const

Return the maximum value.

6.86.3.22 void QwtThermo::setMinValue (double *min*)

Set the minimum value.

Parameters:

min Minimum value

See also:

[minValue\(\)](#), [setMaxValue\(\)](#)

6.86.3.23 double QwtThermo::minValue () const

Return the minimum value.

6.86.3.24 double QwtThermo::value () const

Return the value.

6.86.3.25 void QwtThermo::setRange (double *vmin*, double *vmax*, bool *logarithmic* = false)

Set the range.

Parameters:

vmin value corresponding lower or left end of the thermometer

vmax value corresponding to the upper or right end of the thermometer

logarithmic logarithmic mapping, true or false

6.86.3.26 void QwtThermo::setMargin (int *m*)

Specify the distance between the pipe's endpoints and the widget's border.

The margin is used to leave some space for the scale labels. If a large font is used, it is advisable to adjust the margins.

Parameters:

m New Margin. The default values are 10 for horizontal orientation and 20 for vertical orientation.

Warning:

The margin has no effect if the scale is disabled.

This function is a NOOP because margins are determined automatically.

6.86.3.27 QSize QwtThermo::sizeHint () const [virtual]**Returns:**

the minimum size hint

See also:

[minimumSizeHint\(\)](#)

6.86.3.28 `QSize QwtThermo::minimumSizeHint () const` [virtual]

Return a minimum size hint.

Warning:

The return value depends on the font and the scale.

See also:

[sizeHint\(\)](#)

6.86.3.29 `void QwtThermo::setScaleDraw (QwtScaleDraw * scaleDraw)`

Set a scale draw.

For changing the labels of the scales, it is necessary to derive from [QwtScaleDraw](#) and overload [QwtScaleDraw::label\(\)](#).

Parameters:

scaleDraw ScaleDraw object, that has to be created with `new` and will be deleted in `~QwtThermo` or the next call of [setScaleDraw\(\)](#).

6.86.3.30 `const QwtScaleDraw * QwtThermo::scaleDraw () const`**Returns:**

the scale draw of the thermo

See also:

[setScaleDraw\(\)](#)

6.86.3.31 `void QwtThermo::setValue (double value)` [slot]

Set the current value.

Parameters:

value New Value

See also:

[value\(\)](#)

6.86.3.32 `void QwtThermo::draw (QPainter * painter, const QRect & rect)` [protected]

Draw the whole [QwtThermo](#).

Parameters:

painter Painter

rect Update rectangle

6.86.3.33 void QwtThermo::drawThermo (QPainter * *painter*) [protected]

Redraw the liquid in thermometer pipe.

Parameters:

painter Painter

6.86.3.34 void QwtThermo::layoutThermo (bool *update_geometry* = true) [protected]

Recalculate the [QwtThermo](#) geometry and layout based on the QwtThermo::rect() and the fonts.

Parameters:

update_geometry notify the layout system and call update to redraw the scale

6.86.3.35 void QwtThermo::scaleChange () [protected, virtual]

Notify a scale change.

Reimplemented from [QwtAbstractScale](#).

6.86.3.36 void QwtThermo::fontChange (const QFont & *oldFont*) [protected, virtual]

Notify a font change.

6.86.3.37 void QwtThermo::paintEvent (QPaintEvent * *event*) [protected, virtual]

Qt paint event. event Paint event

6.86.3.38 void QwtThermo::resizeEvent (QResizeEvent * *e*) [protected, virtual]

Qt resize event handler.

6.86.3.39 [QwtScaleDraw](#) * QwtThermo::scaleDraw () [protected]

Returns:

the scale draw of the thermo

See also:


[setScaleDraw\(\)](#)

6.87 QwtWheel Class Reference

The Wheel Widget.

```
#include <qwt_wheel.h>
```

Inheritance diagram for QwtWheel:



Public Member Functions

- [QwtWheel](#) (QWidget *parent=NULL)
- virtual [~QwtWheel](#) ()
- virtual void [setOrientation](#) (Qt::Orientation)
- double [totalAngle](#) () const
- double [viewAngle](#) () const
- int [tickCnt](#) () const
- int [internalBorder](#) () const
- double [mass](#) () const
- void [setTotalAngle](#) (double angle)
- void [setTickCnt](#) (int cnt)
- void [setViewAngle](#) (double angle)
- void [setInternalBorder](#) (int width)
- void [setMass](#) (double val)
- void [setWheelWidth](#) (int w)
- virtual QSize [sizeHint](#) () const
- virtual QSize [minimumSizeHint](#) () const

Protected Member Functions

- virtual void [resizeEvent](#) (QResizeEvent *e)
- virtual void [paintEvent](#) (QPaintEvent *e)
- void [layoutWheel](#) (bool update=true)
- void [draw](#) (QPainter *p, const QRect &update_rect)
- void [drawWheel](#) (QPainter *p, const QRect &r)
- void [drawWheelBackground](#) (QPainter *p, const QRect &r)
- void [setColorArray](#) ()
- virtual void [valueChange](#) ()
- virtual void [paletteChange](#) (const QPalette &)
- virtual double [getValue](#) (const QPoint &p)
- virtual void [getScrollMode](#) (const QPoint &p, int &scrollMode, int &direction)

6.87.1 Detailed Description

The Wheel Widget.

The wheel widget can be used to change values over a very large range in very small steps. Using the `setMass` member, it can be configured as a flywheel.

See also:

The radio example.

6.87.2 Constructor & Destructor Documentation

6.87.2.1 QwtWheel::QwtWheel (QWidget * *parent* = NULL) [explicit]

Constructor.

6.87.2.2 QwtWheel::~~QwtWheel () [virtual]

Destructor.

6.87.3 Member Function Documentation

6.87.3.1 void QwtWheel::setOrientation (Qt::Orientation *o*) [virtual]

Set the wheel's orientation.

Parameters:

o Orientation. Allowed values are Qt::Horizontal and Qt::Vertical. Defaults to Qt::Horizontal.

See also:

[QwtAbstractSlider::orientation\(\)](#)

Reimplemented from [QwtAbstractSlider](#).

6.87.3.2 double QwtWheel::totalAngle () const

Returns:

Total angle which the wheel can be turned.

See also:

[setTotalAngle\(\)](#)

6.87.3.3 double QwtWheel::viewAngle () const

Returns:

Visible portion of the wheel

See also:

[setViewAngle\(\)](#), [totalAngle\(\)](#)

6.87.3.4 int QwtWheel::tickCnt () const

Returns:

Number of grooves in the wheel's surface.

See also:

[setTickCnt\(\)](#)

6.87.3.5 int QwtWheel::internalBorder () const**Returns:**

Internal border width of the wheel.

See also:

[setInternalBorder\(\)](#)

6.87.3.6 double QwtWheel::mass () const [virtual]**Returns:**

mass

Reimplemented from [QwtAbstractSlider](#).

6.87.3.7 void QwtWheel::setTotalAngle (double *angle*)

Set the total angle which the wheel can be turned.

One full turn of the wheel corresponds to an angle of 360 degrees. A total angle of $n \times 360$ degrees means that the wheel has to be turned n times around its axis to get from the minimum value to the maximum value.

The default setting of the total angle is 360 degrees.

Parameters:

angle total angle in degrees

See also:

[totalAngle\(\)](#)

6.87.3.8 void QwtWheel::setTickCnt (int *cnt*)

Adjust the number of grooves in the wheel's surface.

The number of grooves is limited to $6 \leq cnt \leq 50$. Values outside this range will be clipped. The default value is 10.

Parameters:

cnt Number of grooves per 360 degrees

See also:

[tickCnt\(\)](#)

6.87.3.9 void QwtWheel::setViewAngle (double *angle*)

Specify the visible portion of the wheel.

You may use this function for fine-tuning the appearance of the wheel. The default value is 175 degrees. The value is limited from 10 to 175 degrees.

Parameters:

angle Visible angle in degrees

See also:

[viewAngle\(\)](#), [setTotalAngle\(\)](#)

6.87.3.10 void QwtWheel::setInternalBorder (int *w*)

Set the internal border width of the wheel.

The internal border must not be smaller than 1 and is limited in dependence on the wheel's size. Values outside the allowed range will be clipped.

The internal border defaults to 2.

Parameters:

w border width

See also:

[internalBorder\(\)](#)

6.87.3.11 void QwtWheel::setMass (double *val*) [virtual]

Set the mass of the wheel.

Assigning a mass turns the wheel into a flywheel.

Parameters:

val the wheel's mass

Reimplemented from [QwtAbstractSlider](#).

6.87.3.12 void QwtWheel::setWheelWidth (int *w*)

Set the width of the wheel.

Corresponds to the wheel height for horizontal orientation, and the wheel width for vertical orientation.

Parameters:

w the wheel's width

6.87.3.13 QSize QwtWheel::sizeHint () const [virtual]**Returns:**

a size hint

6.87.3.14 `QSize QwtWheel::minimumSizeHint () const` [virtual]

Return a minimum size hint.

Warning:

The return value is based on the wheel width.

6.87.3.15 `void QwtWheel::resizeEvent (QResizeEvent * e)` [protected, virtual]

Qt Resize Event.

6.87.3.16 `void QwtWheel::paintEvent (QPaintEvent * e)` [protected, virtual]

Qt Paint Event.

6.87.3.17 `void QwtWheel::layoutWheel (bool update = true)` [protected]

Recalculate the slider's geometry and layout based on.

6.87.3.18 `void QwtWheel::draw (QPainter * painter, const QRect & update_rect)` [protected]

Redraw panel and wheel

Parameters:

painter Painter

6.87.3.19 `void QwtWheel::drawWheel (QPainter * painter, const QRect & r)` [protected]

Redraw the wheel.

Parameters:

painter painter

r contents rectangle

6.87.3.20 `void QwtWheel::drawWheelBackground (QPainter * painter, const QRect & r)`
[protected]

Draw the Wheel's background gradient

Parameters:

painter Painter

r Bounding rectangle

6.87.3.21 `void QwtWheel::setColorArray ()` [protected]

Set up the color array for the background pixmap.

6.87.3.22 void QwtWheel::valueChange () [protected, virtual]

Notify value change.

Reimplemented from [QwtAbstractSlider](#).

6.87.3.23 void QwtWheel::paletteChange (const QPalette &) [protected, virtual]

Call update() when the palette changes.

6.87.3.24 double QwtWheel::getValue (const QPoint & p) [protected, virtual]

Determine the value corresponding to a specified point.

Implements [QwtAbstractSlider](#).

6.87.3.25 void QwtWheel::getScrollMode (const QPoint & p, int & scrollMode, int & direction) [protected, virtual]

Determine the scrolling mode and direction corresponding to a specified point.

Parameters:

- p* point
- scrollMode* scrolling mode
- direction* direction


Implements [QwtAbstractSlider](#).

7 Qwt User's Guide File Documentation

7.1 qwt_double_rect.h File Reference

```
#include "qwt_global.h"
#include "qwt_array.h"
#include <QPointF>
#include <QSizeF>
#include <QRectF>
```

Include dependency graph for qwt_double_rect.h:



Defines

- `#define QWT_DOUBLE_RECT_H 1`

Typedefs

- typedef `QPointF` [QwtDoublePoint](#)
- typedef `QSizeF` [QwtDoubleSize](#)
- typedef `QRectF` [QwtDoubleRect](#)

7.1.1 Detailed Description

7.1.2 Typedef Documentation

7.1.2.1 `QPointF` [QwtDoublePoint](#)

This is a typedef, see Trolltech Documentation for `QPointF` in QT assistant 4.x. As soon as Qt3 compatibility is dropped this typedef will disappear.

7.1.2.2 `QRectF` [QwtDoubleRect](#)

This is a typedef, see Trolltech Documentation for `QRectF` in QT assistant 4.x. As soon as Qt3 compatibility is dropped this typedef will disappear.


7.1.2.3 `QSizeF` [QwtDoubleSize](#)

This is a typedef, see Trolltech Documentation for `QSizeF` in QT assistant 4.x. As soon as Qt3 compatibility is dropped this typedef will disappear.

7.2 qwt_plot_dict.h File Reference

```
#include "qwt_global.h"
#include "qwt_plot_item.h"
#include <qlist.h>
```

Include dependency graph for `qwt_plot_dict.h`:



Classes

- class [QwtPlotDict](#)
A dictionary for plot items.

Typedefs

- typedef `QList< QwtPlotItem * >::ConstIterator` [QwtPlotItemIterator](#)
- typedef `QList< QwtPlotItem * >` [QwtPlotItemList](#)

7.2.1 Detailed Description

7.2.2 Typedef Documentation

7.2.2.1 typedef `QList< QwtPlotItem * >` [QwtPlotItemList](#)

See QT 4.x assistant documentation for QList.

8 Qwt User's Guide Page Documentation

8.1 Qwt License, Version 1.0

Qwt License
Version 1.0, January 1, 2003

The Qwt library and included programs are provided under the terms of the GNU LESSER GENERAL PUBLIC LICENSE (LGPL) with the following exceptions:

1. Widgets that are subclassed from Qwt widgets do not constitute a derivative work.

2. Static linking of applications and widgets to the Qwt library does not constitute a derivative work and does not require the author to provide source code for the application or widget, use the shared Qwt libraries, or link their applications or widgets against a user-supplied version of Qwt.

If you link the application or widget to a modified version of Qwt, then the changes to Qwt must be provided under the terms of the LGPL in sections 1, 2, and 4.

3. You do not have to provide a copy of the Qwt license with programs that are linked to the Qwt library, nor do you have to identify the Qwt license in your program or documentation as required by section 6 of the LGPL.

However, programs must still identify their use of Qwt. The following example statement can be included in user documentation to satisfy this requirement:

```
[program/widget] is based in part on the work of
the Qwt project (http://qwt.sf.net).
```

GNU LESSER GENERAL PUBLIC LICENSE
Version 2.1, February 1999

Copyright (C) 1991, 1999 Free Software Foundation, Inc.
59 Temple Place, Suite 330, Boston, MA 02111-1307 USA
Everyone is permitted to copy and distribute verbatim copies
of this license document, but changing it is not allowed.

[This is the first released version of the Lesser GPL. It also counts
as the successor of the GNU Library Public License, version 2, hence
the version number 2.1.]

Preamble

The licenses for most software are designed to take away your
freedom to share and change it. By contrast, the GNU General Public
Licenses are intended to guarantee your freedom to share and change
free software--to make sure the software is free for all its users.

This license, the Lesser General Public License, applies to some
specially designated software packages--typically libraries--of the
Free Software Foundation and other authors who decide to use it. You
can use it too, but we suggest you first think carefully about whether
this license or the ordinary General Public License is the better
strategy to use in any particular case, based on the explanations below.

When we speak of free software, we are referring to freedom of use,
not price. Our General Public Licenses are designed to make sure that
you have the freedom to distribute copies of free software (and charge
for this service if you wish); that you receive source code or can get
it if you want it; that you can change the software and use pieces of
it in new free programs; and that you are informed that you can do
these things.

To protect your rights, we need to make restrictions that forbid
distributors to deny you these rights or to ask you to surrender these
rights. These restrictions translate to certain responsibilities for

you if you distribute copies of the library or if you modify it.

For example, if you distribute copies of the library, whether gratis or for a fee, you must give the recipients all the rights that we gave you. You must make sure that they, too, receive or can get the source code. If you link other code with the library, you must provide complete object files to the recipients, so that they can relink them with the library after making changes to the library and recompiling it. And you must show them these terms so they know their rights.

We protect your rights with a two-step method: (1) we copyright the library, and (2) we offer you this license, which gives you legal permission to copy, distribute and/or modify the library.

To protect each distributor, we want to make it very clear that there is no warranty for the free library. Also, if the library is modified by someone else and passed on, the recipients should know that what they have is not the original version, so that the original author's reputation will not be affected by problems that might be introduced by others.

Finally, software patents pose a constant threat to the existence of any free program. We wish to make sure that a company cannot effectively restrict the users of a free program by obtaining a restrictive license from a patent holder. Therefore, we insist that any patent license obtained for a version of the library must be consistent with the full freedom of use specified in this license.

Most GNU software, including some libraries, is covered by the ordinary GNU General Public License. This license, the GNU Lesser General Public License, applies to certain designated libraries, and is quite different from the ordinary General Public License. We use this license for certain libraries in order to permit linking those libraries into non-free programs.

When a program is linked with a library, whether statically or using a shared library, the combination of the two is legally speaking a combined work, a derivative of the original library. The ordinary General Public License therefore permits such linking only if the entire combination fits its criteria of freedom. The Lesser General Public License permits more lax criteria for linking other code with the library.

We call this license the "Lesser" General Public License because it does Less to protect the user's freedom than the ordinary General Public License. It also provides other free software developers Less of an advantage over competing non-free programs. These disadvantages are the reason we use the ordinary General Public License for many libraries. However, the Lesser license provides advantages in certain special circumstances.

For example, on rare occasions, there may be a special need to encourage the widest possible use of a certain library, so that it becomes a de-facto standard. To achieve this, non-free programs must be allowed to use the library. A more frequent case is that a free library does the same job as widely used non-free libraries. In this case, there is little to gain by limiting the free library to free software only, so we use the Lesser General Public License.

In other cases, permission to use a particular library in non-free programs enables a greater number of people to use a large body of free software. For example, permission to use the GNU C Library in non-free programs enables many more people to use the whole GNU operating system, as well as its variant, the GNU/Linux operating system.

Although the Lesser General Public License is Less protective of the

users' freedom, it does ensure that the user of a program that is linked with the Library has the freedom and the wherewithal to run that program using a modified version of the Library.

The precise terms and conditions for copying, distribution and modification follow. Pay close attention to the difference between a "work based on the library" and a "work that uses the library". The former contains code derived from the library, whereas the latter must be combined with the library in order to run.

GNU LESSER GENERAL PUBLIC LICENSE
TERMS AND CONDITIONS FOR COPYING, DISTRIBUTION AND MODIFICATION

0. This License Agreement applies to any software library or other program which contains a notice placed by the copyright holder or other authorized party saying it may be distributed under the terms of this Lesser General Public License (also called "this License"). Each licensee is addressed as "you".

A "library" means a collection of software functions and/or data prepared so as to be conveniently linked with application programs (which use some of those functions and data) to form executables.

The "Library", below, refers to any such software library or work which has been distributed under these terms. A "work based on the Library" means either the Library or any derivative work under copyright law: that is to say, a work containing the Library or a portion of it, either verbatim or with modifications and/or translated straightforwardly into another language. (Hereinafter, translation is included without limitation in the term "modification".)

"Source code" for a work means the preferred form of the work for making modifications to it. For a library, complete source code means all the source code for all modules it contains, plus any associated interface definition files, plus the scripts used to control compilation and installation of the library.

Activities other than copying, distribution and modification are not covered by this License; they are outside its scope. The act of running a program using the Library is not restricted, and output from such a program is covered only if its contents constitute a work based on the Library (independent of the use of the Library in a tool for writing it). Whether that is true depends on what the Library does and what the program that uses the Library does.

1. You may copy and distribute verbatim copies of the Library's complete source code as you receive it, in any medium, provided that you conspicuously and appropriately publish on each copy an appropriate copyright notice and disclaimer of warranty; keep intact all the notices that refer to this License and to the absence of any warranty; and distribute a copy of this License along with the Library.

You may charge a fee for the physical act of transferring a copy, and you may at your option offer warranty protection in exchange for a fee.

2. You may modify your copy or copies of the Library or any portion of it, thus forming a work based on the Library, and copy and distribute such modifications or work under the terms of Section 1 above, provided that you also meet all of these conditions:

- a) The modified work must itself be a software library.
- b) You must cause the files modified to carry prominent notices stating that you changed the files and the date of any change.

c) You must cause the whole of the work to be licensed at no charge to all third parties under the terms of this License.

d) If a facility in the modified Library refers to a function or a table of data to be supplied by an application program that uses the facility, other than as an argument passed when the facility is invoked, then you must make a good faith effort to ensure that, in the event an application does not supply such function or table, the facility still operates, and performs whatever part of its purpose remains meaningful.

(For example, a function in a library to compute square roots has a purpose that is entirely well-defined independent of the application. Therefore, Subsection 2d requires that any application-supplied function or table used by this function must be optional: if the application does not supply it, the square root function must still compute square roots.)

These requirements apply to the modified work as a whole. If identifiable sections of that work are not derived from the Library, and can be reasonably considered independent and separate works in themselves, then this License, and its terms, do not apply to those sections when you distribute them as separate works. But when you distribute the same sections as part of a whole which is a work based on the Library, the distribution of the whole must be on the terms of this License, whose permissions for other licensees extend to the entire whole, and thus to each and every part regardless of who wrote it.

Thus, it is not the intent of this section to claim rights or contest your rights to work written entirely by you; rather, the intent is to exercise the right to control the distribution of derivative or collective works based on the Library.

In addition, mere aggregation of another work not based on the Library with the Library (or with a work based on the Library) on a volume of a storage or distribution medium does not bring the other work under the scope of this License.

3. You may opt to apply the terms of the ordinary GNU General Public License instead of this License to a given copy of the Library. To do this, you must alter all the notices that refer to this License, so that they refer to the ordinary GNU General Public License, version 2, instead of to this License. (If a newer version than version 2 of the ordinary GNU General Public License has appeared, then you can specify that version instead if you wish.) Do not make any other change in these notices.

Once this change is made in a given copy, it is irreversible for that copy, so the ordinary GNU General Public License applies to all subsequent copies and derivative works made from that copy.

This option is useful when you wish to copy part of the code of the Library into a program that is not a library.

4. You may copy and distribute the Library (or a portion or derivative of it, under Section 2) in object code or executable form under the terms of Sections 1 and 2 above provided that you accompany it with the complete corresponding machine-readable source code, which must be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange.

If distribution of object code is made by offering access to copy from a designated place, then offering equivalent access to copy the source code from the same place satisfies the requirement to distribute the source code, even though third parties are not compelled to copy the source along with the object code.

5. A program that contains no derivative of any portion of the Library, but is designed to work with the Library by being compiled or linked with it, is called a "work that uses the Library". Such a work, in isolation, is not a derivative work of the Library, and therefore falls outside the scope of this License.

However, linking a "work that uses the Library" with the Library creates an executable that is a derivative of the Library (because it contains portions of the Library), rather than a "work that uses the library". The executable is therefore covered by this License. Section 6 states terms for distribution of such executables.

When a "work that uses the Library" uses material from a header file that is part of the Library, the object code for the work may be a derivative work of the Library even though the source code is not. Whether this is true is especially significant if the work can be linked without the Library, or if the work is itself a library. The threshold for this to be true is not precisely defined by law.

If such an object file uses only numerical parameters, data structure layouts and accessors, and small macros and small inline functions (ten lines or less in length), then the use of the object file is unrestricted, regardless of whether it is legally a derivative work. (Executables containing this object code plus portions of the Library will still fall under Section 6.)

Otherwise, if the work is a derivative of the Library, you may distribute the object code for the work under the terms of Section 6. Any executables containing that work also fall under Section 6, whether or not they are linked directly with the Library itself.

6. As an exception to the Sections above, you may also combine or link a "work that uses the Library" with the Library to produce a work containing portions of the Library, and distribute that work under terms of your choice, provided that the terms permit modification of the work for the customer's own use and reverse engineering for debugging such modifications.

You must give prominent notice with each copy of the work that the Library is used in it and that the Library and its use are covered by this License. You must supply a copy of this License. If the work during execution displays copyright notices, you must include the copyright notice for the Library among them, as well as a reference directing the user to the copy of this License. Also, you must do one of these things:

a) Accompany the work with the complete corresponding machine-readable source code for the Library including whatever changes were used in the work (which must be distributed under Sections 1 and 2 above); and, if the work is an executable linked with the Library, with the complete machine-readable "work that uses the Library", as object code and/or source code, so that the user can modify the Library and then relink to produce a modified executable containing the modified Library. (It is understood that the user who changes the contents of definitions files in the Library will not necessarily be able to recompile the application to use the modified definitions.)

b) Use a suitable shared library mechanism for linking with the Library. A suitable mechanism is one that (1) uses at run time a copy of the library already present on the user's computer system, rather than copying library functions into the executable, and (2) will operate properly with a modified version of the library, if the user installs one, as long as the modified version is interface-compatible with the version that the work was made with.

- c) Accompany the work with a written offer, valid for at least three years, to give the same user the materials specified in Subsection 6a, above, for a charge no more than the cost of performing this distribution.
- d) If distribution of the work is made by offering access to copy from a designated place, offer equivalent access to copy the above specified materials from the same place.
- e) Verify that the user has already received a copy of these materials or that you have already sent this user a copy.

For an executable, the required form of the "work that uses the Library" must include any data and utility programs needed for reproducing the executable from it. However, as a special exception, the materials to be distributed need not include anything that is normally distributed (in either source or binary form) with the major components (compiler, kernel, and so on) of the operating system on which the executable runs, unless that component itself accompanies the executable.

It may happen that this requirement contradicts the license restrictions of other proprietary libraries that do not normally accompany the operating system. Such a contradiction means you cannot use both them and the Library together in an executable that you distribute.

7. You may place library facilities that are a work based on the Library side-by-side in a single library together with other library facilities not covered by this License, and distribute such a combined library, provided that the separate distribution of the work based on the Library and of the other library facilities is otherwise permitted, and provided that you do these two things:

- a) Accompany the combined library with a copy of the same work based on the Library, uncombined with any other library facilities. This must be distributed under the terms of the Sections above.
- b) Give prominent notice with the combined library of the fact that part of it is a work based on the Library, and explaining where to find the accompanying uncombined form of the same work.

8. You may not copy, modify, sublicense, link with, or distribute the Library except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense, link with, or distribute the Library is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

9. You are not required to accept this License, since you have not signed it. However, nothing else grants you permission to modify or distribute the Library or its derivative works. These actions are prohibited by law if you do not accept this License. Therefore, by modifying or distributing the Library (or any work based on the Library), you indicate your acceptance of this License to do so, and all its terms and conditions for copying, distributing or modifying the Library or works based on it.

10. Each time you redistribute the Library (or any work based on the Library), the recipient automatically receives a license from the original licensor to copy, distribute, link with or modify the Library subject to these terms and conditions. You may not impose any further restrictions on the recipients' exercise of the rights granted herein. You are not responsible for enforcing compliance by third parties with this License.

11. If, as a consequence of a court judgment or allegation of patent infringement or for any other reason (not limited to patent issues), conditions are imposed on you (whether by court order, agreement or otherwise) that contradict the conditions of this License, they do not excuse you from the conditions of this License. If you cannot distribute so as to satisfy simultaneously your obligations under this License and any other pertinent obligations, then as a consequence you may not distribute the Library at all. For example, if a patent license would not permit royalty-free redistribution of the Library by all those who receive copies directly or indirectly through you, then the only way you could satisfy both it and this License would be to refrain entirely from distribution of the Library.

If any portion of this section is held invalid or unenforceable under any particular circumstance, the balance of the section is intended to apply, and the section as a whole is intended to apply in other circumstances.

It is not the purpose of this section to induce you to infringe any patents or other property right claims or to contest validity of any such claims; this section has the sole purpose of protecting the integrity of the free software distribution system which is implemented by public license practices. Many people have made generous contributions to the wide range of software distributed through that system in reliance on consistent application of that system; it is up to the author/donor to decide if he or she is willing to distribute software through any other system and a licensee cannot impose that choice.

This section is intended to make thoroughly clear what is believed to be a consequence of the rest of this License.

12. If the distribution and/or use of the Library is restricted in certain countries either by patents or by copyrighted interfaces, the original copyright holder who places the Library under this License may add an explicit geographical distribution limitation excluding those countries, so that distribution is permitted only in or among countries not thus excluded. In such case, this License incorporates the limitation as if written in the body of this License.

13. The Free Software Foundation may publish revised and/or new versions of the Lesser General Public License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns.

Each version is given a distinguishing version number. If the Library specifies a version number of this License which applies to it and "any later version", you have the option of following the terms and conditions either of that version or of any later version published by the Free Software Foundation. If the Library does not specify a license version number, you may choose any version ever published by the Free Software Foundation.

14. If you wish to incorporate parts of the Library into other free programs whose distribution conditions are incompatible with these, write to the author to ask for permission. For software which is copyrighted by the Free Software Foundation, write to the Free Software Foundation; we sometimes make exceptions for this. Our decision will be guided by the two goals of preserving the free status of all derivatives of our free software and of promoting the sharing and reuse of software generally.

NO WARRANTY

15. BECAUSE THE LIBRARY IS LICENSED FREE OF CHARGE, THERE IS NO WARRANTY FOR THE LIBRARY, TO THE EXTENT PERMITTED BY APPLICABLE LAW. EXCEPT WHEN OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDERS AND/OR

OTHER PARTIES PROVIDE THE LIBRARY "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE LIBRARY IS WITH YOU. SHOULD THE LIBRARY PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION.

16. IN NO EVENT UNLESS REQUIRED BY APPLICABLE LAW OR AGREED TO IN WRITING WILL ANY COPYRIGHT HOLDER, OR ANY OTHER PARTY WHO MAY MODIFY AND/OR REDISTRIBUTE THE LIBRARY AS PERMITTED ABOVE, BE LIABLE TO YOU FOR DAMAGES, INCLUDING ANY GENERAL, SPECIAL, INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE LIBRARY (INCLUDING BUT NOT LIMITED TO LOSS OF DATA OR DATA BEING RENDERED INACCURATE OR LOSSES SUSTAINED BY YOU OR THIRD PARTIES OR A FAILURE OF THE LIBRARY TO OPERATE WITH ANY OTHER SOFTWARE), EVEN IF SUCH HOLDER OR OTHER PARTY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

END OF TERMS AND CONDITIONS

How to Apply These Terms to Your New Libraries

If you develop a new library, and you want it to be of the greatest possible use to the public, we recommend making it free software that everyone can redistribute and change. You can do so by permitting redistribution under these terms (or, alternatively, under the terms of the ordinary General Public License).

To apply these terms, attach the following notices to the library. It is safest to attach them to the start of each source file to most effectively convey the exclusion of warranty; and each file should have at least the "copyright" line and a pointer to where the full notice is found.

```
<one line to give the library's name and a brief idea of what it does.>
Copyright (C) <year> <name of author>
```

```
This library is free software; you can redistribute it and/or
modify it under the terms of the GNU Lesser General Public
License as published by the Free Software Foundation; either
version 2.1 of the License, or (at your option) any later version.
```

```
This library is distributed in the hope that it will be useful,
but WITHOUT ANY WARRANTY; without even the implied warranty of
MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU
Lesser General Public License for more details.
```

```
You should have received a copy of the GNU Lesser General Public
License along with this library; if not, write to the Free Software
Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA
```

Also add information on how to contact you by electronic and paper mail.

You should also get your employer (if you work as a programmer) or your school, if any, to sign a "copyright disclaimer" for the library, if necessary. Here is a sample; alter the names:

```
Yoyodyne, Inc., hereby disclaims all copyright interest in the
library 'Frob' (a library for tweaking knobs) written by James Random Hacker.
```

```
<signature of Ty Coon>, 1 April 1990
Ty Coon, President of Vice
```

That's all there is to it!

8.2 INSTALL

Introduction

=====

Qwt uses qmake to build all its components and examples.
qmake is part of a Qt distribution.

qmake reads project files, that contain the options and rules how to build a certain project. A project file ends with the suffix "*.pro". Files that end with the suffix "*.pri" are included by the project files and contain definitions, that are common for several project files.

qwtconfig.pri is read by all project files of the Qwt package. So the first step is to edit qwtconfig.pri to adjust it to your needs.

MathML Extension

=====

Qwt/Qt4 supports the MathML render engine from the Qt solutions package, that is only available with a commercial Qt license.

You need a release of qtmmlwidget >= 2.1.
Copy the files qtmmlwidget.[cpp|h] to textengines/mathml.

Documentation

=====

Qwt includes a class documentation, that is available in various formats:

- Html files
- PDF document
- Qt Compressed Help (*.qch) for the Qt assistant.
- Man pages (UNIX only)

A) Unix Qt3/Qt4

=====

```
qmake
make
make install
```

If you have installed a shared library it's path has to be known to the run-time linker of your operating system. On Linux systems read "man ldconfig" (or google for it). Another option is to use the LD_LIBRARY_PATH (on some systems LIBPATH is used instead, on MacOSX it is called DYLD_LIBRARY_PATH) environment variable.

If you only want to check the Qwt examples without installing something, you can set the LD_LIBRARY_PATH to the lib directory of your local build.

If you didn't enable autobuilding of the examples in qwtconfig.pri you have to build the examples this way:

```
cd examples
qmake
make
```

B) Win32/MSVC Qt3/Qt4

=====

Please read the qmake documentation how to convert your *.pro files into your development environment.

```
F.e MSVC with nmake:
qmake qwt.pro
nmake
```

If you didn't enable autobuilding of the examples in qwtconfig.pri you have to build the examples this way:

```
cd examples
qmake examples.pro
nmake
```

admin/msvc-qmake.bat helps users of Visual Studio users to generate makefiles or project files (.dsp for MSVC-6.0 or vcproj for MSVC.NET) for Qwt.

```
To generate makefiles, type: "admin\msvc-qmake"
To generate project files, type: "admin\msvc-qmake vc"
```

When you have built a Qwt DLL you need to add the following define to your compiler flags: QWT_DLL.

Windows doesn't like mixing of debug and release binaries. Most of the problems with using the Qwt designer plugin are because of trying to load a Qwt debug library into a designer release executable.

```
C) Win32/MinGW Qt4
=====
```

```
C1) Windows Shell
```

Start a Windows Shell, where Qt4 is initialized. (F.e. with "Programs->Qt by Trolltech ...->Qt 4.x.x Command Prompt").

```
qmake qwt.pro
make
```

If you didn't enable autobuilding of the examples in qwtconfig.pri you have to build the examples this way:

```
cd examples
qmake examples.pro
make
make install
```

```
C2) MSYS Shell Qt >= 4.3.0
```

Support for the MSYS Shell has been improved in Qt 4.3.0. Now building Qwt from the MSYS Shell works exactly like in UNIX or in the Windows Shell - or at least it should: because of a bug in Qt 4.3.0 you always have to do a "qmake -r".

```
C3) MSYS Shell Qt < 4.3.0
```

For Qt < 4.3.0 you have to set the MINGW_IN_SHELL variable. make will run into errors with the subdirs target, that can be ignored (make -i).

```
export MINGW_IN_SHELL=1;
```

```
qmake
make -i
make -i install
```

If you didn't enable autobuilding of the examples in qwtconfig.pri you have to build the examples this way:

```
cd examples
qmake examples.pro
make -i
make -i install
```

C1-C3)

When you have built a Qwt DLL you need to add QWT_DLL to your compiler flags. If you are using qmake for your own builds this done by adding the following line to your profile: "DEFINES += QWT_DLL".

Windows doesn't like mixing of debug and release binaries. Most of the problems with using the Qwt designer plugin are because of trying to load a Qwt debug library into a designer release executable.

D) MacOSX

Well, the Mac is only another Unix system. So read the instructions in A).

In the recent Qt4 releases the default target of qmake is to generate XCode project files instead of makefiles. So you might need to do the following:

```
qmake -spec macx-g++
...
```

D) Qtopia Core

I only tested Qwt with Qtopia Core in qvfb (Virtual Framebuffer Devivce) Emulator on my Linux box. To build Qwt for the emulator was as simple as for a regular Unix build.

```
qmake
make
```

E) Qtopia (!= Qtopia Core)

I once compiled the Qwt library against Qtopia 4.2.0 successfully - but not more. It should be possible to build and install Qwt, but it's not done yet.

Good luck !

8.3 Curve Plots

8.4 Scatter Plot

8.5 Spectrogram, Contour Plot

/*!

8.6 Histogram

8.7 Dials, Compasses, Knobs, Wheels, Sliders, Thermos

8.8 Deprecated List

Member [QwtPlot::clear\(\)](#) Use [QwtPlotDeict::detachItems](#) instead

Class [QwtPlotPrintFilter](#) In Qwt 5.0 the design of [QwtPlot](#) allows/recommends writing individual Qwt-PlotItems, that are not known to [QwtPlotPrintFilter](#). So this concept is outdated and [QwtPlotPrintFilter](#) will be removed/replaced in Qwt 6.x.

Index

- ~QwtAbstractScale
 - QwtAbstractScale, 13
- ~QwtAbstractScaleDraw
 - QwtAbstractScaleDraw, 18
- ~QwtAbstractSlider
 - QwtAbstractSlider, 25
- ~QwtAlphaColorMap
 - QwtAlphaColorMap, 32
- ~QwtAnalogClock
 - QwtAnalogClock, 35
- ~QwtArrowButton
 - QwtArrowButton, 40
- ~QwtColorMap
 - QwtColorMap, 44
- ~QwtCompass
 - QwtCompass, 47
- ~QwtCounter
 - QwtCounter, 59
- ~QwtCurveFitter
 - QwtCurveFitter, 66
- ~QwtData
 - QwtData, 67
- ~QwtDial
 - QwtDial, 71
- ~QwtDialNeedle
 - QwtDialNeedle, 82
- ~QwtDoubleRange
 - QwtDoubleRange, 95
- ~QwtDynGridLayout
 - QwtDynGridLayout, 101
- ~QwtEventPattern
 - QwtEventPattern, 109
- ~QwtIntervalData
 - QwtIntervalData, 113
- ~QwtKnob
 - QwtKnob, 116
- ~QwtLegend
 - QwtLegend, 121
- ~QwtLegendItem
 - QwtLegendItem, 127
- ~QwtLegendItemManager
 - QwtLegendItemManager, 132
- ~QwtLinearColorMap
 - QwtLinearColorMap, 134
- ~QwtMagnifier
 - QwtMagnifier, 141
- ~QwtMathMLTextEngine
 - QwtMathMLTextEngine, 147
- ~QwtPanner
 - QwtPanner, 156
- ~QwtPicker
 - QwtPicker, 165
- ~QwtPickerMachine
 - QwtPickerMachine, 180
- ~QwtPlainTextEngine
 - QwtPlainTextEngine, 182
- ~QwtPlot
 - QwtPlot, 188
- ~QwtPlotCanvas
 - QwtPlotCanvas, 205
- ~QwtPlotCurve
 - QwtPlotCurve, 213
- ~QwtPlotDict
 - QwtPlotDict, 224
- ~QwtPlotGrid
 - QwtPlotGrid, 226
- ~QwtPlotItem
 - QwtPlotItem, 233
- ~QwtPlotLayout
 - QwtPlotLayout, 243
- ~QwtPlotMagnifier
 - QwtPlotMagnifier, 249
- ~QwtPlotMarker
 - QwtPlotMarker, 252
- ~QwtPlotPanner
 - QwtPlotPanner, 258
- ~QwtPlotPicker
 - QwtPlotPicker, 261
- ~QwtPlotPrintFilter
 - QwtPlotPrintFilter, 268
- ~QwtPlotRasterItem
 - QwtPlotRasterItem, 271
- ~QwtPlotRescaler
 - QwtPlotRescaler, 275
- ~QwtPlotScaleItem
 - QwtPlotScaleItem, 281
- ~QwtPlotSpectrogram
 - QwtPlotSpectrogram, 287
- ~QwtPlotSvgItem
 - QwtPlotSvgItem, 294
- ~QwtRasterData
 - QwtRasterData, 307
- ~QwtRoundScaleDraw
 - QwtRoundScaleDraw, 312
- ~QwtScaleDraw
 - QwtScaleDraw, 321
- ~QwtScaleEngine
 - QwtScaleEngine, 330
- ~QwtScaleMap
 - QwtScaleMap, 334

- ~QwtScaleTransformation
 - QwtScaleTransformation, 338
- ~QwtScaleWidget
 - QwtScaleWidget, 340
- ~QwtSpline
 - QwtSpline, 358
- ~QwtSplineCurveFitter
 - QwtSplineCurveFitter, 361
- ~QwtSymbol
 - QwtSymbol, 364
- ~QwtText
 - QwtText, 370
- ~QwtTextEngine
 - QwtTextEngine, 377
- ~QwtTextLabel
 - QwtTextLabel, 380
- ~QwtThermo
 - QwtThermo, 385
- ~QwtWheel
 - QwtWheel, 393
- abstractScaleDraw
 - QwtAbstractScale, 16
- accept
 - QwtPicker, 172
 - QwtPlotZoomer, 303
- activate
 - QwtPlotLayout, 246
- addColorStop
 - QwtLinearColorMap, 135
- addItem
 - QwtDynGridLayout, 102
- alarmBrush
 - QwtThermo, 387
- alarmColor
 - QwtThermo, 387
- alarmEnabled
 - QwtThermo, 388
- alarmLevel
 - QwtThermo, 387
- align
 - QwtLinearScaleEngine, 138
- alignCanvasToScales
 - QwtPlotLayout, 244
- alignLegend
 - QwtPlotLayout, 248
- Alignment
 - QwtScaleDraw, 321
- alignment
 - QwtScaleDraw, 324
 - QwtScaleWidget, 346
- alignScales
 - QwtPlotLayout, 248
- alpha
 - QwtPlotRasterItem, 271
- append
 - QwtPicker, 172
 - QwtPlotPicker, 265
- appended
 - QwtPicker, 171
 - QwtPlotPicker, 263
- apply
 - QwtPlotPrintFilter, 269
- arrowSize
 - QwtArrowButton, 41
- arrowType
 - QwtArrowButton, 40
- aspectRatio
 - QwtPlotRescaler, 277
- attach
 - QwtPlotItem, 234
- Attribute
 - QwtScaleEngine, 329
- attributes
 - QwtScaleEngine, 330
- autoDelete
 - QwtPlotDict, 225
- autoRefresh
 - QwtPlot, 201
- autoReplot
 - QwtPlot, 188
- autoScale
 - QwtAbstractScale, 14
 - QwtLinearScaleEngine, 137
 - QwtLog10ScaleEngine, 139
 - QwtScaleEngine, 332
- Axis
 - QwtPlot, 187
- axisAutoScale
 - QwtPlot, 193
- axisEnabled
 - QwtPlot, 193
- axisFont
 - QwtPlot, 194
- axisMaxMajor
 - QwtPlot, 198
- axisMaxMinor
 - QwtPlot, 198
- axisScaleDiv
 - QwtPlot, 195
- axisScaleDraw
 - QwtPlot, 196
- axisScaleEngine
 - QwtPlot, 192
- axisStepSize
 - QwtPlot, 195
- axisTitle
 - QwtPlot, 197

- axisValid
 - QwtPlot, 201
- axisWidget
 - QwtPlot, 196
- backgroundBrush
 - QwtText, 373
- backgroundPen
 - QwtText, 373
- baseline
 - QwtPlotCurve, 218
- begin
 - QwtPicker, 172
 - QwtPlotZoomer, 303
- BGSTYLE
 - QwtSlider, 351
- bgStyle
 - QwtSlider, 352
- borderDistance
 - QwtPlotScaleItem, 284
- borderFlags
 - QwtDoubleInterval, 91
- BorderMode
 - QwtDoubleInterval, 89
- borderWidth
 - QwtKnob, 117
 - QwtSlider, 353
 - QwtThermo, 386
- boundingLabelRect
 - QwtScaleDraw, 327
- boundingRect
 - QwtArrayData, 39
 - QwtCPointerData, 65
 - QwtData, 68
 - QwtDial, 76
 - QwtIntervalData, 114
 - QwtPlotCurve, 216
 - QwtPlotItem, 238
 - QwtPlotMarker, 257
 - QwtPlotSpectrogram, 288
 - QwtPlotSvgItem, 295
 - QwtRasterData, 307
- brush
 - QwtPlotCurve, 218
 - QwtSymbol, 366
- buildInterval
 - QwtScaleEngine, 333
- buildNaturalSpline
 - QwtSpline, 360
- buildPeriodicSpline
 - QwtSpline, 360
- Button
 - QwtCounter, 58
- buttonReleased
 - QwtCounter, 62
- CachePolicy
 - QwtPlotRasterItem, 270
- cachePolicy
 - QwtPlotRasterItem, 272
- canvas
 - QwtPlot, 190
 - QwtPlotMagnifier, 250
 - QwtPlotPanner, 258
 - QwtPlotPicker, 262
 - QwtPlotRescaler, 277
- canvasBackground
 - QwtPlot, 191
- canvasLineWidth
 - QwtPlot, 191
- canvasMap
 - QwtPlot, 191
- canvasMargin
 - QwtPlotLayout, 243
- canvasRect
 - QwtPlotLayout, 247
- ceil125
 - QwtScaleArithmetic, 316
- ceilEps
 - QwtScaleArithmetic, 315
- center
 - QwtRoundScaleDraw, 312
- changed
 - QwtPicker, 172
- checked
 - QwtLegendItem, 130
- clear
 - QwtLegend, 123
 - QwtPlot, 201
 - QwtTextLabel, 381
- clicked
 - QwtLegendItem, 130
- clipCircle
 - QwtClipper, 43
- clipPolygon
 - QwtClipper, 42
- clipPolygonF
 - QwtClipper, 42
- clone
 - QwtSymbol, 364
- closePolyline
 - QwtPlotCurve, 223
- closestPoint
 - QwtPlotCurve, 215
- coefficientsA
 - QwtSpline, 360
- coefficientsB
 - QwtSpline, 360

- coefficientsC
 - QwtSpline, 360
- color
 - QwtAlphaColorMap, 33
 - QwtColorMap, 45
 - QwtPlotPrintFilter, 268
 - QwtText, 372
- color1
 - QwtLinearColorMap, 136
- color2
 - QwtLinearColorMap, 136
- colorIndex
 - QwtColorMap, 45
 - QwtLinearColorMap, 136
- colorMap
 - QwtPlotSpectrogram, 288
- colorStops
 - QwtLinearColorMap, 135
- colorTable
 - QwtColorMap, 46
- columnsForWidth
 - QwtDynGridLayout, 104
- Command
 - QwtPickerMachine, 180
- compareEps
 - QwtScaleArithmetic, 315
- ConrecAttribute
 - QwtRasterData, 306
- contains
 - QwtDoubleInterval, 92
 - QwtScaleDiv, 319
 - QwtScaleEngine, 333
- contentsRect
 - QwtDial, 77
- contentsWidget
 - QwtLegend, 122
- contourLevels
 - QwtPlotSpectrogram, 291
- contourLines
 - QwtRasterData, 308
- contourPen
 - QwtPlotSpectrogram, 289
- contourRasterSize
 - QwtPlotSpectrogram, 292
- copy
 - QwtAlphaColorMap, 32
 - QwtArrayData, 38
 - QwtColorMap, 45
 - QwtCPointerData, 64
 - QwtData, 67
 - QwtLinearColorMap, 134
 - QwtPolygonFData, 304
 - QwtRasterData, 307
 - QwtScaleTransformation, 338
- count
 - QwtDynGridLayout, 102
- cursor
 - QwtPanner, 157
- CurveAttribute
 - QwtPlotCurve, 212
- curveFitter
 - QwtPlotCurve, 219
- curvePen
 - QwtLegendItem, 129
- CurveStyle
 - QwtPlotCurve, 211
- CurveType
 - QwtPlotCurve, 211
- curveType
 - QwtPlotCurve, 213
- data
 - QwtPlotCurve, 215, 216
 - QwtPlotSpectrogram, 288
 - QwtPolygonFData, 305
- dataSize
 - QwtPlotCurve, 216
- defaultContourPen
 - QwtPlotSpectrogram, 289
- detach
 - QwtPlotItem, 234
- detachItems
 - QwtPlotDict, 225
- deviceClipping
 - QwtPainter, 152
- deviceClipRect
 - QwtPainter, 153
- dimForLength
 - QwtScaleWidget, 345
- Direction
 - QwtDial, 71
- direction
 - QwtDial, 76
- discardRaster
 - QwtRasterData, 308
- DisplayMode
 - QwtPicker, 164
 - QwtPlotSpectrogram, 286
- displayPolicy
 - QwtLegend, 122
- divideEps
 - QwtScaleArithmetic, 315
- divideInterval
 - QwtScaleEngine, 333
- divideScale
 - QwtLinearScaleEngine, 137
 - QwtLog10ScaleEngine, 139
 - QwtScaleEngine, 332

- draw
 - QwtAbstractScaleDraw, 20
 - QwtCompassMagnetNeedle, 52
 - QwtCompassRose, 54
 - QwtCompassWindArrow, 56
 - QwtDialNeedle, 82
 - QwtDialSimpleNeedle, 86
 - QwtKnob, 118
 - QwtMathMLTextEngine, 148
 - QwtPlainTextEngine, 183
 - QwtPlotCurve, 219, 220
 - QwtPlotGrid, 230
 - QwtPlotItem, 238
 - QwtPlotMarker, 256
 - QwtPlotRasterItem, 272
 - QwtPlotScaleItem, 284
 - QwtPlotSpectrogram, 291
 - QwtPlotSvgItem, 295
 - QwtRichTextEngine, 310
 - QwtScaleWidget, 346
 - QwtSimpleCompassRose, 349
 - QwtSlider, 355
 - QwtSymbol, 366
 - QwtText, 375
 - QwtTextEngine, 378
 - QwtThermo, 390
 - QwtWheel, 396
- drawArrow
 - QwtArrowButton, 41
- drawArrowNeedle
 - QwtDialSimpleNeedle, 87
- drawAt
 - QwtPlotMarker, 257
- drawBackbone
 - QwtAbstractScaleDraw, 22
 - QwtRoundScaleDraw, 314
 - QwtScaleDraw, 327
- drawButtonLabel
 - QwtArrowButton, 41
- drawCanvas
 - QwtPlot, 200
 - QwtPlotCanvas, 208
- drawContents
 - QwtDial, 79
 - QwtPlotCanvas, 207
 - QwtTextLabel, 382
- drawContourLines
 - QwtPlotSpectrogram, 293
- drawCurve
 - QwtPlotCurve, 221
- drawDots
 - QwtPlotCurve, 222
- drawEllipse
 - QwtPainter, 154
- drawFocusIndicator
 - QwtDial, 79
 - QwtPlotCanvas, 208
- drawFrame
 - QwtDial, 79
- drawHand
 - QwtAnalogClock, 37
- drawIdentifier
 - QwtLegendItem, 129
- drawItem
 - QwtLegendItem, 130
- drawItems
 - QwtPlot, 202
- drawKnob
 - QwtDialNeedle, 83
 - QwtKnob, 119
- drawLabel
 - QwtAbstractScaleDraw, 22
 - QwtRoundScaleDraw, 314
 - QwtScaleDraw, 328
- drawLine
 - QwtPainter, 154
- drawLines
 - QwtPlotCurve, 221
- drawMarker
 - QwtKnob, 119
- drawNeedle
 - QwtAnalogClock, 36
 - QwtDial, 80
- drawPie
 - QwtPainter, 154
- drawPoint
 - QwtPainter, 154
- drawPointer
 - QwtCompassMagnetNeedle, 53
- drawPolygon
 - QwtPainter, 154
- drawPolyline
 - QwtPainter, 154
- drawRayNeedle
 - QwtDialSimpleNeedle, 87
- drawRect
 - QwtPainter, 153
- drawRose
 - QwtCompass, 49
 - QwtSimpleCompassRose, 349
- drawRoundFrame
 - QwtPainter, 154
- drawRubberBand
 - QwtPicker, 170
- drawScale
 - QwtDial, 79
- drawScaleContents
 - QwtCompass, 49

- QwtDial, 80
- drawSimpleRichText
 - QwtPainter, 153
- drawSlider
 - QwtSlider, 355
- drawSteps
 - QwtPlotCurve, 222
- drawSticks
 - QwtPlotCurve, 222
- drawStyle1Needle
 - QwtCompassWindArrow, 56
- drawStyle2Needle
 - QwtCompassWindArrow, 56
- drawSymbols
 - QwtPlotCurve, 221
- drawText
 - QwtLegendItem, 131
 - QwtPainter, 153
 - QwtTextLabel, 382
- drawThermo
 - QwtThermo, 390
- drawThinNeedle
 - QwtCompassMagnetNeedle, 52
- drawThumb
 - QwtSlider, 355
- drawTick
 - QwtAbstractScaleDraw, 22
 - QwtRoundScaleDraw, 313
 - QwtScaleDraw, 327
- drawTitle
 - QwtScaleWidget, 345
- drawTracker
 - QwtPicker, 170
- drawTriangleNeedle
 - QwtCompassMagnetNeedle, 52
- drawWheel
 - QwtWheel, 396
- drawWheelBackground
 - QwtWheel, 396
- editable
 - QwtCounter, 59
- enableAxis
 - QwtPlot, 193
- enableComponent
 - QwtAbstractScaleDraw, 19
- enableX
 - QwtPlotGrid, 227
- enableXMin
 - QwtPlotGrid, 227
- enableY
 - QwtPlotGrid, 227
- enableYMin
 - QwtPlotGrid, 228
- end
 - QwtPicker, 173
 - QwtPlotPicker, 266
 - QwtPlotZoomer, 303
- endBorderDist
 - QwtScaleWidget, 342
- event
 - QwtCounter, 62
 - QwtPlot, 200
- eventFilter
 - QwtLegend, 124
 - QwtMagnifier, 145
 - QwtPanner, 158
 - QwtPicker, 169
 - QwtPlotRescaler, 278
- exactPrevValue
 - QwtDoubleRange, 99
- exactValue
 - QwtDoubleRange, 99
- expandingDirection
 - QwtPlotRescaler, 276
- expandingDirections
 - QwtDynGridLayout, 103
- expandInterval
 - QwtPlotRescaler, 279
- expandLineBreaks
 - QwtPlotLayout, 248
- expandScale
 - QwtPlotRescaler, 278
- extend
 - QwtDoubleInterval, 93
- extent
 - QwtAbstractScaleDraw, 21
 - QwtRoundScaleDraw, 313
 - QwtScaleDraw, 322
- fillBrush
 - QwtThermo, 386
- fillColor
 - QwtThermo, 386
- fillCurve
 - QwtPlotCurve, 223
- fillRect
 - QwtPainter, 153
- find
 - QwtLegend, 123
- fitCurve
 - QwtCurveFitter, 66
 - QwtSplineCurveFitter, 362
- fitMode
 - QwtSplineCurveFitter, 361
- fitValue
 - QwtAbstractSlider, 27
 - QwtDoubleRange, 98

- floor125
 - QwtScaleArithmetic, 316
- floorEps
 - QwtScaleArithmetic, 315
- FocusIndicator
 - QwtPlotCanvas, 205
- focusIndicator
 - QwtPlotCanvas, 206
- font
 - QwtPlotPrintFilter, 268
 - QwtPlotScaleItem, 282
 - QwtText, 371
- fontChange
 - QwtSlider, 356
 - QwtThermo, 391
- Format
 - QwtColorMap, 44
- format
 - QwtColorMap, 45
- frameShadow
 - QwtDial, 72
- getAbortKey
 - QwtPanner, 157
- getBorderDistHint
 - QwtScaleDraw, 322
 - QwtScaleWidget, 342
- getMinBorderDist
 - QwtScaleWidget, 342
- getMouseButton
 - QwtMagnifier, 143
 - QwtPanner, 157
- getScrollMode
 - QwtAbstractSlider, 30
 - QwtDial, 81
 - QwtSlider, 355
 - QwtWheel, 397
- getValue
 - QwtAbstractSlider, 30
 - QwtDial, 81
 - QwtSlider, 354
 - QwtWheel, 397
- getZoomInKey
 - QwtMagnifier, 144
- getZoomOutKey
 - QwtMagnifier, 145
- Hand
 - QwtAnalogClock, 35
- hand
 - QwtAnalogClock, 35
- hasComponent
 - QwtAbstractScaleDraw, 19
- hasHeightForWidth
 - QwtDynGridLayout, 104
- hasVisibleBackground
 - QwtDial, 72
- heightForWidth
 - QwtDynGridLayout, 104
 - QwtLegend, 124
 - QwtMathMLTextEngine, 148
 - QwtPlainTextEngine, 182
 - QwtRichTextEngine, 309
 - QwtText, 374
 - QwtTextEngine, 377
 - QwtTextLabel, 381
- hide
 - QwtPlotItem, 236
- hideEvent
 - QwtPlotCanvas, 207
- horizontalScrollBar
 - QwtLegend, 124
- IdentifierMode
 - QwtLegendItem, 126
- identifierMode
 - QwtLegend, 122
 - QwtLegendItem, 128
- identifierWidth
 - QwtLegendItem, 128
- incPages
 - QwtDoubleRange, 98
- incSteps
 - QwtCounter, 60
- incValue
 - QwtAbstractSlider, 28
 - QwtDoubleRange, 98
- indent
 - QwtTextLabel, 381
- init
 - QwtPlotCurve, 221
- initKeyPattern
 - QwtEventPattern, 109
- initMousePattern
 - QwtEventPattern, 109
- initRaster
 - QwtRasterData, 307
- insert
 - QwtLegend, 122
 - QwtPlot, 198
- insertLegend
 - QwtPlot, 198
- internalBorder
 - QwtWheel, 393
- intersect
 - QwtDoubleInterval, 92
- intersects
 - QwtDoubleInterval, 92
- interval

- QwtIntervalData, 114
- QwtPlotRescaler, 279
- QwtScaleDiv, 318
- invalidate
 - QwtDoubleInterval, 94
 - QwtDynGridLayout, 101
 - QwtPlotLayout, 246
 - QwtScaleDiv, 319
- invalidateCache
 - QwtAbstractScaleDraw, 23
 - QwtPlotRasterItem, 272
- invalidatePaintCache
 - QwtPlotCanvas, 207
- invert
 - QwtScaleDiv, 320
- inverted
 - QwtDoubleInterval, 90
- invTransform
 - QwtPlot, 191
 - QwtPlotItem, 240
 - QwtPlotPicker, 263, 264
 - QwtScaleMap, 336
- invXForm
 - QwtScaleTransformation, 338
- isActive
 - QwtPicker, 169
- isAxisEnabled
 - QwtPlotMagnifier, 250
 - QwtPlotPanner, 259
- isChecked
 - QwtLegendItem, 130
- isDown
 - QwtLegendItem, 131
- isEmpty
 - QwtDynGridLayout, 104
 - QwtLegend, 123
 - QwtText, 371
- isEnabled
 - QwtMagnifier, 142
 - QwtPanner, 156
 - QwtPicker, 169
 - QwtPlotRescaler, 275
- isNull
 - QwtDoubleInterval, 94
 - QwtText, 371
- isOrientationEnabled
 - QwtPanner, 157
- isReadOnly
 - QwtAbstractSlider, 27
- isScaleDivFromAxis
 - QwtPlotScaleItem, 282
- isValid
 - QwtAbstractSlider, 27
 - QwtDoubleInterval, 93
 - QwtDoubleRange, 96
 - QwtScaleDiv, 320
 - QwtSpline, 359
- isVisible
 - QwtPlotItem, 237
- Item
 - QwtPlotPrintFilter, 267
- itemAt
 - QwtDynGridLayout, 102
- ItemAttribute
 - QwtPlotItem, 233
- itemChanged
 - QwtPlotItem, 238
- itemCount
 - QwtDynGridLayout, 104
 - QwtLegend, 124
- itemList
 - QwtPlotDict, 225
- itemMode
 - QwtLegend, 122
 - QwtLegendItem, 127
- keyFactor
 - QwtMagnifier, 144
- keyMatch
 - QwtEventPattern, 111, 112
- keyPattern
 - QwtEventPattern, 110
- KeyPatternCode
 - QwtEventPattern, 108
- keyPressEvent
 - QwtAbstractSlider, 30
 - QwtArrowButton, 42
 - QwtCompass, 49
 - QwtCounter, 62
 - QwtDial, 78
 - QwtLegendItem, 131
- keyReleaseEvent
 - QwtLegendItem, 131
- knobWidth
 - QwtKnob, 116
- label
 - QwtAbstractScaleDraw, 21
 - QwtDialScaleDraw, 84
 - QwtPlotMarker, 255
- labelAlignment
 - QwtPlotMarker, 255
 - QwtScaleDraw, 325
- labelMap
 - QwtCompass, 48
- labelMatrix
 - QwtScaleDraw, 327
- labelOrientation

- QwtPlotMarker, 256
- labelPosition
 - QwtScaleDraw, 326
- labelRect
 - QwtArrowButton, 41
 - QwtScaleDraw, 326
- labelRotation
 - QwtScaleDraw, 325
- labelSize
 - QwtScaleDraw, 326
- LayoutAttribute
 - QwtText, 369
- layoutContents
 - QwtLegend, 125
- layoutGrid
 - QwtDynGridLayout, 105
- layoutItems
 - QwtDynGridLayout, 103
- layoutLegend
 - QwtPlotLayout, 247
- layoutScale
 - QwtScaleWidget, 346
- layoutSlider
 - QwtSlider, 356
- layoutThermo
 - QwtThermo, 391
- layoutWheel
 - QwtWheel, 396
- legend
 - QwtPlot, 199
- legendChecked
 - QwtPlot, 200
- legendClicked
 - QwtPlot, 200
- LegendDisplayPolicy
 - QwtLegend, 120
- legendItem
 - QwtLegendItemManager, 132
 - QwtPlotItem, 239
- legendItemChecked
 - QwtPlot, 201
- legendItemClicked
 - QwtPlot, 201
- LegendItemMode
 - QwtLegend, 121
- legendItems
 - QwtLegend, 123
- LegendPosition
 - QwtPlot, 187
- legendPosition
 - QwtPlotLayout, 245
- legendRatio
 - QwtPlotLayout, 246
- legendRect
 - QwtPlotLayout, 247
- length
 - QwtScaleDraw, 324
- limited
 - QwtDoubleInterval, 91
- linePen
 - QwtPlotMarker, 254
- LineStyle
 - QwtPlotMarker, 252
- lineStyle
 - QwtPlotMarker, 253
- lineWidth
 - QwtDial, 72
- loadData
 - QwtPlotSvgItem, 295
- loadFile
 - QwtPlotSvgItem, 294
- log10
 - QwtLog10ScaleEngine, 140
- lowerBound
 - QwtScaleDiv, 318
- lowerMargin
 - QwtScaleEngine, 331
- majPen
 - QwtPlotGrid, 229
- majTickLength
 - QwtAbstractScaleDraw, 20
- map
 - QwtAbstractScaleDraw, 19
- margin
 - QwtPlot, 189
 - QwtPlotLayout, 243
 - QwtScaleWidget, 343
 - QwtTextLabel, 381
- mass
 - QwtAbstractSlider, 26
 - QwtWheel, 394
- maxCols
 - QwtDynGridLayout, 101
- maxItemWidth
 - QwtDynGridLayout, 103
- maxLabelHeight
 - QwtScaleDraw, 326
- maxLabelWidth
 - QwtScaleDraw, 326
- maxScaleArc
 - QwtDial, 75
- maxStackDepth
 - QwtPlotZoomer, 300
- maxVal
 - QwtCounter, 61
- maxValue
 - QwtDoubleInterval, 92

- QwtDoubleRange, 97
- QwtThermo, 388
- maxXValue
 - QwtPlotCurve, 217
- maxYValue
 - QwtPlotCurve, 217
- metricsMap
 - QwtPainter, 152
- mightRender
 - QwtMathMLTextEngine, 148
 - QwtPlainTextEngine, 183
 - QwtRichTextEngine, 310
 - QwtTextEngine, 378
- minimumExtent
 - QwtAbstractScaleDraw, 21
- minimumSizeHint
 - QwtArrowButton, 41
 - QwtDial, 77
 - QwtKnob, 117
 - QwtPlot, 199
 - QwtPlotLayout, 246
 - QwtScaleWidget, 345
 - QwtSlider, 354
 - QwtTextLabel, 381
 - QwtThermo, 389
 - QwtWheel, 395
- minLabelDist
 - QwtScaleDraw, 322
- minLength
 - QwtScaleDraw, 322
- minPen
 - QwtPlotGrid, 230
- minScaleArc
 - QwtDial, 75
- minVal
 - QwtCounter, 61
- minValue
 - QwtDoubleInterval, 91
 - QwtDoubleRange, 98
 - QwtThermo, 389
- minXValue
 - QwtPlotCurve, 216
- minYValue
 - QwtPlotCurve, 217
- minZoomSize
 - QwtPlotZoomer, 302
- Mode
 - QwtDial, 71
 - QwtLinearColorMap, 134
- mode
 - QwtDial, 73
 - QwtLinearColorMap, 135
- mouseFactor
 - QwtMagnifier, 142
- mouseMatch
 - QwtEventPattern, 111
- mouseMoveEvent
 - QwtAbstractSlider, 29
- mousePattern
 - QwtEventPattern, 110
- MousePatternCode
 - QwtEventPattern, 107
- mousePressEvent
 - QwtAbstractSlider, 29
 - QwtLegendItem, 131
- mouseReleaseEvent
 - QwtAbstractSlider, 29
 - QwtLegendItem, 131
- move
 - QwtPicker, 173
 - QwtPlotPicker, 265
 - QwtPlotZoomer, 301
 - QwtScaleDraw, 323
- moveBy
 - QwtPlotZoomer, 301
- moveCanvas
 - QwtPlotPanner, 259
- moveCenter
 - QwtRoundScaleDraw, 312
- moved
 - QwtPanner, 158
 - QwtPicker, 171
 - QwtPlotPicker, 263
- needle
 - QwtDial, 76
- normalized
 - QwtDoubleInterval, 90
- num
 - QwtArrowButton, 40
- numButtons
 - QwtCounter, 59
- numCols
 - QwtDynGridLayout, 102
- numRows
 - QwtDynGridLayout, 101
- numThornLevels
 - QwtSimpleCompassRose, 348
- numThorns
 - QwtSimpleCompassRose, 348
- operator &
 - QwtDoubleInterval, 93
- operator &=
 - QwtDoubleInterval, 93
- operator !=
 - QwtDoubleInterval, 91
 - QwtScaleDiv, 318

- QwtSymbol, 364
- QwtText, 370
- operator=
 - QwtAbstractScaleDraw, 18
 - QwtAlphaColorMap, 32
 - QwtArrayData, 38
 - QwtCPointerData, 64
 - QwtData, 68
 - QwtLinearColorMap, 134
 - QwtPolygonFDData, 304
 - QwtRoundScaleDraw, 312
 - QwtScaleDraw, 322
 - QwtScaleMap, 335
 - QwtSpline, 358
 - QwtText, 370
- operator==
 - QwtDoubleInterval, 91
 - QwtScaleDiv, 318
 - QwtSymbol, 364
 - QwtText, 370
- operator |
 - QwtDoubleInterval, 93
- operator | =
 - QwtDoubleInterval, 93
- Options
 - QwtPlotLayout, 242
 - QwtPlotPrintFilter, 267
- options
 - QwtPlotPrintFilter, 268
- orientation
 - QwtAbstractSlider, 26
 - QwtPlotRescaler, 279
 - QwtScaleDraw, 324
- orientations
 - QwtPanner, 157
- origin
 - QwtDial, 75
- p1
 - QwtScaleMap, 336
- p2
 - QwtScaleMap, 336
- pageSize
 - QwtDoubleRange, 98
- PaintAttribute
 - QwtPlotCanvas, 205
 - QwtPlotCurve, 212
 - QwtText, 369
- paintCache
 - QwtPlotCanvas, 207
- paintEvent
 - QwtArrowButton, 41
 - QwtDial, 78
 - QwtKnob, 118
 - QwtLegendItem, 131
 - QwtPanner, 159
 - QwtPlotCanvas, 207
 - QwtScaleWidget, 346
 - QwtSlider, 355
 - QwtTextLabel, 382
 - QwtThermo, 391
 - QwtWheel, 396
- paintRect
 - QwtPlotItem, 240
- palette
 - QwtCompassRose, 53
 - QwtDialNeedle, 83
 - QwtPlotScaleItem, 282
- paletteChange
 - QwtWheel, 397
- panned
 - QwtPanner, 158
- parentWidget
 - QwtMagnifier, 141
 - QwtPicker, 169, 170
- pDist
 - QwtScaleMap, 337
- pen
 - QwtPlotCurve, 217
 - QwtSymbol, 366
- penWidth
 - QwtDialScaleDraw, 84
 - QwtScaleWidget, 343
- periodic
 - QwtDoubleRange, 97
- pickRect
 - QwtPicker, 170
- pipeWidth
 - QwtThermo, 388
- plot
 - QwtPlotCanvas, 206
 - QwtPlotItem, 234
 - QwtPlotMagnifier, 250
 - QwtPlotPanner, 258
 - QwtPlotPicker, 262
 - QwtPlotRescaler, 278
- plotLayout
 - QwtPlot, 189
- points
 - QwtSpline, 359
- polish
 - QwtCounter, 60
 - QwtPlot, 199
- pos
 - QwtScaleDraw, 324
- position
 - QwtPlotScaleItem, 283
- pow10

- QwtLog10ScaleEngine, 140
- pressed
 - QwtLegendItem, 130
- prevValue
 - QwtDoubleRange, 99
- print
 - QwtPlot, 188, 189
- printCanvas
 - QwtPlot, 203
- printLegend
 - QwtPlot, 203
- printLegendItem
 - QwtPlot, 202
- printScale
 - QwtPlot, 203
- printTitle
 - QwtPlot, 202
- qwt_double_rect.h, 397
 - QwtDoublePoint, 398
 - QwtDoubleRect, 398
 - QwtDoubleSize, 398
- qwt_plot_dict.h, 398
 - QwtPlotItemList, 399
- QwtAbstractScale, 12
 - QwtAbstractScale, 13
- QwtAbstractScale
 - ~QwtAbstractScale, 13
 - abstractScaleDraw, 16
 - autoScale, 14
 - QwtAbstractScale, 13
 - rescale, 16
 - scaleChange, 16
 - scaleEngine, 15
 - scaleMap, 15
 - scaleMaxMajor, 15
 - scaleMaxMinor, 14
 - setAbstractScaleDraw, 16
 - setAutoScale, 14
 - setScale, 13, 14
 - setScaleEngine, 15
 - setScaleMaxMajor, 14
 - setScaleMaxMinor, 15
- QwtAbstractScaleDraw, 17
 - QwtAbstractScaleDraw, 18
- QwtAbstractScaleDraw
 - ~QwtAbstractScaleDraw, 18
 - draw, 20
 - drawBackbone, 22
 - drawLabel, 22
 - drawTick, 22
 - enableComponent, 19
 - extent, 21
 - hasComponent, 19
 - invalidateCache, 23
 - label, 21
 - majTickLength, 20
 - map, 19
 - minimumExtent, 21
 - operator=, 18
 - QwtAbstractScaleDraw, 18
 - ScaleComponent, 18
 - scaleDiv, 19
 - scaleMap, 22
 - setMinimumExtent, 21
 - setScaleDiv, 18
 - setSpacing, 20
 - setTickLength, 19
 - setTransformation, 19
 - spacing, 20
 - tickLabel, 23
 - tickLength, 20
- QwtAbstractSlider, 23
 - QwtAbstractSlider, 25
- QwtAbstractSlider
 - ~QwtAbstractSlider, 25
 - fitValue, 27
 - getScrollMode, 30
 - getValue, 30
 - incValue, 28
 - isReadOnly, 27
 - isValid, 27
 - keyPressEvent, 30
 - mass, 26
 - mouseMoveEvent, 29
 - mousePressEvent, 29
 - mouseReleaseEvent, 29
 - orientation, 26
 - QwtAbstractSlider, 25
 - ScrollMode, 25
 - setMass, 26
 - setOrientation, 26
 - setPosition, 29
 - setReadOnly, 28
 - setTracking, 25
 - setUpdateTime, 25
 - setValid, 27
 - setValue, 27
 - sliderMoved, 29
 - sliderPressed, 28
 - sliderReleased, 28
 - stopMoving, 25
 - timerEvent, 29
 - valueChange, 29
 - valueChanged, 28
 - wheelEvent, 30
- QwtAlphaColorMap, 31
 - QwtAlphaColorMap, 32

- QwtAlphaColorMap
 - ~QwtAlphaColorMap, 32
 - color, 33
 - copy, 32
 - operator=, 32
 - QwtAlphaColorMap, 32
 - rgb, 33
 - setColor, 32
- QwtAnalogClock, 33
 - QwtAnalogClock, 35
- QwtAnalogClock
 - ~QwtAnalogClock, 35
 - drawHand, 37
 - drawNeedle, 36
 - Hand, 35
 - hand, 35
 - QwtAnalogClock, 35
 - scaleLabel, 36
 - setCurrentTime, 36
 - setHand, 35
 - setTime, 36
- QwtArrayData, 37
 - QwtArrayData, 38
- QwtArrayData
 - boundingRect, 39
 - copy, 38
 - operator=, 38
 - QwtArrayData, 38
 - size, 38
 - x, 38
 - xData, 39
 - y, 39
 - yData, 39
- QwtArrowButton, 39
 - QwtArrowButton, 40
- QwtArrowButton
 - ~QwtArrowButton, 40
 - arrowSize, 41
 - arrowType, 40
 - drawArrow, 41
 - drawButtonLabel, 41
 - keyPressEvent, 42
 - labelRect, 41
 - minimumSizeHint, 41
 - num, 40
 - paintEvent, 41
 - QwtArrowButton, 40
 - sizeHint, 40
- QwtClipper, 42
- QwtClipper
 - clipCircle, 43
 - clipPolygon, 42
 - clipPolygonF, 42
- QwtColorMap, 43
 - QwtColorMap, 44
- QwtColorMap
 - ~QwtColorMap, 44
 - color, 45
 - colorIndex, 45
 - colorTable, 46
 - copy, 45
 - Format, 44
 - format, 45
 - QwtColorMap, 44
 - rgb, 45
- QwtCompass, 46
 - QwtCompass, 47
- QwtCompass
 - ~QwtCompass, 47
 - drawRose, 49
 - drawScaleContents, 49
 - keyPressEvent, 49
 - labelMap, 48
 - QwtCompass, 47
 - rose, 47, 48
 - scaleLabel, 49
 - setLabelMap, 48
 - setRose, 47
- QwtCompassMagnetNeedle, 50
 - QwtCompassMagnetNeedle, 52
- QwtCompassMagnetNeedle
 - draw, 52
 - drawPointer, 53
 - drawThinNeedle, 52
 - drawTriangleNeedle, 52
 - QwtCompassMagnetNeedle, 52
 - Style, 51
- QwtCompassRose, 53
- QwtCompassRose
 - draw, 54
 - palette, 53
 - setPalette, 53
- QwtCompassWindArrow, 54
 - QwtCompassWindArrow, 56
- QwtCompassWindArrow
 - draw, 56
 - drawStyle1Needle, 56
 - drawStyle2Needle, 56
 - QwtCompassWindArrow, 56
 - Style, 55
- QwtCounter, 57
 - QwtCounter, 59
- QwtCounter
 - ~QwtCounter, 59
 - Button, 58
 - buttonReleased, 62
 - editable, 59
 - event, 62

- incSteps, 60
- keyPressEvent, 62
- maxVal, 61
- minVal, 61
- numButtons, 59
- polish, 60
- QwtCounter, 59
- rangeChange, 63
- setEditable, 59
- setIncSteps, 59
- setMax Value, 61
- setMin Value, 61
- setNumButtons, 59
- setStep, 60
- setStepButton1, 61
- setStepButton2, 61
- setStepButton3, 62
- setValue, 60
- sizeHint, 60
- step, 60
- stepButton1, 61
- stepButton2, 61
- stepButton3, 62
- value, 62
- valueChanged, 62
- wheelEvent, 62
- QwtCPointerData, 63
 - QwtCPointerData, 64
- QwtCPointerData
 - boundingRect, 65
 - copy, 64
 - operator=, 64
 - QwtCPointerData, 64
 - size, 64
 - x, 64
 - xData, 65
 - y, 65
 - yData, 65
- QwtCurveFitter, 65
 - QwtCurveFitter, 66
- QwtCurveFitter
 - ~QwtCurveFitter, 66
 - fitCurve, 66
 - QwtCurveFitter, 66
- QwtData, 66
 - QwtData, 67
- QwtData
 - ~QwtData, 67
 - boundingRect, 68
 - copy, 67
 - operator=, 68
 - QwtData, 67
 - size, 67
 - x, 67
 - y, 68
- QwtDial, 68
 - QwtDial, 71
- QwtDial
 - ~QwtDial, 71
 - boundingRect, 76
 - contentsRect, 77
 - Direction, 71
 - direction, 76
 - drawContents, 79
 - drawFocusIndicator, 79
 - drawFrame, 79
 - drawNeedle, 80
 - drawScale, 79
 - drawScaleContents, 80
 - frameShadow, 72
 - getScrollMode, 81
 - getValue, 81
 - hasVisibleBackground, 72
 - keyPressEvent, 78
 - lineWidth, 72
 - maxScaleArc, 75
 - minimumSizeHint, 77
 - minScaleArc, 75
 - Mode, 71
 - mode, 73
 - needle, 76
 - origin, 75
 - paintEvent, 78
 - QwtDial, 71
 - rangeChange, 81
 - resizeEvent, 78
 - scaleContentsRect, 77
 - scaleDraw, 77, 78
 - scaleLabel, 80
 - ScaleOptions, 71
 - setDirection, 75
 - setFrameShadow, 72
 - setLineWidth, 72
 - setMode, 73
 - setNeedle, 76
 - setOrigin, 75
 - setScale, 74
 - setScaleArc, 74
 - setScaleDraw, 77
 - setScaleOptions, 74
 - setScaleTicks, 74
 - setWrapping, 73
 - Shadow, 71
 - showBackground, 72
 - sizeHint, 77
 - updateMask, 78
 - updateScale, 80
 - valueChange, 81

- wrapping, 73
- QwtDialNeedle, 82
 - QwtDialNeedle, 82
- QwtDialNeedle
 - ~QwtDialNeedle, 82
 - draw, 82
 - drawKnob, 83
 - palette, 83
 - QwtDialNeedle, 82
 - setPalette, 83
- QwtDialScaleDraw, 83
 - QwtDialScaleDraw, 84
- QwtDialScaleDraw
 - label, 84
 - penWidth, 84
 - QwtDialScaleDraw, 84
 - setPenWidth, 84
- QwtDialSimpleNeedle, 85
 - QwtDialSimpleNeedle, 86
- QwtDialSimpleNeedle
 - draw, 86
 - drawArrowNeedle, 87
 - drawRayNeedle, 87
 - QwtDialSimpleNeedle, 86
 - setWidth, 87
 - Style, 86
 - width, 88
- QwtDoubleInterval, 88
 - QwtDoubleInterval, 90
- QwtDoubleInterval
 - borderFlags, 91
 - BorderMode, 89
 - contains, 92
 - extend, 93
 - intersect, 92
 - intersects, 92
 - invalidate, 94
 - inverted, 90
 - isNull, 94
 - isValid, 93
 - limited, 91
 - maxValue, 92
 - minValue, 91
 - normalized, 90
 - operator &, 93
 - operator &=, 93
 - operator !=, 91
 - operator ==, 91
 - operator |, 93
 - operator |=, 93
 - QwtDoubleInterval, 90
 - setBorderFlags, 91
 - setInterval, 90
 - setMaxValue, 92
 - setMinValue, 92
 - symmetrize, 94
 - unite, 93
 - width, 92
- QwtDoublePoint
 - qwt_double_rect.h, 398
- QwtDoubleRange, 94
 - QwtDoubleRange, 95
- QwtDoubleRange
 - ~QwtDoubleRange, 95
 - exactPrevValue, 99
 - exactValue, 99
 - fitValue, 98
 - incPages, 98
 - incValue, 98
 - isValid, 96
 - maxValue, 97
 - minValue, 98
 - pageSize, 98
 - periodic, 97
 - prevValue, 99
 - QwtDoubleRange, 95
 - rangeChange, 99
 - setPeriodic, 97
 - setRange, 96
 - setStep, 97
 - setValid, 96
 - setValue, 96
 - step, 97
 - stepChange, 99
 - value, 96
 - valueChange, 99
- QwtDoubleRect
 - qwt_double_rect.h, 398
- QwtDoubleSize
 - qwt_double_rect.h, 398
- QwtDynGridLayout, 100
 - QwtDynGridLayout, 101
- QwtDynGridLayout
 - ~QwtDynGridLayout, 101
 - addItem, 102
 - columnsForWidth, 104
 - count, 102
 - expandingDirections, 103
 - hasHeightForWidth, 104
 - heightForWidth, 104
 - invalidate, 101
 - isEmpty, 104
 - itemAt, 102
 - itemCount, 104
 - layoutGrid, 105
 - layoutItems, 103
 - maxCols, 101
 - maxItemWidth, 103

- numCols, 102
- numRows, 101
- QwtDynGridLayout, 101
- setExpandingDirections, 103
- setGeometry, 103
- setMaxCols, 101
- sizeHint, 104
- stretchGrid, 105
- takeAt, 102
- QwtEventPattern, 105
 - QwtEventPattern, 109
- QwtEventPattern
 - ~QwtEventPattern, 109
 - initKeyPattern, 109
 - initMousePattern, 109
 - keyMatch, 111, 112
 - keyPattern, 110
 - KeyPatternCode, 108
 - mouseMatch, 111
 - mousePattern, 110
 - MousePatternCode, 107
 - QwtEventPattern, 109
 - setKeyPattern, 110
 - setMousePattern, 109, 110
- QwtEventPattern::KeyPattern, 112
- QwtEventPattern::MousePattern, 112
- QwtIntervalData, 113
 - QwtIntervalData, 113
- QwtIntervalData
 - ~QwtIntervalData, 113
 - boundingRect, 114
 - interval, 114
 - QwtIntervalData, 113
 - setData, 114
 - size, 114
 - value, 114
- QwtKnob, 115
 - QwtKnob, 116
- QwtKnob
 - ~QwtKnob, 116
 - borderWidth, 117
 - draw, 118
 - drawKnob, 119
 - drawMarker, 119
 - knobWidth, 116
 - minimumSizeHint, 117
 - paintEvent, 118
 - QwtKnob, 116
 - resizeEvent, 118
 - scaleDraw, 118
 - setBorderWidth, 117
 - setKnobWidth, 116
 - setScaleDraw, 118
 - setSymbol, 117
 - setTotalAngle, 116
 - sizeHint, 117
 - Symbol, 116
 - symbol, 117
 - totalAngle, 117
- QwtLegend, 119
 - QwtLegend, 121
- QwtLegend
 - ~QwtLegend, 121
 - clear, 123
 - contentsWidget, 122
 - displayPolicy, 122
 - eventFilter, 124
 - find, 123
 - heightForWidth, 124
 - horizontalScrollBar, 124
 - identifierMode, 122
 - insert, 122
 - isEmpty, 123
 - itemCount, 124
 - itemMode, 122
 - layoutContents, 125
 - LegendDisplayPolicy, 120
 - LegendItemMode, 121
 - legendItems, 123
 - QwtLegend, 121
 - remove, 123
 - resizeEvent, 124
 - setDisplayPolicy, 122
 - setItemMode, 122
 - sizeHint, 124
 - verticalScrollBar, 124
- QwtLegendItem, 125
 - QwtLegendItem, 127
- QwtLegendItem
 - ~QwtLegendItem, 127
 - checked, 130
 - clicked, 130
 - curvePen, 129
 - drawIdentifier, 129
 - drawItem, 130
 - drawText, 131
 - IdentifierMode, 126
 - identifierMode, 128
 - identifierWidth, 128
 - isChecked, 130
 - isDown, 131
 - itemMode, 127
 - keyPressEvent, 131
 - keyReleaseEvent, 131
 - mousePressEvent, 131
 - mouseReleaseEvent, 131
 - paintEvent, 131
 - pressed, 130

- QwtLegendItem, 127
 - released, 130
 - setChecked, 130
 - setCurvePen, 129
 - setDown, 131
 - setIdentifierMode, 128
 - setIdentifierWidth, 128
 - setItemMode, 127
 - setSpacing, 128
 - setSymbol, 129
 - setText, 127
 - sizeHint, 130
 - spacing, 128
 - symbol, 129
- QwtLegendItemManager, 131
 - QwtLegendItemManager, 132
- QwtLegendItemManager
 - ~QwtLegendItemManager, 132
 - legendItem, 132
 - QwtLegendItemManager, 132
 - updateLegend, 132
- QwtLinearColorMap, 133
 - QwtLinearColorMap, 134
- QwtLinearColorMap
 - ~QwtLinearColorMap, 134
 - addColorStop, 135
 - color1, 136
 - color2, 136
 - colorIndex, 136
 - colorStops, 135
 - copy, 134
 - Mode, 134
 - mode, 135
 - operator=, 134
 - QwtLinearColorMap, 134
 - rgb, 136
 - setColorInterval, 135
 - setMode, 135
- QwtLinearScaleEngine, 137
- QwtLinearScaleEngine
 - align, 138
 - autoScale, 137
 - divideScale, 137
 - transformation, 138
- QwtLog10ScaleEngine, 138
- QwtLog10ScaleEngine
 - autoScale, 139
 - divideScale, 139
 - log10, 140
 - pow10, 140
 - transformation, 140
- QwtMagnifier, 140
 - QwtMagnifier, 141
- QwtMagnifier
 - ~QwtMagnifier, 141
 - eventFilter, 145
 - getMouseButton, 143
 - getZoomInKey, 144
 - getZoomOutKey, 145
 - isEnabled, 142
 - keyFactor, 144
 - mouseFactor, 142
 - parentWidget, 141
 - QwtMagnifier, 141
 - rescale, 145
 - setEnabled, 142
 - setKeyFactor, 144
 - setMouseButton, 142
 - setMouseFactor, 142
 - setWheelButtonState, 143
 - setWheelFactor, 143
 - setZoomInKey, 144
 - setZoomOutKey, 144
 - wheelButtonState, 143
 - wheelFactor, 143
 - widgetKeyPressEvent, 146
 - widgetKeyReleaseEvent, 146
 - widgetMouseMoveEvent, 146
 - widgetMousePressEvent, 145
 - widgetMouseReleaseEvent, 145
 - widgetWheelEvent, 146
- QwtMathMLTextEngine, 147
 - QwtMathMLTextEngine, 147
- QwtMathMLTextEngine
 - ~QwtMathMLTextEngine, 147
 - draw, 148
 - heightForWidth, 148
 - mightRender, 148
 - QwtMathMLTextEngine, 147
 - textMargins, 149
 - textSize, 148
- QwtMetricsMap, 149
- QwtMetricsMap
 - translate, 150
- QwtPainter, 151
- QwtPainter
 - deviceClipping, 152
 - deviceClipRect, 153
 - drawEllipse, 154
 - drawLine, 154
 - drawPie, 154
 - drawPoint, 154
 - drawPolygon, 154
 - drawPolyline, 154
 - drawRect, 153
 - drawRoundFrame, 154
 - drawSimpleRichText, 153
 - drawText, 153

- fillRect, 153
- metricsMap, 152
- resetMetricsMap, 152
- scaledPen, 154
- setClipRect, 153
- setDeviceClipping, 152
- setMetricsMap, 152
- QwtPanner, 155
 - QwtPanner, 156
- QwtPanner
 - ~QwtPanner, 156
 - cursor, 157
 - eventFilter, 158
 - getAbortKey, 157
 - getMouseButton, 157
 - isEnabled, 156
 - isOrientationEnabled, 157
 - moved, 158
 - orientations, 157
 - paintEvent, 159
 - panned, 158
 - QwtPanner, 156
 - setAbortKey, 157
 - setCursor, 157
 - setEnabled, 156
 - setMouseButton, 156
 - setOrientations, 157
 - widgetKeyPressEvent, 159
 - widgetKeyReleaseEvent, 159
 - widgetMouseMoveEvent, 159
 - widgetMousePressEvent, 158
 - widgetMouseReleaseEvent, 158
- QwtPicker, 160
 - QwtPicker, 165
- QwtPicker
 - ~QwtPicker, 165
 - accept, 172
 - append, 172
 - appended, 171
 - begin, 172
 - changed, 172
 - DisplayMode, 164
 - drawRubberBand, 170
 - drawTracker, 170
 - end, 173
 - eventFilter, 169
 - isActive, 169
 - isEnabled, 169
 - move, 173
 - moved, 171
 - parentWidget, 169, 170
 - pickRect, 170
 - QwtPicker, 165
 - RectSelectionType, 163
 - reset, 173
 - ResizeMode, 165
 - resizeMode, 167
 - RubberBand, 164
 - rubberBand, 166
 - rubberBandPen, 168
 - rubberBandWidget, 176
 - selected, 171
 - selection, 170
 - selectionFlags, 166
 - SelectionMode, 164
 - SelectionType, 163
 - setEnabled, 169
 - setResizeMode, 167
 - setRubberBand, 166
 - setRubberBandPen, 167
 - setSelectionFlags, 166
 - setTrackerFont, 168
 - setTrackerMode, 166
 - setTrackerPen, 168
 - stateMachine, 175
 - stretchSelection, 175
 - trackerFont, 168
 - trackerMode, 167
 - trackerPen, 168
 - trackerPosition, 171
 - trackerRect, 171
 - trackerText, 170
 - trackerWidget, 176
 - transition, 172
 - updateDisplay, 176
 - widgetKeyPressEvent, 174
 - widgetKeyReleaseEvent, 175
 - widgetLeaveEvent, 175
 - widgetMouseDoubleClickEvent, 174
 - widgetMouseMoveEvent, 174
 - widgetMousePressEvent, 173
 - widgetMouseReleaseEvent, 174
 - widgetWheelEvent, 174
- QwtPickerClickPointMachine, 176
- QwtPickerClickPointMachine
 - transition, 177
- QwtPickerClickRectMachine, 177
- QwtPickerClickRectMachine
 - transition, 178
- QwtPickerDragPointMachine, 178
- QwtPickerDragPointMachine
 - transition, 178
- QwtPickerDragRectMachine, 178
- QwtPickerDragRectMachine
 - transition, 179
- QwtPickerMachine, 179
 - QwtPickerMachine, 180
- QwtPickerMachine

- ~QwtPickerMachine, 180
- Command, 180
- QwtPickerMachine, 180
- reset, 180
- setState, 181
- state, 180
- transition, 180
- QwtPickerPolygonMachine, 181
- QwtPickerPolygonMachine
 - transition, 181
- QwtPlainTextEngine, 181
 - QwtPlainTextEngine, 182
- QwtPlainTextEngine
 - ~QwtPlainTextEngine, 182
 - draw, 183
 - heightForWidth, 182
 - mightRender, 183
 - QwtPlainTextEngine, 182
 - textMargins, 183
 - textSize, 182
- QwtPlot, 184
 - QwtPlot, 188
- QwtPlot
 - ~QwtPlot, 188
 - autoRefresh, 201
 - autoReplot, 188
 - Axis, 187
 - axisAutoScale, 193
 - axisEnabled, 193
 - axisFont, 194
 - axisMaxMajor, 198
 - axisMaxMinor, 198
 - axisScaleDiv, 195
 - axisScaleDraw, 196
 - axisScaleEngine, 192
 - axisStepSize, 195
 - axisTitle, 197
 - axisValid, 201
 - axisWidget, 196
 - canvas, 190
 - canvasBackground, 191
 - canvasLineWidth, 191
 - canvasMap, 191
 - clear, 201
 - drawCanvas, 200
 - drawItems, 202
 - enableAxis, 193
 - event, 200
 - insertLegend, 198
 - invTransform, 191
 - legend, 199
 - legendChecked, 200
 - legendClicked, 200
 - legendItemChecked, 201
 - legendItemClicked, 201
 - LegendPosition, 187
 - margin, 189
 - minimumSizeHint, 199
 - plotLayout, 189
 - polish, 199
 - print, 188, 189
 - printCanvas, 203
 - printLegend, 203
 - printLegendItem, 202
 - printScale, 203
 - printTitle, 202
 - QwtPlot, 188
 - replot, 201
 - resizeEvent, 202
 - setAutoReplot, 188
 - setAxisAutoScale, 192
 - setAxisFont, 193
 - setAxisLabelAlignment, 197
 - setAxisLabelRotation, 197
 - setAxisMaxMajor, 198
 - setAxisMaxMinor, 198
 - setAxisScale, 194
 - setAxisScaleDiv, 194
 - setAxisScaleDraw, 194
 - setAxisScaleEngine, 192
 - setAxisTitle, 197
 - setCanvasBackground, 191
 - setCanvasLineWidth, 191
 - setMargin, 189
 - setTitle, 190
 - sizeHint, 199
 - title, 190
 - titleLabel, 190
 - transform, 192
 - updateAxes, 200
 - updateLayout, 200
 - updateTabOrder, 202
- QwtPlotCanvas, 204
 - QwtPlotCanvas, 205
- QwtPlotCanvas
 - ~QwtPlotCanvas, 205
 - drawCanvas, 208
 - drawContents, 207
 - drawFocusIndicator, 208
 - FocusIndicator, 205
 - focusIndicator, 206
 - hideEvent, 207
 - invalidatePaintCache, 207
 - PaintAttribute, 205
 - paintCache, 207
 - paintEvent, 207
 - plot, 206
 - QwtPlotCanvas, 205

- replot, 207
- setFocusIndicator, 206
- setPaintAttribute, 206
- testPaintAttribute, 206
- QwtPlotCurve, 208
 - QwtPlotCurve, 212, 213
- QwtPlotCurve
 - ~QwtPlotCurve, 213
 - baseline, 218
 - boundingRect, 216
 - brush, 218
 - closePolyline, 223
 - closestPoint, 215
 - CurveAttribute, 212
 - curveFitter, 219
 - CurveStyle, 211
 - CurveType, 211
 - curveType, 213
 - data, 215, 216
 - dataSize, 216
 - draw, 219, 220
 - drawCurve, 221
 - drawDots, 222
 - drawLines, 221
 - drawSteps, 222
 - drawSticks, 222
 - drawSymbols, 221
 - fillCurve, 223
 - init, 221
 - maxXValue, 217
 - maxYValue, 217
 - minXValue, 216
 - minYValue, 217
 - PaintAttribute, 212
 - pen, 217
 - QwtPlotCurve, 212, 213
 - rtti, 213
 - setBaseline, 218
 - setBrush, 218
 - setCurveAttribute, 217
 - setCurveFitter, 219
 - setCurveType, 213
 - setData, 214, 215
 - setPaintAttribute, 213
 - setPen, 217
 - setRawData, 214
 - setStyle, 218
 - setSymbol, 219
 - style, 219
 - symbol, 219
 - testCurveAttribute, 217
 - testPaintAttribute, 214
 - updateLegend, 220
 - x, 216
 - y, 216
- QwtPlotDict, 223
 - QwtPlotDict, 224
- QwtPlotDict
 - ~QwtPlotDict, 224
 - autoDelete, 225
 - detachItems, 225
 - itemList, 225
 - QwtPlotDict, 224
 - setAutoDelete, 225
- QwtPlotGrid, 225
 - QwtPlotGrid, 226
- QwtPlotGrid
 - ~QwtPlotGrid, 226
 - draw, 230
 - enableX, 227
 - enableXMin, 227
 - enableY, 227
 - enableYMin, 228
 - majPen, 229
 - minPen, 230
 - QwtPlotGrid, 226
 - rtti, 227
 - setMajPen, 229
 - setMinPen, 229
 - setPen, 229
 - setXDiv, 228
 - setYDiv, 229
 - updateScaleDiv, 230
 - xEnabled, 227
 - xMinEnabled, 228
 - xScaleDiv, 228
 - yEnabled, 227
 - yMinEnabled, 228
 - yScaleDiv, 229
- QwtPlotItem, 231
 - QwtPlotItem, 233
- QwtPlotItem
 - ~QwtPlotItem, 233
 - attach, 234
 - boundingRect, 238
 - detach, 234
 - draw, 238
 - hide, 236
 - invTransform, 240
 - isVisible, 237
 - ItemAttribute, 233
 - itemChanged, 238
 - legendItem, 239
 - paintRect, 240
 - plot, 234
 - QwtPlotItem, 233
 - RenderHint, 233
 - rtti, 235

- RttiValues, 233
- scaleRect, 239
- setAxis, 237
- setItemAttribute, 235
- setRenderHint, 235
- setTitle, 234
- setVisible, 237
- setXAxis, 237
- setYAxis, 238
- setZ, 236
- show, 236
- testItemAttribute, 235
- testRenderHint, 236
- title, 234
- transform, 240
- updateLegend, 238
- updateScaleDiv, 239
- xAxis, 237
- yAxis, 238
- z, 236
- QwtPlotItemList
 - qwt_plot_dict.h, 399
- QwtPlotLayout, 241
 - QwtPlotLayout, 243
- QwtPlotLayout
 - ~QwtPlotLayout, 243
 - activate, 246
 - alignCanvasToScales, 244
 - alignLegend, 248
 - alignScales, 248
 - canvasMargin, 243
 - canvasRect, 247
 - expandLineBreaks, 248
 - invalidate, 246
 - layoutLegend, 247
 - legendPosition, 245
 - legendRatio, 246
 - legendRect, 247
 - margin, 243
 - minimumSizeHint, 246
 - Options, 242
 - QwtPlotLayout, 243
 - scaleRect, 247
 - setAlignCanvasToScales, 244
 - setCanvasMargin, 243
 - setLegendPosition, 245
 - setLegendRatio, 246
 - setMargin, 243
 - setSpacing, 244
 - spacing, 245
 - titleRect, 247
- QwtPlotMagnifier, 249
 - QwtPlotMagnifier, 249
- QwtPlotMagnifier
 - ~QwtPlotMagnifier, 249
 - canvas, 250
 - isAxisEnabled, 250
 - plot, 250
 - QwtPlotMagnifier, 249
 - rescale, 250
 - setAxisEnabled, 250
- QwtPlotMarker, 251
 - QwtPlotMarker, 252
- QwtPlotMarker
 - ~QwtPlotMarker, 252
 - boundingRect, 257
 - draw, 256
 - drawAt, 257
 - label, 255
 - labelAlignment, 255
 - labelOrientation, 256
 - linePen, 254
 - LineStyle, 252
 - lineStyle, 253
 - QwtPlotMarker, 252
 - rtti, 253
 - setLabel, 254
 - setLabelAlignment, 255
 - setLabelOrientation, 255
 - setLinePen, 254
 - setLineStyle, 253
 - setSpacing, 256
 - setSymbol, 254
 - setValue, 253
 - setXValue, 253
 - setYValue, 253
 - spacing, 256
 - symbol, 254
 - value, 253
 - xValue, 253
 - yValue, 253
- QwtPlotPanner, 257
 - QwtPlotPanner, 258
- QwtPlotPanner
 - ~QwtPlotPanner, 258
 - canvas, 258
 - isAxisEnabled, 259
 - moveCanvas, 259
 - plot, 258
 - QwtPlotPanner, 258
 - setAxisEnabled, 259
- QwtPlotPicker, 259
 - QwtPlotPicker, 261
- QwtPlotPicker
 - ~QwtPlotPicker, 261
 - append, 265
 - appended, 263
 - canvas, 262

- end, 266
- invTransform, 263, 264
- move, 265
- moved, 263
- plot, 262
- QwtPlotPicker, 261
- scaleRect, 263
- selected, 262, 263
- setAxis, 262
- trackerText, 264, 265
- transform, 264
- xAxis, 262
- yAxis, 262
- QwtPlotPrintFilter, 266
 - QwtPlotPrintFilter, 268
- QwtPlotPrintFilter
 - ~QwtPlotPrintFilter, 268
 - apply, 269
 - color, 268
 - font, 268
 - Item, 267
 - Options, 267
 - options, 268
 - QwtPlotPrintFilter, 268
 - reset, 269
 - setOptions, 268
- QwtPlotRasterItem, 269
 - QwtPlotRasterItem, 271
- QwtPlotRasterItem
 - ~QwtPlotRasterItem, 271
 - alpha, 271
 - CachePolicy, 270
 - cachePolicy, 272
 - draw, 272
 - invalidateCache, 272
 - QwtPlotRasterItem, 271
 - rasterHint, 272
 - renderImage, 272
 - setAlpha, 271
 - setCachePolicy, 271
- QwtPlotRescaler, 273
 - QwtPlotRescaler, 275
- QwtPlotRescaler
 - ~QwtPlotRescaler, 275
 - aspectRatio, 277
 - canvas, 277
 - eventFilter, 278
 - expandingDirection, 276
 - expandInterval, 279
 - expandScale, 278
 - interval, 279
 - isEnabled, 275
 - orientation, 279
 - plot, 278
 - QwtPlotRescaler, 275
 - referenceAxis, 276
 - rescale, 278
 - RescalePolicy, 274
 - rescalePolicy, 275
 - setAspectRatio, 277
 - setEnabled, 275
 - setExpandingDirection, 276
 - setReferenceAxis, 276
 - setRescalePolicy, 275
 - syncScale, 278
 - updateScales, 279
- QwtPlotScaleItem, 280
 - QwtPlotScaleItem, 281
- QwtPlotScaleItem
 - ~QwtPlotScaleItem, 281
 - borderDistance, 284
 - draw, 284
 - font, 282
 - isScaleDivFromAxis, 282
 - palette, 282
 - position, 283
 - QwtPlotScaleItem, 281
 - rtti, 281
 - scaleDiv, 281
 - scaleDraw, 283
 - setAlignment, 284
 - setBorderDistance, 284
 - setFont, 282
 - setPalette, 282
 - setPosition, 283
 - setScaleDiv, 281
 - setScaleDivFromAxis, 282
 - setScaleDraw, 283
 - updateScaleDiv, 285
- QwtPlotSpectrogram, 285
 - QwtPlotSpectrogram, 287
- QwtPlotSpectrogram
 - ~QwtPlotSpectrogram, 287
 - boundingRect, 288
 - colorMap, 288
 - contourLevels, 291
 - contourPen, 289
 - contourRasterSize, 292
 - data, 288
 - defaultContourPen, 289
 - DisplayMode, 286
 - draw, 291
 - drawContourLines, 293
 - QwtPlotSpectrogram, 287
 - rasterHint, 289
 - renderContourLines, 292
 - renderImage, 291
 - rtti, 291

- setColorMap, 288
- setConrecAttribute, 290
- setContourLevels, 290
- setData, 288
- setDefaultContourPen, 289
- setDisplayMode, 287
- testConrecAttribute, 290
- testDisplayMode, 287
- QwtPlotSvgItem, 293
 - QwtPlotSvgItem, 294
- QwtPlotSvgItem
 - ~QwtPlotSvgItem, 294
 - boundingRect, 295
 - draw, 295
 - loadData, 295
 - loadFile, 294
 - QwtPlotSvgItem, 294
 - render, 295
 - rtti, 295
 - viewBox, 296
- QwtPlotZoomer, 296
 - QwtPlotZoomer, 298
- QwtPlotZoomer
 - accept, 303
 - begin, 303
 - end, 303
 - maxStackDepth, 300
 - minZoomSize, 302
 - move, 301
 - moveBy, 301
 - QwtPlotZoomer, 298
 - rescale, 302
 - setAxis, 300
 - setMaxStackDepth, 300
 - setSelectionFlags, 301
 - setZoomBase, 299
 - widgetKeyPressEvent, 303
 - widgetMouseEvent, 302
 - zoom, 301, 302
 - zoomBase, 299
 - zoomed, 302
 - zoomRect, 299
 - zoomRectIndex, 300
 - zoomStack, 300
- QwtPolygonFData, 304
 - QwtPolygonFData, 304
- QwtPolygonFData
 - copy, 304
 - data, 305
 - operator=, 304
 - QwtPolygonFData, 304
 - size, 304
 - x, 305
 - y, 305
- QwtRasterData, 305
 - QwtRasterData, 306
- QwtRasterData
 - ~QwtRasterData, 307
 - boundingRect, 307
 - ConrecAttribute, 306
 - contourLines, 308
 - copy, 307
 - discardRaster, 308
 - initRaster, 307
 - QwtRasterData, 306
 - range, 308
 - rasterHint, 307
 - setBoundingRect, 307
 - value, 308
- QwtRichTextEngine, 309
 - QwtRichTextEngine, 309
- QwtRichTextEngine
 - draw, 310
 - heightForWidth, 309
 - mightRender, 310
 - QwtRichTextEngine, 309
 - textMargins, 310
 - textSize, 309
- QwtRoundScaleDraw, 311
 - QwtRoundScaleDraw, 311
- QwtRoundScaleDraw
 - ~QwtRoundScaleDraw, 312
 - center, 312
 - drawBackbone, 314
 - drawLabel, 314
 - drawTick, 313
 - extent, 313
 - moveCenter, 312
 - operator=, 312
 - QwtRoundScaleDraw, 311
 - radius, 312
 - setAngleRange, 313
 - setRadius, 312
- QwtScaleArithmetic, 314
- QwtScaleArithmetic
 - ceil125, 316
 - ceilEps, 315
 - compareEps, 315
 - divideEps, 315
 - floor125, 316
 - floorEps, 315
- QwtScaleDiv, 316
 - QwtScaleDiv, 317
- QwtScaleDiv
 - contains, 319
 - interval, 318
 - invalidate, 319
 - invert, 320

- isValid, 320
- lowerBound, 318
- operator!=, 318
- operator==, 318
- QwtScaleDiv, 317
- range, 319
- setInterval, 318
- setTicks, 319
- ticks, 319
- TickType, 317
- upperBound, 319
- QwtScaleDraw, 320
 - QwtScaleDraw, 321
- QwtScaleDraw
 - ~QwtScaleDraw, 321
 - Alignment, 321
 - alignment, 324
 - boundingLabelRect, 327
 - drawBackbone, 327
 - drawLabel, 328
 - drawTick, 327
 - extent, 322
 - getBorderDistHint, 322
 - labelAlignment, 325
 - labelMatrix, 327
 - labelPosition, 326
 - labelRect, 326
 - labelRotation, 325
 - labelSize, 326
 - length, 324
 - maxLabelHeight, 326
 - maxLabelWidth, 326
 - minLabelDist, 322
 - minLength, 322
 - move, 323
 - operator=, 322
 - orientation, 324
 - pos, 324
 - QwtScaleDraw, 321
 - setAlignment, 324
 - setLabelAlignment, 324
 - setLabelRotation, 325
 - setLength, 323
- QwtScaleEngine, 328
 - QwtScaleEngine, 330
- QwtScaleEngine
 - ~QwtScaleEngine, 330
 - Attribute, 329
 - attributes, 330
 - autoScale, 332
 - buildInterval, 333
 - contains, 333
 - divideInterval, 333
 - divideScale, 332
 - lowerMargin, 331
 - QwtScaleEngine, 330
 - reference, 331
 - setAttribute, 330
 - setAttributes, 330
 - setMargins, 331
 - setReference, 331
 - strip, 333
 - testAttribute, 330
 - transformation, 332
 - upperMargin, 332
- QwtScaleMap, 334
 - QwtScaleMap, 334
- QwtScaleMap
 - ~QwtScaleMap, 334
 - invTransform, 336
 - operator=, 335
 - p1, 336
 - p2, 336
 - pDist, 337
 - QwtScaleMap, 334
 - s1, 336
 - s2, 336
 - sDist, 337
 - setPaintInterval, 335
 - setPaintXInterval, 335
 - setScaleInterval, 335
 - setTransformation, 335
 - transform, 335
 - transformation, 335
 - xTransform, 336
- QwtScaleTransformation, 337
 - QwtScaleTransformation, 338
- QwtScaleTransformation
 - ~QwtScaleTransformation, 338
 - copy, 338
 - invXForm, 338
 - QwtScaleTransformation, 338
 - type, 338
 - xForm, 338
- QwtScaleWidget, 339
 - QwtScaleWidget, 340
- QwtScaleWidget
 - ~QwtScaleWidget, 340
 - alignment, 346
 - dimForLength, 345
 - draw, 346
 - drawTitle, 345
 - endBorderDist, 342
 - getBorderDistHint, 342
 - getMinBorderDist, 342
 - layoutScale, 346
 - margin, 343
 - minimumSizeHint, 345

- paintEvent, 346
- penWidth, 343
- QwtScaleWidget, 340
- resizeEvent, 346
- scaleChange, 346
- scaleDivChanged, 340
- scaleDraw, 344
- setAlignment, 346
- setBorderDist, 341
- setLabelAlignment, 344
- setLabelRotation, 345
- setMargin, 342
- setMinBorderDist, 342
- setPenWidth, 343
- setScaleDiv, 344
- setScaleDraw, 344
- setSpacing, 343
- setTitle, 340, 341
- sizeHint, 345
- spacing, 343
- startBorderDist, 341
- title, 341
- titleHeightForWidth, 345
- QwtSimpleCompassRose, 347
 - QwtSimpleCompassRose, 347
- QwtSimpleCompassRose
 - draw, 349
 - drawRose, 349
 - numThornLevels, 348
 - numThorns, 348
 - QwtSimpleCompassRose, 347
 - setNumThornLevels, 348
 - setNumThorns, 348
 - setWidth, 348
 - width, 348
- QwtSlider, 349
 - QwtSlider, 352
- QwtSlider
 - BGSTYLE, 351
 - bgStyle, 352
 - borderWidth, 353
 - draw, 355
 - drawSlider, 355
 - drawThumb, 355
 - fontChange, 356
 - getScrollMode, 355
 - getValue, 354
 - layoutSlider, 356
 - minimumSizeHint, 354
 - paintEvent, 355
 - QwtSlider, 352
 - rangeChange, 356
 - resizeEvent, 355
 - scaleChange, 356
 - scaleDraw, 354, 356
 - ScalePos, 351
 - scalePosition, 353
 - setBgStyle, 352
 - setBorderWidth, 353
 - setMargins, 354
 - setOrientation, 352
 - setScaleDraw, 354
 - setScalePosition, 352
 - setThumbLength, 353
 - setThumbWidth, 353
 - sizeHint, 354
 - thumbLength, 353
 - thumbWidth, 353
 - valueChange, 356
 - xyPosition, 356
- QwtSpline, 357
 - QwtSpline, 358
- QwtSpline
 - ~QwtSpline, 358
 - buildNaturalSpline, 360
 - buildPeriodicSpline, 360
 - coefficientsA, 360
 - coefficientsB, 360
 - coefficientsC, 360
 - isValid, 359
 - operator=, 358
 - points, 359
 - QwtSpline, 358
 - reset, 359
 - setPoints, 359
 - setSplineType, 358
 - SplineType, 358
 - splineType, 359
 - value, 360
- QwtSplineCurveFitter, 360
 - QwtSplineCurveFitter, 361
- QwtSplineCurveFitter
 - ~QwtSplineCurveFitter, 361
 - fitCurve, 362
 - fitMode, 361
 - QwtSplineCurveFitter, 361
 - setFitMode, 361
- QwtSymbol, 362
 - QwtSymbol, 364
- QwtSymbol
 - ~QwtSymbol, 364
 - brush, 366
 - clone, 364
 - draw, 366
 - operator!=, 364
 - operator==, 364
 - pen, 366
 - QwtSymbol, 364

- setBrush, 365
- setPen, 365
- setSize, 364
- setStyle, 365
- size, 366
- Style, 363
- style, 366
- QwtText, 367
 - QwtText, 370
- QwtText
 - ~QwtText, 370
 - backgroundBrush, 373
 - backgroundPen, 373
 - color, 372
 - draw, 375
 - font, 371
 - heightForWidth, 374
 - isEmpty, 371
 - isNull, 371
 - LayoutAttribute, 369
 - operator!=, 370
 - operator=, 370
 - operator==, 370
 - PaintAttribute, 369
 - QwtText, 370
 - renderFlags, 372
 - setBackgroundBrush, 373
 - setBackgroundPen, 372
 - setColor, 372
 - setFont, 371
 - setLayoutAttribute, 374
 - setPaintAttribute, 373
 - setRenderFlags, 371
 - setText, 370
 - setTextEngine, 376
 - testLayoutAttribute, 374
 - testPaintAttribute, 374
 - text, 371
 - textEngine, 375
 - TextFormat, 369
 - textSize, 375
 - usedColor, 372
 - usedFont, 371
- QwtTextEngine, 376
 - QwtTextEngine, 377
- QwtTextEngine
 - ~QwtTextEngine, 377
 - draw, 378
 - heightForWidth, 377
 - mightRender, 378
 - QwtTextEngine, 377
 - textMargins, 378
 - textSize, 378
- QwtTextLabel, 379
 - QwtTextLabel, 380
- QwtTextLabel
 - ~QwtTextLabel, 380
 - clear, 381
 - drawContents, 382
 - drawText, 382
 - heightForWidth, 381
 - indent, 381
 - margin, 381
 - minimumSizeHint, 381
 - paintEvent, 382
 - QwtTextLabel, 380
 - setIndent, 381
 - setMargin, 381
 - setText, 380
 - sizeHint, 381
 - text, 381
 - textRect, 382
- QwtThermo, 382
 - QwtThermo, 385
- QwtThermo
 - ~QwtThermo, 385
 - alarmBrush, 387
 - alarmColor, 387
 - alarmEnabled, 388
 - alarmLevel, 387
 - borderWidth, 386
 - draw, 390
 - drawThermo, 390
 - fillBrush, 386
 - fillColor, 386
 - fontChange, 391
 - layoutThermo, 391
 - maxValue, 388
 - minimumSizeHint, 389
 - minValue, 389
 - paintEvent, 391
 - pipeWidth, 388
 - QwtThermo, 385
 - resizeEvent, 391
 - scaleChange, 391
 - scaleDraw, 390, 391
 - scalePosition, 385
 - setAlarmBrush, 387
 - setAlarmColor, 387
 - setAlarmEnabled, 388
 - setAlarmLevel, 387
 - setBorderWidth, 386
 - setFillBrush, 386
 - setFillColor, 386
 - setMargin, 389
 - setMaxValue, 388
 - setMinValue, 388
 - setOrientation, 385

- setPipeWidth, 388
- setRange, 389
- setScaleDraw, 390
- setScalePosition, 385
- setValue, 390
- sizeHint, 389
- value, 389
- QwtWheel, 391
 - QwtWheel, 393
- QwtWheel
 - ~QwtWheel, 393
 - draw, 396
 - drawWheel, 396
 - drawWheelBackground, 396
 - getScrollMode, 397
 - getValue, 397
 - internalBorder, 393
 - layoutWheel, 396
 - mass, 394
 - minimumSizeHint, 395
 - paintEvent, 396
 - paletteChange, 397
 - QwtWheel, 393
 - resizeEvent, 396
 - setColorArray, 396
 - setInternalBorder, 395
 - setMass, 395
 - setOrientation, 393
 - setTickCnt, 394
 - setTotalAngle, 394
 - setViewAngle, 394
 - setWheelWidth, 395
 - sizeHint, 395
 - tickCnt, 393
 - totalAngle, 393
 - valueChange, 396
 - viewAngle, 393
- radius
 - QwtRoundScaleDraw, 312
- range
 - QwtRasterData, 308
 - QwtScaleDiv, 319
- rangeChange
 - QwtCounter, 63
 - QwtDial, 81
 - QwtDoubleRange, 99
 - QwtSlider, 356
- rasterHint
 - QwtPlotRasterItem, 272
 - QwtPlotSpectrogram, 289
 - QwtRasterData, 307
- RectSelectionType
 - QwtPicker, 163
- reference
 - QwtScaleEngine, 331
- referenceAxis
 - QwtPlotRescaler, 276
- released
 - QwtLegendItem, 130
- remove
 - QwtLegend, 123
- render
 - QwtPlotSvgItem, 295
- renderContourLines
 - QwtPlotSpectrogram, 292
- renderFlags
 - QwtText, 372
- RenderHint
 - QwtPlotItem, 233
- renderImage
 - QwtPlotRasterItem, 272
 - QwtPlotSpectrogram, 291
- replot
 - QwtPlot, 201
 - QwtPlotCanvas, 207
- rescale
 - QwtAbstractScale, 16
 - QwtMagnifier, 145
 - QwtPlotMagnifier, 250
 - QwtPlotRescaler, 278
 - QwtPlotZoomer, 302
- RescalePolicy
 - QwtPlotRescaler, 274
- rescalePolicy
 - QwtPlotRescaler, 275
- reset
 - QwtPicker, 173
 - QwtPickerMachine, 180
 - QwtPlotPrintFilter, 269
 - QwtSpline, 359
- resetMetricsMap
 - QwtPainter, 152
- resizeEvent
 - QwtDial, 78
 - QwtKnob, 118
 - QwtLegend, 124
 - QwtPlot, 202
 - QwtScaleWidget, 346
 - QwtSlider, 355
 - QwtThermo, 391
 - QwtWheel, 396
- SizeMode
 - QwtPicker, 165
- resizeMode
 - QwtPicker, 167
- rgb
 - QwtAlphaColorMap, 33

- QwtColorMap, 45
- QwtLinearColorMap, 136
- rose
 - QwtCompass, 47, 48
- rtti
 - QwtPlotCurve, 213
 - QwtPlotGrid, 227
 - QwtPlotItem, 235
 - QwtPlotMarker, 253
 - QwtPlotScaleItem, 281
 - QwtPlotSpectrogram, 291
 - QwtPlotSvgItem, 295
- RttiValues
 - QwtPlotItem, 233
- RubberBand
 - QwtPicker, 164
- rubberBand
 - QwtPicker, 166
- rubberBandPen
 - QwtPicker, 168
- rubberBandWidget
 - QwtPicker, 176
- s1
 - QwtScaleMap, 336
- s2
 - QwtScaleMap, 336
- scaleChange
 - QwtAbstractScale, 16
 - QwtScaleWidget, 346
 - QwtSlider, 356
 - QwtThermo, 391
- ScaleComponent
 - QwtAbstractScaleDraw, 18
- scaleContentsRect
 - QwtDial, 77
- scaleDiv
 - QwtAbstractScaleDraw, 19
 - QwtPlotScaleItem, 281
- scaleDivChanged
 - QwtScaleWidget, 340
- scaledPen
 - QwtPainter, 154
- scaleDraw
 - QwtDial, 77, 78
 - QwtKnob, 118
 - QwtPlotScaleItem, 283
 - QwtScaleWidget, 344
 - QwtSlider, 354, 356
 - QwtThermo, 390, 391
- scaleEngine
 - QwtAbstractScale, 15
- scaleLabel
 - QwtAnalogClock, 36
 - QwtCompass, 49
 - QwtDial, 80
- scaleMap
 - QwtAbstractScale, 15
 - QwtAbstractScaleDraw, 22
- scaleMaxMajor
 - QwtAbstractScale, 15
- scaleMaxMinor
 - QwtAbstractScale, 14
- ScaleOptions
 - QwtDial, 71
- ScalePos
 - QwtSlider, 351
- scalePosition
 - QwtSlider, 353
 - QwtThermo, 385
- scaleRect
 - QwtPlotItem, 239
 - QwtPlotLayout, 247
 - QwtPlotPicker, 263
- ScrollMode
 - QwtAbstractSlider, 25
- sDist
 - QwtScaleMap, 337
- selected
 - QwtPicker, 171
 - QwtPlotPicker, 262, 263
- selection
 - QwtPicker, 170
- selectionFlags
 - QwtPicker, 166
- SelectionMode
 - QwtPicker, 164
- SelectionType
 - QwtPicker, 163
- setAbortKey
 - QwtPanner, 157
- setAbstractScaleDraw
 - QwtAbstractScale, 16
- setAlarmBrush
 - QwtThermo, 387
- setAlarmColor
 - QwtThermo, 387
- setAlarmEnabled
 - QwtThermo, 388
- setAlarmLevel
 - QwtThermo, 387
- setAlignCanvasToScales
 - QwtPlotLayout, 244
- setAlignment
 - QwtPlotScaleItem, 284
 - QwtScaleDraw, 324
 - QwtScaleWidget, 346
- setAlpha

- QwtPlotRasterItem, 271
- setAngleRange
 - QwtRoundScaleDraw, 313
- setAspectRatio
 - QwtPlotRescaler, 277
- setAttribute
 - QwtScaleEngine, 330
- setAttributes
 - QwtScaleEngine, 330
- setAutoDelete
 - QwtPlotDict, 225
- setAutoReplot
 - QwtPlot, 188
- setAutoScale
 - QwtAbstractScale, 14
- setAxis
 - QwtPlotItem, 237
 - QwtPlotPicker, 262
 - QwtPlotZoomer, 300
- setAxisAutoScale
 - QwtPlot, 192
- setAxisEnabled
 - QwtPlotMagnifier, 250
 - QwtPlotPanner, 259
- setAxisFont
 - QwtPlot, 193
- setAxisLabelAlignment
 - QwtPlot, 197
- setAxisLabelRotation
 - QwtPlot, 197
- setAxisMaxMajor
 - QwtPlot, 198
- setAxisMaxMinor
 - QwtPlot, 198
- setAxisScale
 - QwtPlot, 194
- setAxisScaleDiv
 - QwtPlot, 194
- setAxisScaleDraw
 - QwtPlot, 194
- setAxisScaleEngine
 - QwtPlot, 192
- setAxisTitle
 - QwtPlot, 197
- setBackgroundBrush
 - QwtText, 373
- setBackgroundPen
 - QwtText, 372
- setBaseline
 - QwtPlotCurve, 218
- setBgStyle
 - QwtSlider, 352
- setBorderDist
 - QwtScaleWidget, 341
- setBorderDistance
 - QwtPlotScaleItem, 284
- setBorderFlags
 - QwtDoubleInterval, 91
- setBorderWidth
 - QwtKnob, 117
 - QwtSlider, 353
 - QwtThermo, 386
- setBoundingRect
 - QwtRasterData, 307
- setBrush
 - QwtPlotCurve, 218
 - QwtSymbol, 365
- setCachePolicy
 - QwtPlotRasterItem, 271
- setCanvasBackground
 - QwtPlot, 191
- setCanvasLineWidth
 - QwtPlot, 191
- setCanvasMargin
 - QwtPlotLayout, 243
- setChecked
 - QwtLegendItem, 130
- setClipRect
 - QwtPainter, 153
- setColor
 - QwtAlphaColorMap, 32
 - QwtText, 372
- setColorArray
 - QwtWheel, 396
- setColorInterval
 - QwtLinearColorMap, 135
- setColorMap
 - QwtPlotSpectrogram, 288
- setConrecAttribute
 - QwtPlotSpectrogram, 290
- setContourLevels
 - QwtPlotSpectrogram, 290
- setCurrentTime
 - QwtAnalogClock, 36
- setCursor
 - QwtPanner, 157
- setCurveAttribute
 - QwtPlotCurve, 217
- setCurveFitter
 - QwtPlotCurve, 219
- setCurvePen
 - QwtLegendItem, 129
- setCurveType
 - QwtPlotCurve, 213
- setData
 - QwtIntervalData, 114
 - QwtPlotCurve, 214, 215
 - QwtPlotSpectrogram, 288

- setDefaultContourPen
 - QwtPlotSpectrogram, 289
- setDeviceClipping
 - QwtPainter, 152
- setDirection
 - QwtDial, 75
- setDisplayMode
 - QwtPlotSpectrogram, 287
- setDisplayPolicy
 - QwtLegend, 122
- setDown
 - QwtLegendItem, 131
- setEditable
 - QwtCounter, 59
- setEnabled
 - QwtMagnifier, 142
 - QwtPanner, 156
 - QwtPicker, 169
 - QwtPlotRescaler, 275
- setExpandingDirection
 - QwtPlotRescaler, 276
- setExpandingDirections
 - QwtDynGridLayout, 103
- setFillBrush
 - QwtThermo, 386
- setFillColor
 - QwtThermo, 386
- setFitMode
 - QwtSplineCurveFitter, 361
- setFocusIndicator
 - QwtPlotCanvas, 206
- setFont
 - QwtPlotScaleItem, 282
 - QwtText, 371
- setFrameShadow
 - QwtDial, 72
- setGeometry
 - QwtDynGridLayout, 103
- setHand
 - QwtAnalogClock, 35
- setIdentifierMode
 - QwtLegendItem, 128
- setIdentifierWidth
 - QwtLegendItem, 128
- setIncSteps
 - QwtCounter, 59
- setIndent
 - QwtTextLabel, 381
- setInternalBorder
 - QwtWheel, 395
- setInterval
 - QwtDoubleInterval, 90
 - QwtScaleDiv, 318
- setItemAttribute
 - QwtPlotItem, 235
- setItemMode
 - QwtLegend, 122
 - QwtLegendItem, 127
- setKeyFactor
 - QwtMagnifier, 144
- setKeyPattern
 - QwtEventPattern, 110
- setKnobWidth
 - QwtKnob, 116
- setLabel
 - QwtPlotMarker, 254
- setLabelAlignment
 - QwtPlotMarker, 255
 - QwtScaleDraw, 324
 - QwtScaleWidget, 344
- setLabelMap
 - QwtCompass, 48
- setLabelOrientation
 - QwtPlotMarker, 255
- setLabelRotation
 - QwtScaleDraw, 325
 - QwtScaleWidget, 345
- setLayoutAttribute
 - QwtText, 374
- setLegendPosition
 - QwtPlotLayout, 245
- setLegendRatio
 - QwtPlotLayout, 246
- setLength
 - QwtScaleDraw, 323
- setLinePen
 - QwtPlotMarker, 254
- setLineStyle
 - QwtPlotMarker, 253
- setLineWidth
 - QwtDial, 72
- setMajPen
 - QwtPlotGrid, 229
- setMargin
 - QwtPlot, 189
 - QwtPlotLayout, 243
 - QwtScaleWidget, 342
 - QwtTextLabel, 381
 - QwtThermo, 389
- setMargins
 - QwtScaleEngine, 331
 - QwtSlider, 354
- setMass
 - QwtAbstractSlider, 26
 - QwtWheel, 395
- setMaxCols
 - QwtDynGridLayout, 101
- setMaxStackDepth

- QwtPlotZoomer, 300
- setMaxValue
 - QwtCounter, 61
 - QwtDoubleInterval, 92
 - QwtThermo, 388
- setMetricsMap
 - QwtPainter, 152
- setMinBorderDist
 - QwtScaleWidget, 342
- setMinimumExtent
 - QwtAbstractScaleDraw, 21
- setMinPen
 - QwtPlotGrid, 229
- setMinValue
 - QwtCounter, 61
 - QwtDoubleInterval, 92
 - QwtThermo, 388
- setMode
 - QwtDial, 73
 - QwtLinearColorMap, 135
- setMouseButton
 - QwtMagnifier, 142
 - QwtPanner, 156
- setMouseFactor
 - QwtMagnifier, 142
- setMousePattern
 - QwtEventPattern, 109, 110
- setNeedle
 - QwtDial, 76
- setNumButtons
 - QwtCounter, 59
- setNumThornLevels
 - QwtSimpleCompassRose, 348
- setNumThorns
 - QwtSimpleCompassRose, 348
- setOptions
 - QwtPlotPrintFilter, 268
- setOrientation
 - QwtAbstractSlider, 26
 - QwtSlider, 352
 - QwtThermo, 385
 - QwtWheel, 393
- setOrientations
 - QwtPanner, 157
- setOrigin
 - QwtDial, 75
- setPaintAttribute
 - QwtPlotCanvas, 206
 - QwtPlotCurve, 213
 - QwtText, 373
- setPaintInterval
 - QwtScaleMap, 335
- setPaintXInterval
 - QwtScaleMap, 335
- setPalette
 - QwtCompassRose, 53
 - QwtDialNeedle, 83
 - QwtPlotScaleItem, 282
- setPen
 - QwtPlotCurve, 217
 - QwtPlotGrid, 229
 - QwtSymbol, 365
- setPenWidth
 - QwtDialScaleDraw, 84
 - QwtScaleWidget, 343
- setPeriodic
 - QwtDoubleRange, 97
- setPipeWidth
 - QwtThermo, 388
- setPoints
 - QwtSpline, 359
- setPosition
 - QwtAbstractSlider, 29
 - QwtPlotScaleItem, 283
- setRadius
 - QwtRoundScaleDraw, 312
- setRange
 - QwtDoubleRange, 96
 - QwtThermo, 389
- setRawData
 - QwtPlotCurve, 214
- setReadOnly
 - QwtAbstractSlider, 28
- setReference
 - QwtScaleEngine, 331
- setReferenceAxis
 - QwtPlotRescaler, 276
- setRenderFlags
 - QwtText, 371
- setRenderHint
 - QwtPlotItem, 235
- setRescalePolicy
 - QwtPlotRescaler, 275
- setResizeMode
 - QwtPicker, 167
- setRose
 - QwtCompass, 47
- setRubberBand
 - QwtPicker, 166
- setRubberBandPen
 - QwtPicker, 167
- setScale
 - QwtAbstractScale, 13, 14
 - QwtDial, 74
- setScaleArc
 - QwtDial, 74
- setScaleDiv
 - QwtAbstractScaleDraw, 18

- QwtPlotScaleItem, 281
- QwtScaleWidget, 344
- setScaleDivFromAxis
 - QwtPlotScaleItem, 282
- setScaleDraw
 - QwtDial, 77
 - QwtKnob, 118
 - QwtPlotScaleItem, 283
 - QwtScaleWidget, 344
 - QwtSlider, 354
 - QwtThermo, 390
- setScaleEngine
 - QwtAbstractScale, 15
- setScaleInterval
 - QwtScaleMap, 335
- setScaleMaxMajor
 - QwtAbstractScale, 14
- setScaleMaxMinor
 - QwtAbstractScale, 15
- setScaleOptions
 - QwtDial, 74
- setScalePosition
 - QwtSlider, 352
 - QwtThermo, 385
- setScaleTicks
 - QwtDial, 74
- setSelectionFlags
 - QwtPicker, 166
 - QwtPlotZoomer, 301
- setSize
 - QwtSymbol, 364
- setSpacing
 - QwtAbstractScaleDraw, 20
 - QwtLegendItem, 128
 - QwtPlotLayout, 244
 - QwtPlotMarker, 256
 - QwtScaleWidget, 343
- setSplineType
 - QwtSpline, 358
- setState
 - QwtPickerMachine, 181
- setStep
 - QwtCounter, 60
 - QwtDoubleRange, 97
- setStepButton1
 - QwtCounter, 61
- setStepButton2
 - QwtCounter, 61
- setStepButton3
 - QwtCounter, 62
- setStyle
 - QwtPlotCurve, 218
 - QwtSymbol, 365
- setSymbol
 - QwtKnob, 117
 - QwtLegendItem, 129
 - QwtPlotCurve, 219
 - QwtPlotMarker, 254
- setText
 - QwtLegendItem, 127
 - QwtText, 370
 - QwtTextLabel, 380
- setTextEngine
 - QwtText, 376
- setThumbLength
 - QwtSlider, 353
- setThumbWidth
 - QwtSlider, 353
- setTickCnt
 - QwtWheel, 394
- setTickLength
 - QwtAbstractScaleDraw, 19
- setTicks
 - QwtScaleDiv, 319
- setTime
 - QwtAnalogClock, 36
- setTitle
 - QwtPlot, 190
 - QwtPlotItem, 234
 - QwtScaleWidget, 340, 341
- setTotalAngle
 - QwtKnob, 116
 - QwtWheel, 394
- setTrackerFont
 - QwtPicker, 168
- setTrackerMode
 - QwtPicker, 166
- setTrackerPen
 - QwtPicker, 168
- setTracking
 - QwtAbstractSlider, 25
- setTransformation
 - QwtAbstractScaleDraw, 19
 - QwtScaleMap, 335
- setUpdateTime
 - QwtAbstractSlider, 25
- setValid
 - QwtAbstractSlider, 27
 - QwtDoubleRange, 96
- setValue
 - QwtAbstractSlider, 27
 - QwtCounter, 60
 - QwtDoubleRange, 96
 - QwtPlotMarker, 253
 - QwtThermo, 390
- setViewAngle
 - QwtWheel, 394
- setVisible

- QwtPlotItem, 237
- setWheelButtonState
 - QwtMagnifier, 143
- setWheelFactor
 - QwtMagnifier, 143
- setWheelWidth
 - QwtWheel, 395
- setWidth
 - QwtDialSimpleNeedle, 87
 - QwtSimpleCompassRose, 348
- setWrapping
 - QwtDial, 73
- setXAxis
 - QwtPlotItem, 237
- setXDiv
 - QwtPlotGrid, 228
- setXValue
 - QwtPlotMarker, 253
- setYAxis
 - QwtPlotItem, 238
- setYDiv
 - QwtPlotGrid, 229
- setYValue
 - QwtPlotMarker, 253
- setZ
 - QwtPlotItem, 236
- setZoomBase
 - QwtPlotZoomer, 299
- setZoomInKey
 - QwtMagnifier, 144
- setZoomOutKey
 - QwtMagnifier, 144
- Shadow
 - QwtDial, 71
- show
 - QwtPlotItem, 236
- showBackground
 - QwtDial, 72
- size
 - QwtArrayData, 38
 - QwtCPointerData, 64
 - QwtData, 67
 - QwtIntervalData, 114
 - QwtPolygonFData, 304
 - QwtSymbol, 366
- sizeHint
 - QwtArrowButton, 40
 - QwtCounter, 60
 - QwtDial, 77
 - QwtDynGridLayout, 104
 - QwtKnob, 117
 - QwtLegend, 124
 - QwtLegendItem, 130
 - QwtPlot, 199
 - QwtScaleWidget, 345
 - QwtSlider, 354
 - QwtTextLabel, 381
 - QwtThermo, 389
 - QwtWheel, 395
- sliderMoved
 - QwtAbstractSlider, 29
- sliderPressed
 - QwtAbstractSlider, 28
- sliderReleased
 - QwtAbstractSlider, 28
- spacing
 - QwtAbstractScaleDraw, 20
 - QwtLegendItem, 128
 - QwtPlotLayout, 245
 - QwtPlotMarker, 256
 - QwtScaleWidget, 343
- SplineType
 - QwtSpline, 358
- splineType
 - QwtSpline, 359
- startBorderDist
 - QwtScaleWidget, 341
- state
 - QwtPickerMachine, 180
- stateMachine
 - QwtPicker, 175
- step
 - QwtCounter, 60
 - QwtDoubleRange, 97
- stepButton1
 - QwtCounter, 61
- stepButton2
 - QwtCounter, 61
- stepButton3
 - QwtCounter, 62
- stepChange
 - QwtDoubleRange, 99
- stopMoving
 - QwtAbstractSlider, 25
- stretchGrid
 - QwtDynGridLayout, 105
- stretchSelection
 - QwtPicker, 175
- strip
 - QwtScaleEngine, 333
- Style
 - QwtCompassMagnetNeedle, 51
 - QwtCompassWindArrow, 55
 - QwtDialSimpleNeedle, 86
 - QwtSymbol, 363
- style
 - QwtPlotCurve, 219
 - QwtSymbol, 366

- Symbol
 - QwtKnob, 116
- symbol
 - QwtKnob, 117
 - QwtLegendItem, 129
 - QwtPlotCurve, 219
 - QwtPlotMarker, 254
- symmetrize
 - QwtDoubleInterval, 94
- syncScale
 - QwtPlotRescaler, 278
- takeAt
 - QwtDynGridLayout, 102
- testAttribute
 - QwtScaleEngine, 330
- testConrecAttribute
 - QwtPlotSpectrogram, 290
- testCurveAttribute
 - QwtPlotCurve, 217
- testDisplayMode
 - QwtPlotSpectrogram, 287
- testItemAttribute
 - QwtPlotItem, 235
- testLayoutAttribute
 - QwtText, 374
- testPaintAttribute
 - QwtPlotCanvas, 206
 - QwtPlotCurve, 214
 - QwtText, 374
- testRenderHint
 - QwtPlotItem, 236
- text
 - QwtText, 371
 - QwtTextLabel, 381
- textEngine
 - QwtText, 375
- TextFormat
 - QwtText, 369
- textMargins
 - QwtMathMLTextEngine, 149
 - QwtPlainTextEngine, 183
 - QwtRichTextEngine, 310
 - QwtTextEngine, 378
- textRect
 - QwtTextLabel, 382
- textSize
 - QwtMathMLTextEngine, 148
 - QwtPlainTextEngine, 182
 - QwtRichTextEngine, 309
 - QwtText, 375
 - QwtTextEngine, 378
- thumbLength
 - QwtSlider, 353
- thumbWidth
 - QwtSlider, 353
- tickCnt
 - QwtWheel, 393
- tickLabel
 - QwtAbstractScaleDraw, 23
- tickLength
 - QwtAbstractScaleDraw, 20
- ticks
 - QwtScaleDiv, 319
- TickType
 - QwtScaleDiv, 317
- timerEvent
 - QwtAbstractSlider, 29
- title
 - QwtPlot, 190
 - QwtPlotItem, 234
 - QwtScaleWidget, 341
- titleHeightForWidth
 - QwtScaleWidget, 345
- titleLabel
 - QwtPlot, 190
- titleRect
 - QwtPlotLayout, 247
- totalAngle
 - QwtKnob, 117
 - QwtWheel, 393
- trackerFont
 - QwtPicker, 168
- trackerMode
 - QwtPicker, 167
- trackerPen
 - QwtPicker, 168
- trackerPosition
 - QwtPicker, 171
- trackerRect
 - QwtPicker, 171
- trackerText
 - QwtPicker, 170
 - QwtPlotPicker, 264, 265
- trackerWidget
 - QwtPicker, 176
- transform
 - QwtPlot, 192
 - QwtPlotItem, 240
 - QwtPlotPicker, 264
 - QwtScaleMap, 335
- transformation
 - QwtLinearScaleEngine, 138
 - QwtLog10ScaleEngine, 140
 - QwtScaleEngine, 332
 - QwtScaleMap, 335
- transition
 - QwtPicker, 172

- QwtPickerClickPointMachine, 177
- QwtPickerClickRectMachine, 178
- QwtPickerDragPointMachine, 178
- QwtPickerDragRectMachine, 179
- QwtPickerMachine, 180
- QwtPickerPolygonMachine, 181
- translate
 - QwtMetricsMap, 150
- type
 - QwtScaleTransformation, 338
- unite
 - QwtDoubleInterval, 93
- updateAxes
 - QwtPlot, 200
- updateDisplay
 - QwtPicker, 176
- updateLayout
 - QwtPlot, 200
- updateLegend
 - QwtLegendItemManager, 132
 - QwtPlotCurve, 220
 - QwtPlotItem, 238
- updateMask
 - QwtDial, 78
- updateScale
 - QwtDial, 80
- updateScaleDiv
 - QwtPlotGrid, 230
 - QwtPlotItem, 239
 - QwtPlotScaleItem, 285
- updateScales
 - QwtPlotRescaler, 279
- updateTabOrder
 - QwtPlot, 202
- upperBound
 - QwtScaleDiv, 319
- upperMargin
 - QwtScaleEngine, 332
- usedColor
 - QwtText, 372
- usedFont
 - QwtText, 371
- value
 - QwtCounter, 62
 - QwtDoubleRange, 96
 - QwtIntervalData, 114
 - QwtPlotMarker, 253
 - QwtRasterData, 308
 - QwtSpline, 360
 - QwtThermo, 389
- valueChange
 - QwtAbstractSlider, 29
 - QwtDial, 81
 - QwtDoubleRange, 99
 - QwtSlider, 356
 - QwtWheel, 396
- valueChanged
 - QwtAbstractSlider, 28
 - QwtCounter, 62
- verticalScrollBar
 - QwtLegend, 124
- viewAngle
 - QwtWheel, 393
- viewBox
 - QwtPlotSvgItem, 296
- wheelButtonState
 - QwtMagnifier, 143
- wheelEvent
 - QwtAbstractSlider, 30
 - QwtCounter, 62
- wheelFactor
 - QwtMagnifier, 143
- widgetKeyPressEvent
 - QwtMagnifier, 146
 - QwtPanner, 159
 - QwtPicker, 174
 - QwtPlotZoomer, 303
- widgetKeyReleaseEvent
 - QwtMagnifier, 146
 - QwtPanner, 159
 - QwtPicker, 175
- widgetLeaveEvent
 - QwtPicker, 175
- widgetMouseDoubleClickEvent
 - QwtPicker, 174
- widgetMouseMoveEvent
 - QwtMagnifier, 146
 - QwtPanner, 159
 - QwtPicker, 174
- widgetMousePressEvent
 - QwtMagnifier, 145
 - QwtPanner, 158
 - QwtPicker, 173
- widgetMouseReleaseEvent
 - QwtMagnifier, 145
 - QwtPanner, 158
 - QwtPicker, 174
 - QwtPlotZoomer, 302
- widgetWheelEvent
 - QwtMagnifier, 146
 - QwtPicker, 174
- width
 - QwtDialSimpleNeedle, 88
 - QwtDoubleInterval, 92
 - QwtSimpleCompassRose, 348

- wrapping
 - QwtDial, [73](#)
- x
 - QwtArrayData, [38](#)
 - QwtCPointerData, [64](#)
 - QwtData, [67](#)
 - QwtPlotCurve, [216](#)
 - QwtPolygonFData, [305](#)
- xAxis
 - QwtPlotItem, [237](#)
 - QwtPlotPicker, [262](#)
- xData
 - QwtArrayData, [39](#)
 - QwtCPointerData, [65](#)
- xEnabled
 - QwtPlotGrid, [227](#)
- xForm
 - QwtScaleTransformation, [338](#)
- xMinEnabled
 - QwtPlotGrid, [228](#)
- xScaleDiv
 - QwtPlotGrid, [228](#)
- xTransform
 - QwtScaleMap, [336](#)
- xValue
 - QwtPlotMarker, [253](#)
- xyPosition
 - QwtSlider, [356](#)
- y
 - QwtArrayData, [39](#)
 - QwtCPointerData, [65](#)
 - QwtData, [68](#)
 - QwtPlotCurve, [216](#)
 - QwtPolygonFData, [305](#)
- yAxis
 - QwtPlotItem, [238](#)
 - QwtPlotPicker, [262](#)
- yData
 - QwtArrayData, [39](#)
 - QwtCPointerData, [65](#)
- yEnabled
 - QwtPlotGrid, [227](#)
- yMinEnabled
 - QwtPlotGrid, [228](#)
- yScaleDiv
 - QwtPlotGrid, [229](#)
- yValue
 - QwtPlotMarker, [253](#)
- z
 - QwtPlotItem, [236](#)
- zoom
 - QwtPlotZoomer, [301](#), [302](#)
 - zoomBase
 - QwtPlotZoomer, [299](#)
 - zoomed
 - QwtPlotZoomer, [302](#)
 - zoomRect
 - QwtPlotZoomer, [299](#)
 - zoomRectIndex
 - QwtPlotZoomer, [300](#)
 - zoomStack
 - QwtPlotZoomer, [300](#)