

**NAME**

gvmap.sh – pipeline for running gvmap

**SYNOPSIS**

**gvmap.sh** [**-vV?**] [*options*] [**-o** *outfile*] [*files*]

**DESCRIPTION**

**gvmap.sh** takes as input a graph in DOT format, performs a layout, runs the output through gvmap and renders the output. At some point, it is hoped to integrate all of these tasks into gvmap.

**OPTIONS**

The following options are supported:

- a k**     The integer k specifies the average number of artificial points added along the bounding box of the labels. Such artificial points are added to avoid a country boundary cutting through the boundary box of the labels. Computing time is proportional to k; hence, for large graphs, a small value of k is suggested. If k = -1, a suitable value of k is automatically selected based on the graph size. By default k = -1.
- K layout**  
specifies which program should be use for the initial layout. By default, sfdp is run. Also by default, the layout is passed the flag -Goverlap=prism. This can be overridden using a -g flag.
- T format**  
specifies the final output format. This works the same way as the -T flag for any Graphviz layout program.
- N attr=val**  
specifies the setting of a default node attribute during the rendering phase. This works the same way as the -N flag for any Graphviz layout program.
- G attr=val**  
specifies the setting of a graph attribute during the rendering phase. This works the same way as the -G flag for any Graphviz layout program.
- E attr=val**  
specifies the setting of a default edge attribute during the rendering phase. This works the same way as the -E flag for any Graphviz layout program.
- n attr=val**  
specifies the setting of a default node attribute during the layout phase. This works the same way as the -N flag for any Graphviz layout program.
- g attr=val**  
specifies the setting of a graph attribute during the layout phase. This works the same way as the -G flag for any Graphviz layout program.
- e attr=val**  
specifies the setting of a default edge attribute during the layout phase. This works the same way as the -E flag for any Graphviz layout program.
- A flag**  
specifies a flag to be passed to gvmap. For example, gvmap.sh -Ae -As3 causes gvmap -e -s3 to be run.
- v**     Set verbose mode.
- V**     Print version information and exit.
- ?**     Print usage information and exit.

**EXAMPLES**

The following invocation creates a map with edges in semi-transparent light gray and nodes laid out using `sfdp`:

```
gvmap.sh -Ae -Ecolor=#55555522 -Tpng foo.gv > foo.png
```

It is equivalent to running the pipeline

```
sfdp -Goverlap=prism foo.gv | gvmap -e | neato -n2 -Ecolor=#55555522 -Tpng > foo.png
```

**AUTHOR**

Emden R. Gansner <erg@research.att.com>

**SEE ALSO**

`gvmap(1)`, `sfdp(1)`, `neato(1)`, `gvpr(1)`

E. R. Gansner, Y. Hu, S. G. Kobourov, "GMap: Visualizing graphs and clusters as maps," Proc. Pacific Vis. 2010, pp. 201-208.